

IBM Rational Developer for System z  
Version 8.0.3

## *Configuration Guide*





IBM Rational Developer for System z  
Version 8.0.3

## *Configuration Guide*



## Note

Before using this document, read the general information under "Documentation notices for IBM Rational Developer for System z" on page 181.

### Seventh edition (October 2011)

This edition applies to IBM Rational Developer for System z Version 8.0.3 (program number 5724-T07) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications by phone or fax. IBM Software Manufacturing Solutions takes publication orders between 8:30 a.m. and 7:00 p.m. eastern standard time (EST). The phone number is (800) 879-2755. The fax number is (800) 445-9269. Faxes should be sent Attn: Publications, 3rd floor.

You can also order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

IBM welcomes your comments. You can send your comments by mail to the following address:

IBM Corporation  
Attn: Information Development Department 53NA  
Building 501 P.O. Box 12195  
Research Triangle Park NC 27709-2195  
USA

You can fax your comments to: 1-800-227-5088 (US and Canada)

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

Note to U.S. Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© Copyright IBM Corporation 2000, 2011.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>Figures</b>	<b>vii</b>
----------------	------------

<b>Tables</b>	<b>ix</b>
---------------	-----------

<b>About this document</b>	<b>xi</b>
----------------------------	-----------

Who should use this document	xi
Summary of changes	xii
Description of document content	xiii
Planning	xiii
Basic customization	xiv
(Optional) Common Access Repository Manager (CARMA)	xiv
(Optional) SCLM Developer Toolkit	xiv
(Optional) Application Deployment Manager	xiv
(Optional) Other customization tasks	xv
Installation verification	xv
Security definitions	xv
Migration guide	xv
Operator commands	xv
Host configuration reference	xv

<b>Chapter 1. Planning</b>	<b>1</b>
----------------------------	----------

Migration considerations	1
Planning considerations	1
Product overview	1
Skill requirements	2
Time requirements	2
Preinstallation considerations	2
Requisite products	2
Required resources	3
Pre-configuration considerations	6
Workload management	6
Resource usage and system limits	6
Required configuration of requisite products	6
User ID considerations	6
Server considerations	7
Configuration method	8
Predeployment considerations	8
Client checklist	9

<b>Chapter 2. Basic customization</b>	<b>11</b>
---------------------------------------	-----------

Requirements and checklist	11
Customization setup	11
PARMLIB changes	12
Set z/OS UNIX limits in BPXPRMxx	12
Add started tasks to COMMNDxx	13
LPA definitions in LPALSTxx	14
APF authorizations in PROGxx	14
LINKLIST definitions in PROGxx	15
Requisite LINKLIST and LPA definitions	16
LINKLIST definitions for other products	17
PROCLIB changes	17
JES Job Monitor	17
RSE daemon	18

Lock daemon	18
JCL limitations for the PARM variable	19
ELAXF* remote build procedures	20
Security definitions	22
FEJJCNFG, JES Job Monitor configuration file	22
rsed.envvars, RSE configuration file	27
Defining the PORTRANGE available for RSE server	35
Defining extra Java startup parameters with _RSE_JAVAOPTS	36
Defining extra Java startup parameters with _RSE_CMDSERV_OPTS	41
ISPF.conf, ISPF's TSO/ISPF Client Gateway configuration file	42
Optional components	43
Installation verification	43

<b>Chapter 3. (Optional) Common Access Repository Manager (CARMA)</b>	<b>45</b>
---	-----------

Requirements and checklist	45
Select server startup method and active RAM	46
CARMA server startup	46
CRASTART	46
Batch submit	46
(deprecated) TSO/ISPF Client Gateway	46
Production RAMs	46
CA Endeavor SCM RAM	46
CA Endeavor SCM packages RAM	47
Sample RAMs	47
PDS RAM	47
Skeleton RAM	47
SCLM RAM	47
Preconfigured RAM and server startup combinations	47
CRASTART with CA Endeavor SCM RAM	47
Create CARMA VSAM data sets	48
Customize CRASRV.properties	48
Customize crastart.endeavor.conf	48
(Optional) Additional CA Endeavor SCM RAM customization	49
CRASTART with sample RAMs	50
Create CARMA VSAM data sets	50
CARMA	50
Sample RAMs	50
Customize CRASRV.properties	50
Customize crastart.conf	51
Batch submit with CA Endeavor SCM RAM	51
Create CARMA VSAM data sets	52
Customize CRASRV.properties	52
Customize CRASUBCA	52
(Optional) Additional CA Endeavor SCM RAM customization	53
Batch submit with sample RAMs	54
Create VSAM data sets	54
CARMA	54

Sample RAMs . . . . .	54
Customize CRASRV.properties . . . . .	54
Customize CRASUBMT . . . . .	55
CARMA configuration details . . . . .	55
CRASRV.properties, RSE interface to CARMA . . . . .	56
crastart*.conf, CRASTART server startup . . . . .	58
Collecting CRASTART log files . . . . .	60
CRASUB*, batch submit server startup . . . . .	60
CARMA VSAM data sets . . . . .	61
CRADEF, configuration data set . . . . .	62
CRAMSG, message data set . . . . .	62
CRASTRS, custom string data set . . . . .	62
CARMA VSAM migration notes . . . . .	62
CARMA Repository Access Managers (RAMs) . . . . .	63
CA Endeavor SCM RAM . . . . .	63
CA Endeavor SCM packages RAM . . . . .	64
PDS RAM . . . . .	64
Skeleton RAM . . . . .	64
SCLM RAM . . . . .	64
CRASHOW and CRATMAP, CA Endeavor SCM RAM configuration files . . . . .	65
CRASHOW, CA Endeavor SCM RAM default filters . . . . .	65
CRATMAP, CA Endeavor SCM RAM file extension mappings . . . . .	65
CRANDVRA, CA Endeavor SCM RAM allocation exec . . . . .	65
CA Endeavor SCM RAM batch actions . . . . .	66
CRABCFG, CA Endeavor SCM RAM batch-action configuration . . . . .	67
CRABATCA, CA Endeavor SCM RAM batch action JCL . . . . .	68
CARMA return codes . . . . .	68
(Optional) Supporting multiple RAMs . . . . .	69
Example . . . . .	69
(Optional) Custom allocation exec . . . . .	70
(Optional) IRXJCL versus CRAXJCL . . . . .	71
Create CRAXJCL . . . . .	71

## Chapter 4. (Optional) SCLM Developer Toolkit . . . . . 73

Requirements and checklist . . . . .	73
Prerequisites . . . . .	73
ISPF.conf updates for SCLMDT . . . . .	74
rsed.envvars updates for SCLMDT . . . . .	75
(Optional) Long/short name translation . . . . .	75
Create LSTRANS.FILE, the long/short name translation VSAM . . . . .	76
rsed.envvars updates for long/short name translation . . . . .	78
(Optional) Install and customize Ant . . . . .	78
SCLM updates for SCLMDT . . . . .	79
Remove old files from WORKAREA and /tmp . . . . .	80

## Chapter 5. (Optional) Application Deployment Manager . . . . . 81

Requirements and checklist . . . . .	81
CRD repository . . . . .	82
CICS administrative utility . . . . .	82
RESTful versus Web Service . . . . .	83

CRD server using the RESTful interface . . . . .	83
CICS primary connection region . . . . .	83
CICS non-primary connection regions . . . . .	83
(Optional) Customize CRD server transaction IDs . . . . .	84
CRD server using the Web Service interface . . . . .	84
Pipeline message handler . . . . .	85
CICS primary connection region . . . . .	85
CICS non-primary connection regions . . . . .	86
(Optional) Manifest repository . . . . .	86

## Chapter 6. (Optional) Other customization tasks . . . . . 89

(Optional) pushtoclient.properties, Host-based client control . . . . .	89
(Optional) (deprecated) FMIEXT.properties, File Manager integration . . . . .	92
(Optional) ssl.properties, RSE SSL encryption . . . . .	93
(Optional) rsecomm.properties, RSE tracing . . . . .	96
(Optional) DB2 stored procedure . . . . .	97
Workload Manager (WLM) changes . . . . .	97
PROCLIB changes . . . . .	97
DB2 changes . . . . .	98
(Optional) z/OS UNIX subprojects . . . . .	99
REXEC (or SSH) set up . . . . .	100
(Optional) Enterprise Service Tools support . . . . .	100
(Optional) CICS bidirectional language support . . . . .	100
(Optional) Diagnostic IRZ error messages . . . . .	101
(Optional) WORKAREA and /tmp cleanup . . . . .	102

## Chapter 7. Installation verification . . . 103

Verify started tasks . . . . .	103
JMON, JES Job Monitor . . . . .	103
LOCKD, Lock daemon . . . . .	103
RSED, RSE daemon . . . . .	103
IVP operator commands . . . . .	108
PassTicket reusability . . . . .	108
RSE daemon connection . . . . .	109
ISPF Client Gateway . . . . .	109
Verify services . . . . .	110
IVP initialization . . . . .	111
Port availability . . . . .	111
TCP/IP setup . . . . .	112
RSE daemon connection . . . . .	113
JES Job Monitor connection . . . . .	114
Lock daemon connection . . . . .	114
ISPF's TSO/ISPF Client Gateway connection . . . . .	115
(Optional) CARMA connection . . . . .	116
(Optional) SCLMDT connection . . . . .	117

## Chapter 8. Security definitions . . . . . 119

Requirements and checklist . . . . .	119
Activate security settings and classes . . . . .	120
Define an OMVS segment for Developer for System z users . . . . .	122
Define data set profiles . . . . .	122
Define the Developer for System z started tasks . . . . .	126
Define JES command security . . . . .	127
Define RSE as a secure z/OS UNIX server . . . . .	129
Define MVS program controlled libraries for RSE . . . . .	129
Define application protection for RSE . . . . .	130

Define PassTicket support for RSE . . . . .	130	Symbols . . . . .	166
Define z/OS UNIX program controlled files for RSE . . . . .	132	Operands. . . . .	166
Verify security settings . . . . .	132	Syntax example . . . . .	166
		Nonalphanumeric characters and blank spaces . . . . .	166
		Selecting more than one operand. . . . .	167
		Longer than one line . . . . .	167
		Syntax fragments . . . . .	167
<b>Chapter 9. Migration guide. . . . .</b>	<b>135</b>	<b>Appendix. Host Configuration</b>	
Migration considerations . . . . .	135	<b>Reference . . . . .</b>	<b>169</b>
Backing up previously configured files . . . . .	135	Understanding Developer for System z. . . . .	169
Version 8.0.x migration notes . . . . .	136	Security considerations . . . . .	169
Migration from version 7.6 to version 8.0.1 . . . . .	138	TCP/IP considerations . . . . .	169
IBM Rational Developer for System z, FMID HHOP801 . . . . .	138	WLM considerations . . . . .	169
Configurable files . . . . .	140	Tuning considerations . . . . .	169
Sample migration scenarios. . . . .	144	Performance considerations. . . . .	169
Migration from version 7.5 to version 7.6. . . . .	144	Push-to-client considerations . . . . .	170
IBM Rational Developer for System z, FMID HHOP760 . . . . .	144	CICSTS considerations . . . . .	170
Configurable files . . . . .	147	Customizing the TSO environment . . . . .	170
Migration from version 7.1 to version 7.5. . . . .	151	Running multiple instances. . . . .	170
IBM Rational Developer for System z, FMID HHOP750 . . . . .	151	Troubleshooting configuration problems . . . . .	170
Configurable files . . . . .	152	Setting up SSL and X.509 authentication . . . . .	170
		Setting up TCP/IP . . . . .	171
<b>Chapter 10. Operator commands . . . . .</b>	<b>155</b>	<b>Bibliography. . . . .</b>	<b>173</b>
Start (S) . . . . .	155	Referenced publications . . . . .	173
JES Job Monitor . . . . .	155	Informational publications . . . . .	176
RSE daemon. . . . .	155		
Lock daemon . . . . .	156	<b>Glossary . . . . .</b>	<b>177</b>
Modify (F) . . . . .	157		
JES Job Monitor . . . . .	157	<b>Documentation notices for IBM</b>	
RSE daemon. . . . .	158	<b>Rational Developer for System z . . . . .</b>	<b>181</b>
Lock daemon . . . . .	163	Copyright license . . . . .	183
Stop (P) . . . . .	163	Trademark acknowledgments . . . . .	183
Console messages . . . . .	164		
JES Job Monitor . . . . .	164	<b>Index . . . . .</b>	<b>185</b>
RSE daemon, RSE thread pool server, and lock daemon . . . . .	164		
How to read a syntax diagram . . . . .	166		





## Figures

1. JMON - JES Job Monitor started task . . . . .	17	21. CRASUB* - CARMA startup using batch submit . . . . .	61
2. RSED - RSE daemon started task . . . . .	18	22. CRASHOW - CA Endeavor SCM RAM default filters . . . . .	65
3. LOCKD - Lock daemon started task . . . . .	19	23. CRATMAP - CA Endeavor SCM RAM default filters . . . . .	65
4. RSED - alternate RSE daemon startup. . . . .	20	24. CRABCFG - CA Endeavor SCM RAM batch-action configuration. . . . .	67
5. rsed.stdin.sh - alternate RSE daemon startup	20	25. CRABATCA - CA Endeavor SCM RAM batch-action JCL . . . . .	68
6. FEJJCNF, JES Job Monitor configuration file	23	26. ISPF.conf updates for SCLMDT . . . . .	75
7. rsed.envvars - RSE configuration file . . . . .	28	27. rsed.envvars updates for SCLMDT. . . . .	75
8. rsed.envvars - RSE configuration file (continued). . . . .	29	28. FLM02LST - long/short name translation setup JCL . . . . .	77
9. rsed.envvars - RSE configuration file (continued). . . . .	30	29. pushtoclient.properties - Host-based client control configuration file . . . . .	90
10. ISPF.conf - ISPF configuration file . . . . .	42	30. FMIEXT.properties - File Manager configuration file. . . . .	93
11. CRASRV.properties - CRASTART with CA Endeavor SCM RAM. . . . .	48	31. ssl.properties - SSL configuration file . . . . .	94
12. crastart.endeavor.conf - CRASTART with CA Endeavor SCM RAM. . . . .	49	32. rsecomm.properties - Logging configuration file . . . . .	96
13. CRASRV.properties - CRASTART with sample RAMs . . . . .	50	33. ELAXMSAM - DB2 stored procedure task	98
14. crastart.conf - CRASTART with sample RAMs	51	34. ELAXMJCL - DB2 stored procedure definition	99
15. CRASRV.properties - batch submit with CA Endeavor SCM RAM. . . . .	52	35. START JMON operator command. . . . .	155
16. CRASUBCA - batch submit with CA Endeavor SCM RAM. . . . .	53	36. START RSED operator command . . . . .	155
17. CRASRV.properties - batch submit with sample RAMs . . . . .	55	37. START LOCKD operator command . . . . .	156
18. CRASUBMT - batch submit with sample RAMs . . . . .	55	38. MODIFY JMON operator command . . . . .	157
19. CRASRV.properties - CARMA configuration file . . . . .	56	39. MODIFY RSED operator command . . . . .	158
20. crastart*.conf - CARMA server startup using CRASTART . . . . .	59	40. MODIFY LOCKD operator command	163
		41. STOP operator command . . . . .	163



---

## Tables

1. Required resources . . . . .	3	15. SSL certificate storage mechanisms. . . . .	94
2. Optional resources . . . . .	3	16. Valid keystore types. . . . .	95
3. Administrators needed for required tasks	4	17. IVPs for services . . . . .	110
4. Administrators needed for optional tasks	5	18. Security setup variables . . . . .	119
5. Client checklist - mandatory parts . . . . .	9	19. JES2 Job Monitor operator commands	128
6. Client checklist - optional parts . . . . .	10	20. JES3 Job Monitor operator commands	128
7. Sample ELAXF* procedures . . . . .	20	21. Version 8.0.1 customizations . . . . .	141
8. ELAXF* high-level qualifier checklist . . . . .	21	22. Version 7.6 customizations . . . . .	147
9. LIMIT_COMMANDS command permission matrix . . . . .	25	23. Version 7.5 customizations . . . . .	152
10. CARMA return codes . . . . .	68	24. Thread pool error status . . . . .	159
11. SCLM administrator checklist . . . . .	79	25. RSE console messages. . . . .	164
12. Default CRD server transaction IDs . . . . .	84	26. Referenced publications . . . . .	173
13. Default CRD server transaction IDs . . . . .	85	27. Referenced Web sites . . . . .	175
14. Push-to-client group support. . . . .	91	28. Informational publications . . . . .	176



---

## About this document

This document discusses the configuration of the IBM Rational Developer for System z functions. It includes instructions on how to configure IBM Rational Developer for System z Version 8.0.3 on your z/OS<sup>®</sup> host system.

From here on, the following names are used in this manual:

- *IBM Rational Developer for System z* is called *Developer for System z*.
- *Common Access Repository Manager* is abbreviated to *CARMA*.
- *Software Configuration and Library Manager Developer Toolkit* is called *SCLM Developer Toolkit*, abbreviated to *SCLMDT*.
- *z/OS UNIX System Services* is called *z/OS UNIX*.
- *Customer Information Control System Transaction Server* is called *CICSTS*, abbreviated to *CICS*<sup>®</sup>.

For earlier releases, including IBM WebSphere Developer for System z, IBM WebSphere Developer for zSeries and IBM<sup>®</sup> WebSphere Studio Enterprise Developer, use the configuration information found in the Host Configuration Guide and Program Directories for those releases.

This document is part of a set of documents that describe Developer for System z host configuration. Each of these documents has a specific target audience. You are not required to read all documents to complete the Developer for System z configuration.

- *Rational<sup>®</sup> Developer for System z<sup>®</sup> Host Configuration Guide* (SC23-7658) describes in detail all planning tasks, configuration tasks, and options (including optional ones) and provides alternative scenarios.
- *Rational Developer for System z Host Configuration Reference* (SC14-7290) describes Developer for System z design and gives background information for various configuration tasks of Developer for System z, z/OS components, and other products (such as WLM and CICS) related to Developer for System z.
- *Rational Developer for System z Host Configuration Quick Start Guide* (GI11-9201) describes a minimal setup of Developer for System z.
- *Rational Developer for System z Host Configuration Utility* (SC14-7282) describes the Host Configuration Utility, an ISPF panel application that guides you through basic and common optional customization steps for Developer for System z.

The information in this document applies to all Rational Developer for System z Version 8.0.3 packages including IBM Rational Developer for zEnterprise<sup>™</sup>.

---

## Who should use this document

This document is intended for system programmers installing and configuring IBM Rational Developer for System z Version 8.0.3.

This document lists in detail the different steps needed to do a full setup of the product, including some non-default scenarios. Background information that can help you plan and execute the configuration can be found in the *IBM Rational*

*Developer for System z Host Configuration Reference* (SC14-7290). To use this document, you need to be familiar with the z/OS UNIX System Services and MVS™ host systems.

---

## Summary of changes

This section summarizes the changes for *Rational Developer for System z Version 8.0.3 Host Configuration Guide*, SC23-7658-06 (updated October 2011).

Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

This document contains information previously presented in *Rational Developer for System z Version 8.0.1 Host Configuration Guide*, SC23-7658-05.

New information:

- New directives in `rsed.envvars`. See “`rsed.envvars`, RSE configuration file” on page 27.
- Added support for CA Endeavor® SCM background actions. See “CA Endeavor® SCM RAM batch actions” on page 66.
- Added support for CA Endeavor® SCM packages. See “CARMA Repository Access Managers (RAMs)” on page 63.
- New directives in `pushtoclient.properties`. See “(Optional) `pushtoclient.properties`, Host-based client control” on page 89.
- File Manager Integration is deprecated. See “(Optional) (deprecated) `FMIEXT.properties`, File Manager integration” on page 92.
- New and enhanced operator commands. See Chapter 10, “Operator commands,” on page 155.
- Version 8.0.3 migration information. See “Version 8.0.x migration notes” on page 136.
- Version 8.0.1 sample migration scenarios. See “Sample migration scenarios” on page 144.
- New publication, *Rational Developer for System z Messages and Codes* (SC14-7497).

This document contains information previously presented in *Rational Developer for System z Version 7.6.1 Host Configuration Guide*, SC23-7658-04.

New information:

- New directives in `FEJJCNFG`. See “`FEJJCNFG`, JES Job Monitor configuration file” on page 22.
- New directives in `rsed.envvars`. See “`rsed.envvars`, RSE configuration file” on page 27.
- The CARMA chapter has been reorganized, and some new information has been added. See Chapter 3, “(Optional) Common Access Repository Manager (CARMA),” on page 45.
- New configuration file `pushtoclient.properties`. See “(Optional) `pushtoclient.properties`, Host-based client control” on page 89.
- Version 8.0.1 migration information. See “Migrate from version 7.6 to version 8.0.1” on page 138.

Removed information:

- The information previously presented in *Rational Developer for System z Version 7.6.1 Host Configuration Guide* (SC23-7658-04) is now split into 2 documents: *Rational Developer for System z Host Configuration Guide* (SC23-7658) and *Rational Developer for System z Host Configuration Reference* (SC14-7290).
- Information regarding APPC setup has moved to white paper *Using APPC to provide TSO command services* (SC14-7291).
- Information regarding CARMA using ISPF Client Gateway has moved to white paper *Using ISPF Client Gateway to provide CARMA services* (SC14-7292).
- “(Optional) Host based property groups” section in “(Optional) Other customization tasks” (described propertiescfg.properties).
- “(Optional) Host based projects” section in “(Optional) Other customization tasks” (described projectcfg.properties).
- “(Optional) Uneditable characters” section in “(Optional) Other customization tasks” (described uchars.settings).
- “Version 7.6.1 migration notes” section in “Migration guide”.

This document contains information previously presented in *Rational Developer for System z Version 7.6. Host Configuration Guide*, SC23-7658-03.

New information:

- Corrections and additional information presented in *Rational Developer for System z v7.6 Host Configuration Release Notes*<sup>®</sup> are incorporated.
- Version 7.6.1 specific migration notes.
- Added document overview. See “Description of document content.”
- Support for 64-bit Java. See *Rational Developer for System z Prerequisites* (SC23-7659).
- Product configuration through ISPF panels. See “Pre-configuration considerations” on page 6.
- New directives in rsed.envvars. See “rsed.envvars, RSE configuration file” on page 27.
- New proclib members. See “ELAXF\* remote build procedures” on page 20.
- New CARMA VSAM layout. See “CARMA VSAM migration notes” on page 62.
- Supporting multiple CARMA RAMs. See “(Optional) Supporting multiple RAMs” on page 69.
- New Application Deployment Manager options. See “Administrative utility” in the *Host Configuration Reference* (SC14-7290).
- New Application Deployment Manager VSAM layout. See “Administrative utility migration notes” in the *Host Configuration Reference* (SC14-7290).
- New operator commands. See Chapter 10, “Operator commands,” on page 155.
- New console messages. See “Console messages” on page 164.
- Workload Management information. See “WLM considerations” in the *Host Configuration Reference* (SC14-7290).

---

## Description of document content

This section summarizes the information presented in this document.

### Planning

Use the information in this chapter to plan the installation and deployment of Developer for System z.

## Basic customization

The following customization steps are for a basic Developer for System z setup:

- “Customization setup” on page 11
- “PARMLIB changes” on page 12
- “PROCLIB changes” on page 17
- “Security definitions” on page 22
- “FEJCNFG, JES Job Monitor configuration file” on page 22
- “rsed.envvars, RSE configuration file” on page 27
- “ISPF.conf, ISPF's TSO/ISPF Client Gateway configuration file” on page 42

## (Optional) Common Access Repository Manager (CARMA)

Common Access Repository Manager (CARMA) is a server platform for Repository Access Managers (RAMs). A RAM is an Application Programming Interface (API) for a z/OS based Software Configuration Manager (SCM). By wrapping the SCM functionality in a RAM, a single API is available for a client to access any supported SCM.

Developer for System z provides multiple pre-built RAMs, as well as source code examples for creating your own RAM.

The IBM® Rational® Developer for System z Interface for CA Endevor® Software Configuration Manager gives Developer for System z clients direct access to CA Endevor® SCM.

## (Optional) SCLM Developer Toolkit

SCLM Developer Toolkit provides the tools needed to extend the capabilities of SCLM to the client. SCLM itself is a host-based source code manager that is shipped as part of ISPF.

The SCLM Developer Toolkit has an Eclipse-based plug-in that interfaces to SCLM and provides for access to all SCLM processes for legacy code development as well as support for full Java and J2EE development on the workstation with synchronization to SCLM on the mainframe including building, assembling, and deployment of the J2EE code from the mainframe.

## (Optional) Application Deployment Manager

Developer for System z uses certain functions of Application Deployment Manager as a common deployment approach for various components. Optional customization enables more features of Application Deployment Manager and can add the following services to Developer for System z:

- IBM CICS Explorer® provides an Eclipse-based infrastructure to view and manage CICS resources and enables greater integration between CICS tools.
- CICS Resource Definition (CRD) client and server provide the following functions:
  - CICS Resource Definition editor
  - Allow application developers to define CICS resources in a limited, controlled, and secure fashion.
  - Prevent CICS development access to unauthorized or incorrect VSAM data sets by providing the CICS administrator control over the physical data set name attribute in File definitions.
  - Miscellaneous CICS development aids



- Miscellaneous CICS Web Service development aids

## **(Optional) Other customization tasks**

This section combines a variety of optional customization tasks. Follow the instructions in the appropriate section to configure the desired service.

Customizations to Developer for System z configuration files:

- pushtoclient.properties, Host-based client control
- (deprecated) FMIEXT.properties, File Manager integration
- ssl.properties, RSE SSL encryption
- rsecomm.properties, RSE tracing

Developer for System z related customizations to/for other products:

- DB2<sup>®</sup> stored procedure
- Enterprise Service Tools support
- CICS bidirectional language support
- Diagnostic IRZ error messages(Optional) IRZ
- WORKAREA and /tmp cleanup
- Using REXEC (or SSH)

## **Installation verification**

After completing the product customization, you can use the Installation Verification Programs (IVPs) described in this chapter to verify the successful setup of key product components.

## **Security definitions**

This section describes the required and optional security definitions with sample RACF<sup>®</sup> commands.

## **Migration guide**

This section highlights installation and configuration changes compared to previous releases of the product. It also gives some general guidelines to migrate to this release.

## **Operator commands**

This section provides an overview of the available operator (or console) commands for Developer for System z.

## **Host configuration reference**

This section summarizes the information in *IBM Rational Developer for System z Host Configuration Reference* (SC14-7290).



---

## Chapter 1. Planning

Use the information in this chapter, *IBM Rational Developer for System z Prerequisites* (SC23-7659), to plan the installation and deployment of Developer for System z. The following subjects are described:

- “Migration considerations”
- “Planning considerations”
- “Preinstallation considerations” on page 2
- “Pre-configuration considerations” on page 6
- “Predeployment considerations” on page 8
- “Client checklist” on page 9

---

### Migration considerations

Chapter 9, “Migration guide,” on page 135 describes installation and configuration changes compared to previous releases of the product. Use this information to plan your migration to the current release of Developer for System z.

#### Note:

- If you are a previous user of IBM Rational Developer for System z, IBM WebSphere Developer for System z, IBM WebSphere Developer for zSeries or IBM WebSphere Studio Enterprise Developer, it is recommended that you save the related customized files BEFORE installing IBM Rational Developer for System z Version 8.0.3. Refer to Chapter 9, “Migration guide,” on page 135 for an overview of files that required customization.
- Refer to “Running multiple instances” in the *Host Configuration Reference* (SC14-7290), if you plan on running multiple instances of Developer for System z.

---

### Planning considerations

#### Product overview

Developer for System z consists of a client, installed on the user's personal computer, and a server, installed on one or more hosts. This documentation will focus on the host being a z/OS system. However, other operating systems, such as AIX® and Linux on System z, are also supported.

The client provides developers an Eclipse-based development environment that facilitates a uniform graphical interface to the host, and that, among other things, can offload work from the host to the client, saving resources on the host.

The host portion consists of several permanently active tasks and tasks that are started ad-hoc. These tasks allow the client to work with the various components of your z/OS host, such as MVS data sets, TSO commands, z/OS UNIX files and commands, job submit, and job output.

Developer for System z can also interact with subsystems and other application software on the host, such as CICS, Debug Tool, and Software Configuration Managers (SCMs), if Developer for system z is configured to do so, and if these (corequisite) products are available.

Refer to "Understanding Developer for System z" in the *Host Configuration Reference* (SC14-7290) to get a basic understanding of the Developer for System z design.

Refer to the Developer for System z web site, <http://www-01.ibm.com/software/rational/products/developer/systemz/>, or your local IBM representative to learn more about the functionality offered by Developer for System z.

## Skill requirements

Minimal SMP/E skills are needed for a Developer for System z host installation.

The configuration of Developer for System z requires more than the typical system programming permissions and expertise, so assistance from others might be needed. Table 3 on page 4 and Table 4 on page 5 list the administrators needed for the required and optional customization tasks.

## Time requirements

The amount of time required to install and configure the Developer for System z host components depends on various factors, such as:

- the current z/OS UNIX and TCP/IP configuration
- the availability of prerequisite software and maintenance
- whether or not OMVS segments are defined for Developer for System z users
- the availability of a user, who has successfully installed the client, to test the installation and report any problems that might occur

Experience has shown that the installation and configuration process of the Developer for System z host requires from one to four days to complete. This time requirement is for a clean installation performed by an experienced system programmer. If problems are encountered, or if the required skills are not available, then the setup will take longer.

---

## Preinstallation considerations

Refer to *Program Directory for IBM Rational Developer for System z* (GI11-8298) for detailed instructions on the SMP/E installation of the product.

Refer to "Running multiple instances" in the *Host Configuration Reference* (SC14-7290) if you plan on running multiple instances of Developer for System z.

The file system (HFS or zFS) in which Developer for System z is installed must be mounted with the SETUID permission bit on (this is the system default). Mounting the file system with the NOSETUID parameter will prevent Developer for System z from creating the user's security environment, and will fail the connection request of the client.

## Requisite products

*IBM Rational Developer for System z Prerequisites* (SC23-7659) has a list of prerequisite software that must be installed and operational before Developer for System z will work. There is also a list of corequisite software to support specific features of Developer for System z. These requisites must be installed and operational at runtime for the corresponding feature to work as designed.

Plan ahead to have these requisite products available, as it might take some time, depending on the policies at your site. The key requisites for a basic setup are the following:

- z/OS 1.8 or higher
- ISPF APAR OA35689 (TSO/ISPF Client Gateway)
- Java 5.0 or higher

## Required resources

Developer for System z requires the allocation of the systems resources listed in Table 1. The resources listed in Table 2 are required for optional services. Plan ahead to have these resources available, as it might take some time to get them, depending on the policies at your site.

*Table 1. Required resources*

Resource	Default value	Information
APF authorized data set	FEK.SFEKAUTH	"APF authorizations in PROGxx" on page 14
started task	JMON, RSED, and LOCKD	"PROCLIB changes" on page 17
port for host-confined use	6715	"FEJJCNFG, JES Job Monitor configuration file" on page 22
port for host-confined use	4036	"rsed.envvars, RSE configuration file" on page 27
port for client-host communication	4035	"PROCLIB changes" on page 17
port range for client-host communication	any available port is used	"Defining the PORTRANGE available for RSE server" on page 35
z/OS UNIX server security definition	UPDATE permission to BPX.SERVER for RSED started task	"Define RSE as a secure z/OS UNIX server" on page 129
PassTicket security definitions	no default	"Define PassTicket support for RSE" on page 130
MVS build procedures	ELAXF*	"PROCLIB changes" on page 17

*Table 2. Optional resources*

Resource	Default value	Information
LINKLIST data set	FEK.SFEKAUTH and FEK.SFEKLOAD	Chapter 4, "(Optional) SCLM Developer Toolkit," on page 73
LPA data set	FEK.SFEKLPA	Chapter 3, "(Optional) Common Access Repository Manager (CARMA)," on page 45
port range for host-confined use	5227-5326 (100 ports)	Chapter 3, "(Optional) Common Access Repository Manager (CARMA)," on page 45

Table 2. Optional resources (continued)

Resource	Default value	Information
port for client-host communication	5129 for Web Service or 5130 for RESTful	Chapter 5, “(Optional) Application Deployment Manager,” on page 81
CICS CSD update	multiple values	Chapter 5, “(Optional) Application Deployment Manager,” on page 81
CICS JCL update	FEK.SFEKLOAD	<ul style="list-style-type: none"> <li>Chapter 5, “(Optional) Application Deployment Manager,” on page 81</li> <li>“(Optional) CICS bidirectional language support” on page 100</li> </ul>
security definitions	FEK.PTC.* profiles for push-to-client	“Push-to-client considerations” in the <i>Host Configuration Reference</i> (SC14-7290)
LDAP definitions	FEK.PTC.* groups for push-to-client	“Push-to-client considerations” in the <i>Host Configuration Reference</i> (SC14-7290)

The configuration of Developer for System z requires more than the typical system programming permissions and expertise, so minimal assistance from others might be needed. Table 3 and Table 4 on page 5 list the administrators needed for the required and optional customization tasks.

Table 3. Administrators needed for required tasks

Administrator	Task	Information
System	Typical system programmer actions are required for all customization tasks	N/A
Security	<ul style="list-style-type: none"> <li>Define OMVS segment for Developer for System z users</li> <li>Define data set profiles</li> <li>Define started tasks</li> <li>Define operator command security</li> <li>Define z/OS UNIX server profiles</li> <li>Define application security</li> <li>Define PassTicket support</li> <li>Define program controlled data sets</li> <li>Define program controlled z/OS UNIX files</li> </ul>	"Security considerations" in <i>Host Configuration Reference</i> (SC14-7290)
TCP/IP	Define new TCP/IP ports	"TCP/IP considerations" in <i>Host Configuration Reference</i> (SC14-7290)

Table 3. Administrators needed for required tasks (continued)

Administrator	Task	Information
WLM	Assign started task goals to the servers and their child processes	"WLM considerations" in the <i>Host Configuration Reference</i> (SC14-7290).

Table 4. Administrators needed for optional tasks

Administrator	Task	Information
System	Typical system programmer actions are required for all customization tasks	N/A
Security	<ul style="list-style-type: none"> <li>Define data set profiles</li> <li>Define program controlled data sets</li> <li>Define permission to submit xxx* jobs</li> <li>Define CICS transaction security</li> <li>Add certificate for SSL</li> <li>Define X.509 client certificate support</li> <li>Define groups and profiles for push-to-client</li> </ul>	<ul style="list-style-type: none"> <li>"Security considerations" in <i>Host Configuration Reference</i> (SC14-7290)</li> <li>"CICSTS considerations" in the <i>Host Configuration Reference</i> (SC14-7290)</li> <li>"Setting up SSL and X.509 authentication" in the <i>Host Configuration Reference</i> (SC14-7290)</li> <li>"Push-to-client considerations" in the <i>Host Configuration Reference</i> (SC14-7290)</li> </ul>
TCP/IP	Define new TCP/IP ports	"TCP/IP ports" in <i>Host Configuration Reference</i> (SC14-7290)
SCLM	<ul style="list-style-type: none"> <li>Define SCLM language translators for JAVA/J2EE support</li> <li>Define SCLM types for JAVA/J2EE support</li> </ul>	Chapter 4, "(Optional) SCLM Developer Toolkit," on page 73
CICS TS	<ul style="list-style-type: none"> <li>Update CICS region JCL</li> <li>Update CICS region CSD</li> <li>Define CICS group</li> <li>Define CICS transaction names</li> <li>Define a program to CICS</li> </ul>	<ul style="list-style-type: none"> <li>Chapter 5, "(Optional) Application Deployment Manager," on page 81</li> <li>"(Optional) CICS bidirectional language support" on page 100</li> </ul>
DB2	Define a DB2 stored procedure	"(Optional) DB2 stored procedure" on page 97
WLM	<ul style="list-style-type: none"> <li>Assign goals to a DB2 stored procedure</li> <li>Assign goals to Developer for System z tasks</li> </ul>	<ul style="list-style-type: none"> <li>"(Optional) DB2 stored procedure" on page 97</li> <li>"WLM considerations" in the <i>Host Configuration Reference</i> (SC14-7290)</li> </ul>
LDAP	Define groups for push-to-client	"Push-to-client considerations" in the <i>Host Configuration Reference</i> (SC14-7290)

---

## Pre-configuration considerations

Refer to *Host Configuration Reference* (SC14-7290) for information about Developer for System z itself and how it interacts with your system and with the prerequisite and corequisite products. This information can assist you in creating a setup that supports your current needs and future growth.

## Workload management

Unlike traditional z/OS applications, Developer for System z is not a monolithic application that can be identified easily to Workload Manager (WLM). Developer for System z consists of several components that interact to give the client access to the host services and data. Refer to "WLM considerations" in the *Host Configuration Reference* (SC14-7290) to plan your WLM configuration accordingly.

**Note:** Developer for System z consists of multiple tasks that communicate with each other and the client. These tasks use various timers to detect communication loss with their partner or partners. This implies that timeout issues can arise (due to lack of CPU time during the timeout window) on systems with a heavy CPU load or incorrect Workload Management (WLM) settings for Developer for system z.

## Resource usage and system limits

When in use, Developer for System z will use a variable number of system resources like address spaces and z/OS UNIX processes and threads. The availability of these resources is limited by various system definitions. Refer to "Tuning considerations" in the *Host Configuration Reference* (SC14-7290) to estimate the usage of key resources, so you can plan your system configuration accordingly.

## Required configuration of requisite products

Consult your MVS system programmer, security administrator and TCP/IP administrator to check if the requisite products and software are installed, tested, and working. Some requisite customization tasks that are easily overlooked are listed here:

- All Developer for System z users must have READ and EXECUTE access to the Java directories.
- All Developer for System z users must have READ, WRITE and EXECUTE access to the /tmp/ directory (or a directory referenced in the TMPDIR environment variable).
- Remote (host-based) actions for z/OS UNIX subprojects require that z/OS UNIX version of REXEC or SSH is active on the host.

## User ID considerations

The user ID of a Developer for System z user must have (at least) the following attributes:

- TSO access (with a normal region size).

**Note:** A large region size is required for the user ID that executes the Installation Verification Programs (IVPs), because functions requiring a lot of memory (such as Java) will be executed. You should set the region size to 131072 kilobytes (128 megabytes) or higher.

- An OMVS segment defined to the security system (for example, RACF), both for the user ID and its default group.



- The HOME field must refer to a home directory allocated for the user (with READ, WRITE and EXECUTE access).
- The PROGRAM field in the OMVS segment should be /bin/sh or other valid z/OS UNIX shell, such as /bin/tcsh.
- The ASSIZEMAX field should not be set, so that system defaults will be used.
- The user ID does not require UID 0.

Example (command **LISTUSER userid NORACF OMVS**):

```
USER=userid
```

```
OMVS INFORMATION
-----
UID= 0000003200
HOME= /u/userid
PROGRAM= /bin/sh
CPUTIMEMAX= NONE
ASSIZEMAX= NONE
FILEPROCMA= NONE
PROCUSERMA= NONE
THREADSMA= NONE
MMAPAREAMA= NONE
```

- The user ID's default group requires a GID.

Example (command **LISTGRP group NORACF OMVS**):

```
GROUP group
```

```
OMVS INFORMATION
-----
GID= 0000003243
```

- READ and EXECUTE access to the Developer for System z installation and configuration directories and files, default /usr/lpp/rdz/\*, /etc/rdz/\*, and /var/rdz/\*.
- READ, WRITE, and EXECUTE access to the Developer for System z WORKAREA directory, default /var/rdz/WORKAREA.
- READ access to the Developer for System z installation data sets, default FEK.SFEK\*.

## Server considerations

Developer for System z consists of three permanently active servers, which can be started tasks or user jobs. These servers provide the requested services themselves, or start other servers (as z/OS UNIX threads or user jobs) to provide the service.

- JES Job Monitor (JMON) provides all JES-related services.
- Lock Daemon (LOCKD) provides tracking services for data set locks.
- Remote Systems Explorer (RSE) provides core services such as connecting the client to the host and starting other servers for specific services. RSE consists of two logical entities:
  - RSE daemon (RSED), which manages connection setup and which is responsible for running in single server mode.
  - RSE server, which handles individual client request.

JES Job Monitor (JMON) provides all JES related services.

- The security mechanisms used by JES Job Monitor rely on the data sets it resides in being secure. This implies that only trusted system administrators should be able to update the libraries and configuration files.

Remote Systems Explorer (RSE) is the Developer for System z component that provides core services such as connecting the client to the host.

- Since version 7.5, RSE daemon is no longer an INETD managed process but a started task.
- Since version 7.5, RSE server uses a single server model whereas with previous versions, each client-host connection had a private RSE server.
- Different levels of communication security are supported by RSE:
  - External (client-host) communication can be limited to specified ports. This feature is disabled by default.
  - External (client-host) communication can be encrypted using SSL. This feature is disabled by default.
  - Port Of Entry (POE) checking can be used to allow access only to trusted TCP/IP addresses. This feature is disabled by default.
- RSE also supports multiple client authentication methods:
  - User ID and password
  - User ID and one-time password
  - X.509 certificate
- The security mechanisms used by RSE rely on the file system it resides in being secure. This implies that only trusted system administrators should be able to update the libraries and configuration files.

As documented in "TCP/IP ports" in *Host Configuration Reference* (SC14-7290), certain host services, and thus their ports, must be available for the client to connect to, and must be defined to your firewall protecting the host. All other ports used by Developer for System z have host-only traffic. Listed below are the ports needed for external communication in a basic Developer for System z setup.

- RSE daemon for client-host communication setup (using the tcp protocol), default port 4035.
- RSE server for client-host communication (using the tcp protocol). By default, any available port is used, but this can be limited to a specified range.

## Configuration method

Developer for System z provides alternative methods to configure the host side of the product. This gives you a choice of the following methods:

- Using the Host Configuration Utility. This ISPF panel application guides you through the required customization steps and selected optional customization steps. For more information, refer to the *Host Configuration Utility* (SC14-7282).
- Using the *Host Configuration Quick Start Guide*. This guides you through the required customization steps. The scope of this guide is limited to a basic setup.
- Using the *Host Configuration Guide*. This guides you through the required customization steps and all optional customization steps. All configurable options are covered in this guide, including some non-default scenarios

---

## Predeployment considerations

Developer for System z supports cloning an installation to a different system, avoiding the need for a SMP/E installation on each system.

The following data sets, directories, and files are mandatory for deployment to other systems. If you copied a file to a different location, then this file must replace its counterpart in the following lists.

**Note:** The following list does not cover the deployment needs of the pre- and corequisite software.

- FEK.SFEKAUTH(\*)
- FEK.SFEKLOAD(\*)
- FEK.SFEKPROC(\*)
- FEK.#CUST.PARMLIB(\*)
- FEK.#CUST.PROCLIB(\*)
- /usr/lpp/rdz/\*
- /etc/rdz/\*
- /var/rdz/\* (directory structure only)
- optional parts:
  - FEK.SFEKLPA(\*)
  - FEK.#CUST.CNTL(\*)
  - definitions, data sets, files, and directories resulting from customization jobs in FEK.#CUST.JCL

**Note:**

- FEK and /usr/lpp/rdz are the high-level qualifier and path used during the installation of the product. FEK.#CUST, /etc/rdz and /var/rdz are the default locations used during the customization of the product (see “Customization setup” on page 11 for more information).
- You should install Developer for System z in a private file system (HFS or zFS) to easy deploying the z/OS UNIX parts of the product.
- If you cannot use a private file system, you should use an archiving tool such as the z/OS UNIX tar command to transport the z/OS UNIX directories from system to system. This to preserve the attributes (such as program control) for the Developer for System z files and directories.

Refer to *UNIX System Services Command Reference* (SA22-7802) for more information about the following sample commands to archive and restore the Developer for System z installation directory.

- Archive: `cd /SYS1/usr/lpp/rdz; tar -cSf /u/userid/rdz.tar`
- Restore: `cd /SYS2/usr/lpp/rdz; tar -xSf /u/userid/rdz.tar`

---

## Client checklist

Users of the Developer for System z client must know the result of certain host customizations, such as TCP/IP port numbers, for the client to work properly. Use these checklists to gather the information needed.

The checklist in Table 5 lists the required results of mandatory customization steps. Table 6 on page 10 lists the required results of optional customization steps.

*Table 5. Client checklist - mandatory parts*

Customization	Value
RSE daemon TCP/IP port number (default 4035): See “RSE daemon” on page 18.	

Table 6. Client checklist - optional parts

Customization	Value
<p>Location of the ELAXF* procedures if they are not in a system procedure library:</p> <p>See note on JCLLIB in “ELAXF* remote build procedures” on page 20.</p>	
<p>Procedure or step names of the ELAXF* procedures if they were changed:</p> <p>See note on changing them in “ELAXF* remote build procedures” on page 20.</p>	
<p>DB2 stored procedure name (default ELAXMSAM):</p> <p>See information about DB2 stored procedures in "Running multiple instances" in the <i>Host Configuration Reference</i> (SC14-7290).</p>	
<p>Location of the DB2 stored procedure if it is not in a system procedure library:</p> <p>See “(Optional) DB2 stored procedure” on page 97.</p>	
<p>(corequisite) TN3270 port number for Host Connect Emulator (default 23).</p> <p>See "TCP/IP ports" in <i>Host Configuration Reference</i> (SC14-7290).</p>	
<p>(corequisite) REXEC or SSH port number (default 512 or 22, respectively):</p> <p>See “(Optional) z/OS UNIX subprojects” on page 99.</p>	
<p>Application Deployment Manager port number (default 5129 for WebService or 5130 for RESTful)</p> <p>See "TCP/IP ports" in <i>Host Configuration Reference</i> (SC14-7290).</p>	
<p>Location of the CRA#ASLM JCL for CARMA SCLM RAM data set allocations (default FEK.#CUST.JCL):</p> <p>See note on CRA#ASLM in “SCLM RAM” on page 64.</p>	

---

## Chapter 2. Basic customization

The following customization steps are for a basic Developer for System z setup. Refer to the chapters about the optional components for their customization requirements.

---

### Requirements and checklist

You will need the assistance of a security administrator and a TCP/IP administrator to complete this customization task, which requires the following resources and special customization tasks:

- APF authorized data set
- Various PARMLIB updates
- Various security software updates
- Various TCP/IP ports for internal and client-host communication

In order to verify the installation and to start using Developer for System z at your site, you must perform the following tasks. Unless otherwise indicated, all tasks are mandatory.

1. Create customizable copies of samples and create the work environment for Developer for system z. For details, see “Customization setup.”
2. Update z/OS UNIX system limits, start started tasks, define APF authorized and LINKLIST data sets and optionally LPA data sets. For details, see “PARMLIB changes” on page 12.
3. Create started task procedures and compile/link procedures. For details, see “PROCLIB changes” on page 17.
4. Update security definitions. For details, see “Security definitions” on page 22. You must also be aware of and understand how PassTickets are used to establish thread security. See “Using PassTickets” in *Host Configuration Reference* (SC14-7290) for details.
5. Customize Developer for System z configuration files. For details, see:
  - “FEJCNFG, JES Job Monitor configuration file” on page 22
  - “rsed.envvars, RSE configuration file” on page 27
  - “ISPF.conf, ISPF's TSO/ISPF Client Gateway configuration file” on page 42

---

### Customization setup

Developer for System z comes with several sample configuration files and sample JCL. To avoid overwriting your customizations when applying maintenance, you should copy all these members and z/OS UNIX files to a different location and customize the copy.

Some functions of Developer for System z also require the existence of certain directories in z/OS UNIX, which must be created during the customization of the product. To ease the installation effort, a sample job, FEKSETUP, is provided to create the copies and the required directories.

**Note:** The *Rational Developer for System z Host Configuration Utility Guide* (SC14-7282) describes the host configuration using the Host Configuration Utility. The FEKSETUP job and the utility do some of the same tasks, with no way of

checking to see if those tasks have already been performed. Therefore it is possible to undo changes that have already been made. For this reason, you should not use both methods for a single installation.

Customize and submit sample member FEKSETUP in data set FEK.SFEKSAMP to create customizable copies of configuration files and configuration JCL, and to create required z/OS UNIX directories. The required customization steps are described within the member.

This job performs the following tasks:

- Create FEK.#CUST.PARMLIB and populate it with sample configuration files.
- Create FEK.#CUST.PROCLIB and populate it with sample SYS1.PROCLIB members.
- Create FEK.#CUST.JCL and populate it with sample configuration JCL.
- Create FEK.#CUST.CNTL and populate it with sample server startup scripts.
- Create FEK.#CUST.ASM and populate it with sample assembler source code.
- Create FEK.#CUST.COBOL and populate it with sample COBOL source code.
- Create /etc/rdz/\* and populate it with sample configuration files.
- Create /var/rdz/\* as work directories for various Developer for System z functions, and populate it with sample files.

**Note:**

- The configuration steps in this publication use the member/file locations created by the FEKSETUP job, unless noted otherwise. The original samples, which should not be updated, can be found in FEK.SFEKSAMP and /usr/lpp/rdz/samples/.
- Refer to comments in FEK.SFEKSAMP(FEKSETUP) for more details on which sample members are copied to which data set, and for more details on which directories are created, their permission bitmask, and where the various sample files are copied to.
- The comments in FEK.SFEKSAMP(FEKSETUP) also document changes between different versions of Developer for System z to aid in migrating an existing setup.
- If you want to keep all Developer for System z z/OS UNIX files in the same file system (HFS or zFS), but also want the configuration files placed in /etc/rdz, you can use symbolic links to solve this problem. The following sample z/OS UNIX commands create a new directory in the existing file system (/usr/lpp/rdz/cust) and define a symbolic link (/etc/rdz) to it:

```
mkdir /usr/lpp/rdz/cust
ln -s /usr/lpp/rdz/cust /etc/rdz
```

---

## PARMLIB changes

Refer to *MVS Initialization and Tuning Reference* (SA22-7592) for more information about the PARMLIB definitions listed in the next sections. Refer to *MVS System Commands* (SA22-7627) for more information about the sample console commands.

## Set z/OS UNIX limits in BPXPRMxx

Remote Systems Explorer (RSE), which provides core services such as connecting the client to the host, is a z/OS UNIX based process. Therefore it is important to set correct values for the z/OS UNIX system limits in BPXPRMxx, based upon the number of concurrently active Developer for System z users and their average workload.

Refer to "Tuning considerations" in the *Host Configuration Reference* (SC14-7290) for more information about different BPXPRMxx defined limits and their impact on Developer for System z.

MAXASSIZE specifies the maximum address space (process) region size. Set MAXASSIZE in SYS1.PARMLIB(BPXPRMxx) to 2G. This is the maximum value allowed. This is a system-wide limit, and thus active for all z/OS UNIX address spaces. If this is not what you want, then you can set the limit also just for Developer for System z in your security software, as described in "Define the Developer for System z started tasks" on page 126.

MAXTHREADS specifies the maximum number of active threads for a single process. Set MAXTHREADS in SYS1.PARMLIB(BPXPRMxx) to 1500 or higher. This is a system-wide limit, and thus active for all z/OS UNIX address spaces. If this is not what you want, then you can set the limit also just for Developer for System z in your security software, as described in "Define the Developer for System z started tasks" on page 126.

MAXTHREADTASKS specifies the maximum number of active MVS tasks for a single process. Set MAXTHREADTASKS in SYS1.PARMLIB(BPXPRMxx) to 1500 or higher. This is a system-wide limit, and thus active for all z/OS UNIX address spaces. If this is not what you want, then you can set the limit also just for Developer for System z in your security software, as described in "Define the Developer for System z started tasks" on page 126.

MAXPROCUSER specifies the maximum number of processes that a single z/OS UNIX user ID can have concurrently active. Set MAXPROCUSER in SYS1.PARMLIB(BPXPRMxx) to 50 or higher. This setting is intended to be a system-wide limit, as it should be active for each client using Developer for System z.

These values can be checked and set dynamically (until the next IPL) with the following console commands:

- DISPLAY OMVS,0
- SETOMVS MAXASSIZE=2G
- SETOMVS MAXTHREADS=1500
- SETOMVS MAXTHREADTASKS=1500
- SETOMVS MAXPROCUSER=50

**Note:**

- Refer to "Address space size" in the *Host Configuration Reference* (SC14-7290) for more information about other locations where address space sizes can be set or limited.
- The MAXPROCUSER value used above is based upon users having a unique z/OS UNIX user ID (UID). Increase this value if your users share the same UID.
- Ensure that other BPXPRMxx values, such as those for MAXPROCSYS and MAXUIDS, are sufficient to handle the expected amount of concurrently active Developer for System z users. Refer to "Tuning considerations" in the *Host Configuration Reference* (SC14-7290) for more details.

## Add started tasks to COMMNDxx

Add start commands for the Developer for System z RSED, LOCKD, and JMON servers to SYS1.PARMLIB(COMMANDxx) to start them automatically at next system IPL.



After the servers are defined and configured, they can be started dynamically (until the next IPL) with the following console commands:

- S RSED
- S LOCKD
- S JMON

**Note:** The lock daemon should be started before Developer for System z users log on to the RSE daemon. This is so the lock daemon can track the data set lock requests by these users. Therefore you should start the lock daemon at system startup.

## LPA definitions in LPALSTxx

The (optional) Common Access Repository Manager (CARMA) service supports different server startup methods for the CARMA server. The CRASTART startup method requires that module CRASTART in the FEK.SFEKLPA load library is in the Link Pack Area (LPA).

LPA data sets are defined in SYS1.PARMLIB(LPALSTxx).

LPA definitions can be set dynamically (until the next IPL) with the following console command:

- SETPROG LPA,ADD,DSN=FEK.SFEKLPA

**Note:**

- All libraries loaded into LPA are automatically considered to be APF authorized and program controlled. Ensure you have proper security controls in place for these libraries.
- If you choose to not place a library designed for LPA placement in LPA and use LINKLIST or STEPLIB instead, ensure that you define the APF authorization and program control status.

## APF authorizations in PROGxx

In order for JES Job Monitor to access JES spool files, module FEJJMON in the FEK.SFEKAUTH load library and the Language Environment® (LE) runtime libraries (CEE.SCEERUN\*) must be APF authorized.

In order for the (optional) SCLM Developer Toolkit service to work, module BWBTSOW in the FEK.SFEKAUTH load library and the REXX runtime library (REXX.\*.SEAGLPA) must be APF authorized.

In order for ISPF to create the TSO/ISPF Client Gateway, module ISPZTS0 in SYS1.LINKLIB must be APF authorized. The TSO/ISPF Client Gateway is used by Developer for System z's TSO Commands service and SCLM Developer Toolkit.

APF authorizations are defined in SYS1.PARMLIB(PROGxx), if your site followed IBM recommendations.

APF authorizations can be set dynamically (until the next IPL) with the following console commands, where volser is the volume on which the data set resides if it is not SMS managed:

- SETPROG APF,ADD,DSN=FEK.SFEKAUTH,SMS
- SETPROG APF,ADD,DSN=CEE.SCEERUN,VOL=volser
- SETPROG APF,ADD,DSN=CEE.SCEERUN2,VOL=volser



- SETPROG APF,ADD,DSN=REXX.V1R4M0.SEAGLPA,VOL=volser
- SETPROG APF,ADD,DSN=SYS1.LINKLIB,VOL=volser

**Note:**

- When you use the Alternate Library for REXX product package, the default REXX runtime library name is REXX.\*.SEAGALT, instead of REXX.\*.SEAGLPA as used in the preceding sample.
- LPA libraries, such as REXX.\*.SEAGLPA, are automatically APF authorized when located in LPA, and thus do not require explicit definitions.
- Some of the corequisite products, such as IBM Debug Tool, also require APF authorization. Refer to the related product customization guides for more information about this.

## LINKLIST definitions in PROGxx

LINKLIST definitions for Developer for System z can be grouped in three categories:

- Developer for System z load libraries needed for Developer for System z functions. These definitions are described in this section.
- Requisite load libraries needed for Developer for System z functions. These definitions are described in “Requisite LINKLIST and LPA definitions” on page 16.
- Developer for System z load libraries needed by other products. These definitions are described in “LINKLIST definitions for other products” on page 17.

In order for the (optional) SCLM Developer Toolkit service to work, all BWB\* modules in the FEK.SFEKAUTH and FEK.SFEKLOAD load libraries must be made available either through STEPLIB or LINKLIST.

If you opt to use STEPLIB, you must define the libraries not available through LINKLIST in the STEPLIB directive of rsed.envvars, the RSE configuration file. Be aware, however, that:

- using STEPLIB in z/OS UNIX has a negative performance impact.
- If one STEPLIB library is APF authorized, then all must be authorized. Libraries lose their APF authorization when they are mixed with non-authorized libraries in STEPLIB.
- Libraries added to the STEPLIB DD in a JCL are not propagated to the z/OS UNIX processes started by the JCL.

LINKLIST data sets are defined in SYS1.PARMLIB(PROGxx), if your site followed IBM recommendations.

The required definitions will look like the following, where listname is the name of the LINKLIST set that will be activated, and volser is the volume on which the data set resides if it is not cataloged in the master catalog:

- LNKLST ADD NAME(listname) DSNNAME(FEK.SFEKAUTH) VOLUME(volser)
- LNKLST ADD NAME(listname) DSNNAME(FEK.SFEKLOAD)

LINKLIST definitions can be created dynamically (until the next IPL) with the following group of console commands, where listname is the name of the current LINKLIST set, and volser is the volume on which the data set resides if it is not cataloged in the master catalog:

1. LNKLIST DEFINE,NAME=LLTMP,COPYFROM=CURRENT
2. LNKLIST ADD NAME=LLTMP,DSN=FEK.SFEKAUTH,VOL=volser
3. LNKLIST ADD NAME=LLTMP,DSN=FEK.SFEKLOAD
4. LNKLIST ACTIVATE,NAME=LLTMP

## Requisite LINKLIST and LPA definitions

Remote Systems Explorer (RSE) is a z/OS UNIX process that requires access to MVS load libraries. The following (prerequisite) libraries must be made available, either through STEPLIB or LINKLIST/LPALIB:

- System load library
  - SYS1.LINKLIB
- Language Environment runtime
  - CEE.SCEERUN
  - CEE.SCEERUN2
- C++'s DLL class library
  - CBC.SCLBDLL
- ISPF's TSO/ISPF Client Gateway
  - ISP.SISPLoad
  - ISP.SISPLPA

The following additional libraries must be made available, either through STEPLIB or LINKLIST/LPALIB, to support the use of optional services. This list does not include data sets that are specific to a product that Developer for System z interacts with, such as IBM Debug Tool:

- REXX runtime library (for SCLM Developer Toolkit)
  - REXX.\*.SEAGLPA
- System load library (for SSL encryption)
  - SYS1.SIEALNKE

### Note:

- When you use the Alternate Library for REXX product package, the default REXX runtime library name is REXX.\*.SEAGALT, instead of REXX.\*.SEAGLPA as used in the preceding sample.
- All libraries loaded into LPA are automatically considered to be APF authorized and program controlled. Ensure you have proper security controls in place for these libraries.
- Libraries that are designed for LPA placement, such as REXX.\*.SEAGLPA, might require additional program control or APF authorizations if they are accessed through LINKLIST or STEPLIB.
- Some of the corequisite products, such as IBM Debug Tool, also require STEPLIB or LINKLIST/LPALIB definitions. Refer to the related product customization guides for more information about this.

LINKLIST data sets are defined in SYS1.PARMLIB(PROGxx), if your site followed IBM recommendations. LPA data sets are defined in SYS1.PARMLIB(LPALSTxx).

If you opt to use STEPLIB, you must define the libraries not available through LINKLIST/LPALIB in the STEPLIB directive of rsed.envvars, the RSE configuration file. Be aware, however, that:

- Using STEPLIB in z/OS UNIX has a negative performance impact.

- If one STEPLIB library is APF authorized, then all must be authorized. Libraries lose their APF authorization when they are mixed with non-authorized libraries in STEPLIB.
- Libraries added to the STEPLIB DD in a JCL are not propagated to the z/OS UNIX processes started by the JCL.

## LINKLIST definitions for other products

The Developer for System z client has a code generation component called Enterprise Service Tools. In order for the generated code to issue diagnostic error messages, all IRZM\* and IIRZ\* modules in the FEK.SFEKLOAD load library must be made available either through STEPLIB or LINKLIST.

LINKLIST data sets are defined in SYS1.PARMLIB(PROGxx), if your site followed IBM recommendations.

If you opt to use STEPLIB, you must define the libraries not available through LINKLIST in the STEPLIB directive of the task that executes the code (IMS<sup>™</sup> or batch job). However, be aware of the following:

- If one STEPLIB library is APF authorized, then all must be authorized. Libraries lose their APF authorization when they are mixed with non-authorized libraries in STEPLIB.

---

## PROCLIB changes

The started task and remote build procedures listed in the following sections must reside in a system procedure library defined to your JES subsystem. In the instructions found in the following sections,, the IBM default procedure library, SYS1.PROCLIB, is used.

## JES Job Monitor

Customize the sample started task member FEK.#CUST.PROCLIB(JMON), as described within the member, and copy it to SYS1.PROCLIB. As shown in the following code sample, you have to provide this information:

- The high-level qualifier of the (authorized) load library, default FEK
- The JES Job Monitor configuration file, default FEK.#CUST.PARMLIB(FEJJCNFG)

```

/*
/* JES JOB MONITOR
/*
//JMON      PROC PRM=,                * PRM='-TV' TO START TRACING
//          LEPRM='RPTOPTS(ON)',
//          HLQ=FEK,
//          CFG=FEK.#CUST.PARMLIB(FEJJCNFG)
/*
//JMON      EXEC PGM=FEJJMON,REGION=0M,TIME=NOLIMIT,
//          PARM=('&LEPRM,ENVAR("_CEE_ENVFILE_S=DD:ENVIRON")/&PRM')
//STEPLIB   DD DISP=SHR,DSN=&HLQ..SFEKAUTH
//ENVIRON   DD DISP=SHR,DSN=&CFG
//SYSPRINT  DD SYSOUT=*
//SYSOUT    DD SYSOUT=*
//          PEND
/*

```

*Figure 1. JMON - JES Job Monitor started task*

**Note:**

- Refer to Chapter 10, “Operator commands,” on page 155 for more information about the startup parameters.
- The sample JCL is initially shipped as FEK.SFEKSAMP(FEJJJCL) and is renamed to FEK.#CUST.PROCLIB(JMON) in “Customization setup” on page 11.
- Tracing can also be controlled by console commands, as described in Chapter 10, “Operator commands,” on page 155.
- See “WLM considerations” in the *Host Configuration Reference* (SC14-7290) for the advised Workload Manager (WLM) goals for this task.

## RSE daemon

Customize the sample started task member FEK.#CUST.PROCLIB(RSED), as described within the member, and copy it to SYS1.PROCLIB. As shown in the following code sample, you have to provide this information:

- The home directory where Developer for System z is installed, default /usr/lpp/rdz.
- The location of the configuration files, default /etc/rdz

```
//*
//* RSE DAEMON
//*
//RSED      PROC TMPDIR=,
//          PORT=,
//          IVP=,                * 'IVP' to do an IVP test
//          CNFG='/etc/rdz',
//          HOME='/usr/lpp/rdz'
//*
//RSED      EXEC PGM=BPXBATSL,REGION=0M,TIME=NOLIMIT,
// PARM='PGM &HOME./bin/rsed.sh &IVP -C&CNFG -P&PORT -T&TMPDIR'
//STDOUT    DD SYSOUT=*
//STDERR    DD SYSOUT=*
//          PEND
//*
```

Figure 2. RSED - RSE daemon started task

### Note:

- Refer to Chapter 10, “Operator commands,” on page 155 for more information about the startup parameters.
- The sample JCL is initially shipped as FEK.SFEKSAMP(FEKRSED) and is renamed to FEK.#CUST.PROCLIB(RSED) in “Customization setup” on page 11.
- Limit the length of the job name to 7 characters or less. The **modify** and **stop** operator commands will fail with message “IEE342I MODIFY REJECTED-TASK BUSY” if an 8 character name is used. This behavior is caused by the z/OS UNIX design for child processes.
- See “WLM considerations” in the *Host Configuration Reference* (SC14-7290) for the advised Workload Manager (WLM) goals for this task and the child processes it creates. The child processes have the same name as the parent task, RSED, appended with a random 1-digit number, for example RSED8.

## Lock daemon

Customize the sample started task member FEK.#CUST.PROCLIB(LOCKD), as described within the member, and copy it to SYS1.PROCLIB. As shown in the following code sample, you have to provide this information:

- The home directory where Developer for System z is installed, default /usr/lpp/rdz.

- The location of the configuration files, default /etc/rdz.

```

/**
/** LOCK DAEMON
/**
//LOCKD    PROC TMPDIR=,
//          LOG=,
//          CNFG='/etc/rdz',
//          HOME='/usr/lpp/rdz'
/**
//LOCKD    EXEC PGM=BPXBATSL,REGION=0M,TIME=NOLIMIT,
//          PARM='PGM &HOME./bin/lockd.sh -C&CNFG -L&LOG -T&TMPDIR'
//STDOUT    DD SYSOUT=*
//STDERR    DD SYSOUT=*
//          PEND
/**

```

Figure 3. LOCKD - Lock daemon started task

**Note:**

- Refer to Chapter 10, “Operator commands,” on page 155 for more information about the startup parameters.
- The sample JCL is initially shipped as FEK.SFEKSAMP(FEKLOCKD) and is renamed to FEK.#CUST.PROCLIB(LOCKD) in “Customization setup” on page 11.
- See “WLM considerations” in the *Host Configuration Reference* (SC14-7290) for the advised Workload Manager (WLM) goals for this task.

## JCL limitations for the PARM variable

The maximum length for the PARM variable is 100 characters, which might cause problems if you use custom directory names. To bypass this problem, you can either:

- Use default values

The `rsed.sh` and `lockd.sh` startup scripts can be invoked without arguments, in which case the default argument values will be used.

- Use symbolic links

Symbolic links can be used as shorthand for a long directory name. The following sample z/OS UNIX command defines a symbolic link (/usr/lpp/rdz) to another directory (/long/directory/name/usr/lpp/rdz).

```
ln -s /long/directory/name/usr/lpp/rdz /usr/lpp/rdz
```

- Use STDIN

When the PARM field is empty, **BPXBATCH** will start a z/OS UNIX shell and execute the shell script that is provided by STDIN. Note that STDIN must be a z/OS UNIX file (allocated as ORDONLY) and that using STDIN disables the usage of PROC variables like TMPDIR. Also note that the shell will execute the shell logon scripts /etc/profile and \$HOME/.profile.

To use this method, you must first update the startup JCL to match something like the following sample:

```

/**
/** RSE DAEMON - USING STDIN
/**
//RSED      PROC CNFG='/etc/rdz'
/**
//RSE      EXEC PGM=BPXBATCH,REGION=0M,TIME=NOLIMIT
//STDOUT    DD SYSOUT=*
//STDERR    DD SYSOUT=*
//STDIN     DD PATHOPTS=(ORDONLY),PATH='&CNFG./rsed.stdin.sh'
//          PEND
/**

```

Figure 4. RSED - alternate RSE daemon startup

Second, you must create the shell script (/etc/rdz/rsed.stdin.sh in this example) that will start the RSE daemon. The content of this script will look like the following sample:

```

CNFG=/etc/rdz
PORT=
TMPDIR=
IVP=
/long/directory/name/usr/lpp/rdz/bin/rsed.sh $IVP -C$CNFG -P$PORT -T$TMPDIR

```

Figure 5. rsed.stdin.sh - alternate RSE daemon startup

**Note:** When using this method, the RSE daemon itself will not be active in the RSED address space. The RSE daemon will be active in a RSEDx address space. This because z/OS UNIX runs child processes (such as starting a shell) in separate address spaces. Adding a STDENV DD with a \_BPX\_SHAREAS=YES directive does not change this, as it is interpreted too late. This side effect severely complicates using Developer for System z operator commands.

## ELAXF\* remote build procedures

Developer for System z provides sample JCL procedures that can be used for the JCL generation, remote project builds, and remote syntax check features of CICS BMS maps, IMS MFS screens, COBOL, PL/I, Assembler, and C/C++ programs. These procedures allow installations to apply their own standards, and ensure that developers use the same procedures with the same compiler options and compiler levels.

The sample procedures and their function are listed in Table 7.

Table 7. Sample ELAXF\* procedures

Member	Purpose
ELAXFADT	Sample procedure for assembling and debugging High Level assembler programs.
ELAXFASM	Sample procedure for assembling High Level assembler programs.
ELAXFBMS	Sample procedure for creating CICS BMS object and corresponding copy, dsect, or include member.
ELAXFCOC	Sample procedure for doing COBOL Compiles, Integrated CICS translate and integrated DB2 translate.
ELAXFCOP	Sample procedure for doing DB2 preprocess of EXEC SQL statements embedded in COBOL programs.
ELAXFCOT	Sample procedure for doing CICS translation for EXEC CICS statements embedded in COBOL programs.
ELAXFCPC	Sample procedure for doing C compiles.

Table 7. Sample ELAXF\* procedures (continued)

Member	Purpose
ELAXFCPP	Sample procedure for doing C++ compiles.
ELAXFCP1	Sample procedure for COBOL compiles with SCM preprocessor statements (-INC and ++INCLUDE).
ELAXFDCL	Sample procedure for running a program in TSO mode.
ELAXFGO	Sample procedure for the GO step.
ELAXFLNK	Sample procedure for linking C/C++, COBOL, PLI and High Level Assembler programs.
ELAXFMFS	Sample procedure for creating IMS MFS screens.
ELAXFPLP	Sample procedure for doing DB2 preprocess of EXEC SQL statements embedded in PLI programs.
ELAXFPLT	Sample procedure for doing CICS translation of EXEC CICS statements embedded in PLI programs.
ELAXFPL1	Sample procedure for doing PL/I compiles, integrated CICS translate and integrated DB2 translate.
ELAXFPP1	Sample procedure for PL/I compiles with SCM preprocessor statements (-INC and ++INCLUDE).
ELAXFTSO	Sample procedure for running/debugging generated DB2 code in TSO mode.
ELAXFUOP	Sample procedure for generating the UOPT step when building programs that run in CICS or IMS subsystems.

The names of the procedures and the names of the steps in the procedures match the default properties that are shipped with the Developer for System z client. If you decide to change the name of a procedure or the name of a step in a procedure, the corresponding properties file on all the clients should also be updated. You should not change the procedure and step names.

Customize the sample build procedure members, FEK.#CUST.PROCLIB(ELAXF\*), as described within the members, and copy them to SYS1.PROCLIB. You have to provide the correct high-level qualifiers for different product libraries, as described in Table 8.

Table 8. ELAXF\* high-level qualifier checklist

Product	Default HLQ	Value
Developer for System z	FEK	
CICS	CICSTS32.CICS	
DB2	DSN910	
IMS	IMS	
COBOL	IGY.V4R1M0	
PL/I	IBMZ.V3R8M0	
C/C++	CBC	
LE	CEE	
system LINKLIB	SYS1	
system MACLIB	SYS1	



If the ELAXF\* procedures cannot be copied into a system procedure library, ask the Developer for System z users to add a JCLLIB card (right after the JOB card) to the job properties on the client.

```
//MYJOB    JOB <job parameters>
//PROCS    JCLLIB ORDER=(FEK.#CUST.PROCLIB)
```

---

## Security definitions

Customize and submit sample member FEKRACF to create the security definitions for Developer for System z. The user submitting this job must have security administrator privileges, such as being RACF SPECIAL.

FEKRACF is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

### Note:

- For those sites that use CA ACF2™ for z/OS, please refer to your product page on the CA support site (<https://support.ca.com>) and check for the related Developer for System z Knowledge Document, TEC492389. This Knowledge Document has details on the security commands necessary to properly configure Developer for System z.
- For those sites that use CA Top Secret® for z/OS, please refer to your product page on the CA support site (<https://support.ca.com>) and check for the related Developer for System z Knowledge Document, TEC492091. This Knowledge Document has details on the security commands necessary to properly configure Developer for System z.

The following list of security-related definitions for Developer for System z are discussed in detail in Chapter 8, “Security definitions,” on page 119.

- Activate security settings and classes
- Define an OMVS segment for Developer for System z users
- Define data set profiles
- Define the JMON, RSED, and LOCKD started tasks
- Define JES command security
- Define RSE as a secure z/OS UNIX server
- Define MVS program controlled libraries for RSE
- Define application security for RSE
- Define PassTicket support for RSE
- Define z/OS UNIX program controlled files for RSE

**Note:** The sample FEKRACF job holds more than just RACF commands. The last step of the security definitions consists of making a z/OS UNIX file program controlled. Depending on the policies at your site, this might be a task for the system programmer and not the security administrator.

**Attention:** The client connection request will fail if PassTickets are not set up correctly.

---

## FEJJCNFG, JES Job Monitor configuration file

JES Job Monitor (JMON) provides all JES-related services. The behavior of JES Job Monitor can be controlled with the definitions in FEJJCNFG.



FEJJC�FG is located in FEK.#CUST.PARMLIB, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

Customize the sample JES Job Monitor configuration member FEJJC�FG, as shown in the following sample. Comment lines start with a pound sign (#), when using a US code page. Data lines can only have a directive and its assigned value. Comments are not allowed on the same line.

**Note:** The JMON started task must be restarted to pick up any changes you make.

```
SERV_PORT=6715
TZ=EST5EDT
#_BPXK_SETIBMOPT_TRANSPORT=TCPIP
#APPLID=FEKAPPL
#AUTHMETHOD=SAF
#CODEPAGE=UTF-8
#CONCHAR=$
#CONSOLE_NAME=JMON
#GEN_CONSOLE_NAME=OFF
#HOST_CODEPAGE=IBM-1047
#LIMIT_COMMANDS=NOLIMIT
#LIMIT_VIEW=USERID
#LISTEN_QUEUE_LENGTH=5
#MAX_DATASETS=32
#MAX_THREADS=200
#TIMEOUT=3600
#TIMEOUT_INTERVAL=1200
#SUBMIT_TIMEOUT=30
#SUBMITMETHOD=TSO
#TSO_TEMPLATE=FEK.#CUST.CNTL(FEJTS0)
```

Figure 6. FEJJC�FG, JES Job Monitor configuration file

## SERV\_PORT

The port number for JES Job Monitor host server. The default port is 6715. The port can be changed if desired.

### Note:

- This value must match the port number set for JES Job Monitor in the `rsed.envvars` configuration file. If these values differ, RSE cannot connect the client to JES Job Monitor. Refer to “`rsed.envvars`, RSE configuration file” on page 27 to learn how to define the variable for RSE.
- Before selecting a port, verify that the port is available on your system with the TSO commands **NETSTAT** and **NETSTAT PORTL**.
- When using a version 7.1 or higher client, all communication on this port is confined to your z/OS host machine.

**TZ** Time zone selector. The default is EST5EDT. The default time zone is UTC +5 hours (Eastern Standard Time (EST) Eastern Daylight Savings Time (EDT)). Change this to represent your time zone. Additional information can be found in the *UNIX System Services Command Reference* (SA22-7802).

The following definitions are optional. If omitted, default values will be used as specified below:

## \_BPXK\_SETIBMOPT\_TRANSPORT

Specifies the name of the TCPIP stack to be used. The default is TCPIP.

Uncomment and change to the requested TCPIP stack name, as defined in the TCPIPJOBNAME statement in the related TCPIP.DATA.

**Note:**

- Coding a SYSTCPD DD statement in the server JCL does not set the requested stack affinity.
- When this directive is not active, JES Job Monitor binds to every available stack on the system (BIND INADDRANY).

**APPLID**

Specifies the application identifier used for identifying JES Job Monitor to your security software. The default is FEKAPPL. Uncomment and change to the desired application ID.

**Note:** This value must match the application ID set for RSE in the rsed.envvars configuration file. If these values differ, RSE cannot connect the client to JES Job Monitor. Refer to “rsed.envvars, RSE configuration file” on page 27 to learn how to define the variable for RSE.

**AUTHMETHOD**

The default is SAF, which means that the System Authorization Facility (SAF) security interface is used. Do not change unless directed to do so by the IBM support center.

**CODEPAGE**

The workstation codepage. The default is UTF-8. The workstation codepage is set to UTF-8 and generally should not be changed. You might need to uncomment the directive and change UTF-8 to match the workstation's codepage if you have difficulty with NLS characters, such as the currency symbol.

**CONCHAR**

Specifies the JES console command character. CONCHAR defaults to CONCHAR=\$ for JES2, or CONCHAR=\* for JES3. Uncomment and change to the requested command character.

**CONSOLE\_NAME**

Specifies the name of the EMCS console used for issuing commands against jobs (Hold, Release, Cancel, and Purge). The default is JMON. Uncomment and change to the desired console name, using the following guidelines.

- CONSOLE\_NAME must be either a console name consisting of 2 to 8 alphanumeric characters, or '&SYSUID' (without quotes).
- If a console name is specified, a single console by that name is used for all users. If the console by that name happens to be in use, then the command issued by the client will fail.
- If &SYSUID is specified, the client user ID is used as the console name. Thus a different console is used for each user. If the console by that name happens to be in use (for example, the user is using the SDSF ULOG), then the command issued by the client might fail, depending on the GEN\_CONSOLE\_NAME setting.

No matter which console name is used, the user ID of the client requesting the command is used as the LU of the console, leaving a trace in syslog messages IEA630I and IEA631.

```
IEA630I OPERATOR console NOW ACTIVE,   SYSTEM=sysid, LU=id
IEA631I OPERATOR console NOW INACTIVE, SYSTEM=sysid, LU=id
```

## GEN\_CONSOLE\_NAME

Enables or disables automatic generating of alternative console names. The default is OFF. Uncomment and change to ON to enable alternative console names.

This directive is only used when CONSOLE\_NAME equals &SYSUID and the user ID is not available as console name.

If GEN\_CONSOLE\_NAME=ON, an alternative console name is generated by appending a single numeric digit to the user ID. The digits 0 through 9 are attempted. If no available console is found, the command issued by the client fails.

If GEN\_CONSOLE\_NAME=OFF, the command issued by the client fails.

**Note:** The only valid settings are ON and OFF.

## HOST\_CODEPAGE

The host codepage. The default is IBM-1047. Uncomment and change to match your host codepage.

From version 7.6.1 on, Developer for System z clients ignore the HOST\_CODEPAGE value specified here and use the codepage specified locally in the properties of the “MVS Files” subsystem.

**Note:** Even for recent clients, JES Job Monitor will use the host codepage specified in HOST\_CODEPAGE during initial client communication setup.

## LIMIT\_COMMANDS

Defines against which jobs the user can issue selected JES commands (Show JCL, Hold, Release, Cancel, and Purge). The default (LIMIT\_COMMANDS=USERID) limits the commands to jobs owned by the user. Uncomment this directive and specify LIMITED or NOLIMIT to allow the user to issue commands against all spool files, if permitted by your security product.

Table 9. LIMIT\_COMMANDS command permission matrix

LIMIT_COMMANDS	Job owner	
	User	Other
USERID (default)	Allowed	Not allowed
LIMITED	Allowed	Allowed only if explicitly permitted by security profiles
NOLIMIT	Allowed	Allowed if permitted by security profiles or when the JESSPOOL class is not active

**Note:** The only valid settings are USERID, LIMITED, and NOLIMIT.

## LIMIT\_VIEW

Defines what output the user can view. The default (LIMIT\_VIEW=NOLIMIT) allows the user to view all JES output, if permitted by your security product. Uncomment this directive and specify USERID to limit the view to output owned by the user.

**Note:** The only valid settings are USERID and NOLIMIT.

**LISTEN\_QUEUE\_LENGTH**

The TCP/IP listen queue length. The default is 5. Do not change unless directed to do so by the IBM support center.

**MAX\_DATASETS**

The maximum number of spooled output data sets that JES Job Monitor will return to the client (for example, SYSOUT, SYSPRINT, SYS00001, and so on). The default is 32. The maximum value is 2147483647.

**MAX\_THREADS**

Maximum number of users that can be using one JES Job Monitor at a time. The default is 200. The maximum value is 2147483647. Increasing this number might require you to increase the size of the JES Job Monitor address space.

**TIMEOUT**

The length of time, in seconds, before a thread is killed due to lack of interaction with the client. The default is 3600 (1 hour). The maximum value is 2147483647. TIMEOUT=0 disables the function.

**TIMEOUT\_INTERVAL**

The number of seconds between timeout checks. The default is 1200. The maximum value is 2147483647.

**SUBMIT\_TIMEOUT**

The number of seconds that Developer for System z will wait for the completion of the TSO\_TEMPLATE job. The default is 30. The maximum value is 2147483647. Note: SUBMIT\_TIMEOUT has no effect unless SUBMITMETHOD=TSO is also specified.

**SUBMITMETHOD=TSO**

Submit jobs through TSO. The default (SUBMITMETHOD=JES) submits jobs directly into JES. Uncomment this directive and specify TSO to submit the job through TSO **SUBMIT** command. This method allows TSO exits to be invoked; however, it has a performance drawback and for that reason it is not recommended.

**Note:**

- The only valid settings are TSO and JES.
- If SUBMITMETHOD=TSO is specified, then TSO\_TEMPLATE must also be defined.

**TSO\_TEMPLATE**

Wrapper JCL for submitting the job through TSO. The default value is FEK.#CUST.CNTL(FEJTSO). This statement refers to the fully qualified member name of the JCL to be used as a wrapper for the TSO **SUBMIT** command. See the SUBMITMETHOD statement for more information.

**Note:**

- A sample wrapper job is provided in FEK.#CUST.CNTL(FEJTSO). Refer to this member for more information about the customization needed.
- TSO\_TEMPLATE has no effect unless SUBMITMETHOD=TSO is also specified.

---

## rsed.envvars, RSE configuration file

The RSE lock daemon and the RSE server processes (RSE daemon, RSE thread pool, and RSE server) use the definitions in `rsed.envvars`. Optional Developer for System z and third-party services can use this configuration file also to define environment variables for their use.

Remote Systems Explorer (RSE) provides core services such as connecting the client to the host and starting other servers for specific services. Lock daemon provides tracking services for data set locks.

`rsed.envvars` is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job `FEK.SFEKSAMP(FEKSETUP)`. See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

See the following sample `rsed.envvars` file, which must be customized to match your system environment. Comment lines start with a pound sign (`#`), when using a US code page. Data lines can only have a directive and its assigned value, comments are not allowed on the same line. Line continuations and spaces around the equal sign (`=`) are not supported.

**Note:** The RSED and LOCKD started tasks must be restarted to pick up any changes you make.

```

#=====
# (1) required definitions
JAVA_HOME=/usr/lpp/java/J5.0
RSE_HOME=/usr/lpp/rdz
_RSE_RSED_PORT=4035
_RSE_LOCKD_PORT=4036
_RSE_JMON_PORT=6715
_RSE_HOST_CODEPAGE=IBM-1047
TZ=EST5EDT
LANG=C
PATH=/bin:/usr/sbin
_CEE_DMPARG=/tmp
STEPLIB=NONE
#STEPLIB=$STEPLIB:CEE.SCEERUN:CEE.SCEERUN2:CBC.SCLBDLL
_RSE_JAVAOPTS=""
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Xms1m -Xmx256m"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Ddaemon.log=/var/rdz/logs"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Duser.log=/var/rdz/logs"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_LOG_DIRECTORY="
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dmaximum.clients=60"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dmaximum.threads=1000"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dminimum.threadpool.process=1"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dmaximum.threadpool.process=100"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dipv6=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dkeep.last.log=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Denable.standard.log=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Denable.port.of.entry=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Denable.certificate.mapping=false"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Denable.automount=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Denable.audit.log=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Daudit.cycle=30"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Daudit.action=<user_exit>"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Daudit.action.id=<userid>"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Daudit.retention.period=0"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Daudit.log.mode=RW.R."
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Ddeny.nonzero.port=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dsingle.logon=false"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dprocess.cleanup.interval=0"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DCPP_CLEANUP_INTERVAL=60000"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DAPPLID=FEKAPPL"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDENY_PASSWORD_SAVE=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DHIDE_ZOS_UNIX=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDISABLE_DELETE_IN_SUBPROJECT=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_IDLE_SHUTDOWN_TIMEOUT=3600000"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_TCP_NO_DELAY=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_TRACING_ON=true"
#_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_MEMLOGGING_ON=true"
#=====
# (2) required definitions for TSO/ISPF Client Gateway
_CMDSERV_BASE_HOME=/usr/lpp/ispf
_CMDSERV_CONF_HOME=/etc/rdz
_CMDSERV_WORK_HOME=/var/rdz
#STEPLIB=$STEPLIB:ISP.SISPLPA:SYS1.LINKLIB
_RSE_CMDSERV_OPTS=""
#_RSE_CMDSERV_OPTS="$_RSE_CMDSERV_OPTS&ISPPROF=&SYSUID..ISPPROF"
#=====
# (3) required definitions for SCLM Developer Toolkit
_SCLMDT_CONF_HOME=/var/rdz/sclmdt
#STEPLIB=$STEPLIB:FEK.SFEKAUTH:FEK.SFEKLOAD
#_SCLMDT_TRANTABLE=FEK.#CUST.LSTRANS.FILE
#ANT_HOME=/usr/lpp/Apache/Ant/apache-ant-1.7.1
#=====

```

Figure 7. rsed.envvars - RSE configuration file

```

# (4) optional definitions
# RSE_PORTRANGE=8108-8118
# BPXK_SETIBMOPT_TRANSPORT=TCPIP
#TMPDIR=/tmp
# RSE_FEK_SAF_CLASS=FACILITY
#_RSE_LDAP_SERVER=ldap_server_url
#_RSE_LDAP_PORT=389
| #_RSE_LDAP_PTC_GROUP_SUFFIX="o=PTC,c=DeveloperForZ"
#GSK_CRL_SECURITY_LEVEL=HIGH
#GSK_LDAP_SERVER=ldap_server_url
#GSK_LDAP_PORT=ldap_server_port
#GSK_LDAP_USER=ldap_userid
#GSK_LDAP_PASSWORD=ldap_server_password
#=====
# (5) do not change unless directed by IBM support center
_RSE_SAF_CLASS=/usr/include/java_classes/IRRRacf.jar
_CEE_RUNOPTS="ALL31(ON) HEAP(32M,32K,ANYWHERE,KEEP,,) TRAP(ON)"
_BPX_SHAREAS=YES
_BPX_SPAWN_SCRIPT=YES
_EDC_ADD_ERRNO2=1
JAVA_PROPAGATE=NO
RSE_LIB=$RSE_HOME/lib
PATH=.:$JAVA_HOME/bin:$RSE_HOME/bin:$CMDSEV_BASE_HOME/bin:$PATH
LIBPATH=$JAVA_HOME/bin:$JAVA_HOME/bin/classic:$RSE_LIB:$RSE_LIB/icuc
LIBPATH=.:/usr/lib:$LIBPATH
CLASSPATH=$RSE_LIB:$RSE_LIB/dstore_core.jar:$RSE_LIB/clientserver.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/dstore_extra_server.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/zosserver.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/dstore_miners.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/universalminers.jar:$RSE_LIB/mvsminers.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/carma.jar:$RSE_LIB/luceneminer.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/mvsluceneminer.jar:$RSE_LIB/cdzminer.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/mvscdzminer.jar:$RSE_LIB/jesminers.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/FAMiner.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/mvsutil.jar:$RSE_LIB/jesutils.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/lucene-core-2.3.2.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/cdtparser.jar
CLASSPATH=$CLASSPATH:$RSE_LIB/wdzbidi.jar:$RSE_LIB/fmiExtensions.jar
CLASSPATH=$CLASSPATH:$_RSE_SAF_CLASS
CLASSPATH=.:$CLASSPATH
|_RSE_PTC=$_RSE_LDAP_PTC_GROUP_SUFFIX
_RSE_CMDSEV_OPTS="&SESSION=SPAWN$_RSE_CMDSEV_OPTS"
|_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dldap.server.address=$_RSE_LDAP_SERVER"
|_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dldap.server.port=$_RSE_LDAP_PORT"
|_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dldap.ptc.group.name.suffix=$_RSE_PTC"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DISPF_OPTS='$_RSE_CMDSEV_OPTS'"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DA_PLUGIN_PATH=$RSE_LIB"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Xbootclasspath/p:$RSE_LIB/bidiTools.jar"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dfile.encoding=$_RSE_HOST_CODEPAGE"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dconsole.encoding=$_RSE_HOST_CODEPAGE"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_SPIRIT_ON=true"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DSPIRIT_EXPIRY_TIME=6"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DSPIRIT_INTERVAL_TIME=6"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dcom.ibm.cacheLocalHost=true"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Duser.home=$HOME"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dclient.username=$_RSE_USER_ID"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dlow.heap.usage.ratio=15"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Dmaximum.heap.usage.ratio=40"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_KEEPALIVE_ENABLED=true"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_KEEPALIVE_RESPONSE_TIMEOUT=60000"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_IO_SOCKET_READ_TIMEOUT=180000"
_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DRSECOMM_LOGFILE_MAX=0"

```

Figure 8. rsed.envvars - RSE configuration file (continued)



```

_RSE_JAVAOPTS="$ _RSE_JAVAOPTS -Djob.monitor.port=$_RSE_JMON_PORT"
_RSE_JAVAOPTS="$ _RSE_JAVAOPTS -Dlock.daemon.port=$_RSE_LOCKD_PORT"
_RSE_JAVAOPTS="$ _RSE_JAVAOPTS -Dlock.daemon.cleanup.interval=1440"
_RSE_JAVAOPTS="$ _RSE_JAVAOPTS -showversion"
_RSE_SERVER_CLASS=org.eclipse.dstore.core.server.Server
_RSE_DAEMON_CLASS=com.ibm.etools.zos.server.RseDaemon
_RSE_POOL_SERVER_CLASS=com.ibm.etools.zos.server.ThreadPoolProcess
_RSE_LOCKD_CLASS=com.ibm.ftt.rse.mvs.server.miners.MVSLockDaemon
_RSE_SERVER_TIMEOUT=120000
_SCLMDT_BASE_HOME=$_RSE_HOME
_SCLMDT_WORK_HOME=$_CMDSERV_WORK_HOME
CGI_DTWORK=$__SCLMDT_WORK_HOME
CGI_ISPCONF=$_CMDSERV_CONF_HOME
CGI_ISPWORK=$_CMDSERV_WORK_HOME
#=====
# (6) additional environment variables

```

Figure 9. *rse.d.envvars* - RSE configuration file (continued)

**Note:** Symbolic links are allowed when specifying directories in *rse.d.envvars*.

The following definitions are required:

#### **JAVA\_HOME**

Java home directory. The default is /usr/lpp/java/J5.0. Change to match your Java installation.

#### **RSE\_HOME**

RSE home directory. The default is /usr/lpp/rdz. Change to match your Developer for System z installation.

#### **\_RSE\_RSED\_PORT**

RSE daemon port number. The default is 4035. Can be changed if desired.

#### **Note:**

- Before selecting a port, verify that the port is available on your system with the TSO commands NETSTAT and NETSTAT PORTL.
- This port is used for client-host communication.
- The RSED started task can override the port number specified here.

#### **\_RSE\_LOCKD\_PORT**

RSE lock daemon port number. The default is 4036. Can be changed if desired.

#### **Note:**

- Before selecting a port, verify that the port is available on your system with the TSO commands NETSTAT and NETSTAT PORTL.
- All communication on this port is confined to your z/OS host machine.

#### **\_RSE\_JMON\_PORT**

JES Job Monitor port number. The default is 6715. Can be changed if desired.

#### **Note:**

- This value must match the port number set for JES Job Monitor in the FEJJCNFG configuration file. If these values differ, RSE cannot connect the client to JES Job Monitor. Refer to “FEJJCNFG, JES Job Monitor configuration file” on page 22 to learn how to define the variable for JES Job Monitor.



- Before selecting a port, verify that the port is available on your system with the TSO commands **NETSTAT** and **NETSTAT PORTL**.
- All communication on this port is confined to your z/OS host machine.

#### **RSE\_HOST\_CODEPAGE**

The host codepage. The default is IBM-1047. Change to match your host codepage.

**TZ** Time zone selector. The default is EST5EDT. The default time zone is UTC +5 hours (Eastern Standard Time (EST) Eastern Daylight Savings Time (EDT)). Change to match your time zone.

Additional information can be found in the *UNIX System Services Command Reference* (SA22-7802).

#### **LANG**

Specifies the name of the default locale. The default is C. C specifies the POSIX locale and (for example) Ja\_JP specifies the Japanese locale. Change to match your locale.

**PATH** Command path. The default is /bin:/usr/sbin:.. Can be changed if desired.

#### **CEE\_DMPTARG**

Language Environment (LE) z/OS UNIX dump location used by the Java Virtual Machine (JVM). The default is /tmp.

#### **STEPLIB**

Access MVS data sets not in LINKLIST/LPALIB. The default is NONE.

You can bypass the need of having (prerequisite) libraries in LINKLIST/LPALIB by uncommenting and customizing one or more of the following STEPLIB directives. Refer to “PARMLIB changes” on page 12 for more information about the usage of the libraries listed below:

```
STEPLIB=$STEPLIB:CEE.SCEERUN:CEE.SCEERUN2:CBC.SCLBDLL
STEPLIB=$STEPLIB:ISP.SISPLoad:ISP.SISPLPA:SYS1.LINKLIB
STEPLIB=$STEPLIB:FEK.SFEKAUTH:FEK.SFEKLOAD
```

#### **Note:**

- Using STEPLIB in z/OS UNIX has a negative performance impact.
- If one STEPLIB library is APF authorized, then all must be authorized. Libraries lose their APF authorization when they are mixed with non-authorized libraries in STEPLIB.
- Libraries that are designed for LPA placement might require additional program control and APF authorizations if they are accessed through LINKLIST or STEPLIB.
- Coding a STEPLIB DD statement in the server JCL does not set the requested STEPLIB concatenation.

#### **RSE\_JAVAOPTS**

Additional RSE-specific Java options. See “Defining extra Java startup parameters with RSE\_JAVAOPTS” on page 36 for more information about this definition.

The following definitions are required if ISPF's TSO/ISPF Client Gateway is used for the TSO Commands service or SCLM Developer Toolkit.

#### **CMDSERV\_BASE\_HOME**

Home directory for the ISPF code that provides the TSO/ISPF Client

Gateway service. The default is /usr/lpp/ispf. Change to match your ISPF installation. This directive is only required when ISPF's TSO/ISPF Client Gateway is used.

#### **\_CMDSERV\_CONF\_HOME**

ISPF base configuration directory. The default is /etc/rdz. Change to match the location of ISPF.conf, the TSO/ISPF Client Gateway customization file. This directive is only required when ISPF's TSO/ISPF Client Gateway is used.

#### **\_CMDSERV\_WORK\_HOME**

ISPF base work directory. The default is /var/rdz. Change to match the location of the WORKAREA directory used by the TSO/ISPF Client Gateway. This directive is only required when ISPF's TSO/ISPF Client Gateway is used.

#### **Note:**

- The TSO/ISPF Client Gateway will add /WORKAREA to the path specified in \_CMDSERV\_WORK\_HOME. Do not add it yourself.
- If you did not use the SFEKSAMP(FEKSETUP) sample job to build the customizable environment, then you should verify that the WORKAREA directory exists in the path specified in \_CMDSERV\_WORK\_HOME. The directory permission bits must be 777.

#### **STEPLIB**

STEPLIB is described previously in the required definitions section.

#### **\_RSE\_CMDSERV\_OPTS**

Additional TSO/ISPF Client Gateway specific Java options. The default is "". See "Defining extra Java startup parameters with \_RSE\_CMDSERV\_OPTS" on page 41 for more information about this definition. This directive is only required when ISPF's TSO/ISPF Client Gateway is used.

The following definitions are required if SCLM Developer Toolkit is used.

#### **\_SCLMDT\_CONF\_HOME**

SCLM Developer Toolkit base configuration directory. The default is /var/rdz/sclmdt. Change to match the location of the CONFIG directory used by SCLMDT to store SCLM project information. This directive is only required when SCLMDT is used.

**Note:** SCLMDT will add /CONFIG and /CONFIG/PROJECT to the path specified in SCLMDT\_CNF\_HOME. Do not add it yourself.

#### **STEPLIB**

STEPLIB is described previously in the required definitions section.

#### **\_SCLMDT\_TRANTABLE**

Name of the long/short name translation VSAM. The default is FEK.#CUST.LSTRANS.FILE. Uncomment and change to match the name used in the SCLM sample job ISP.SISPSAMP(FLM02LST). This directive is only required if the long/short name translation in SCLM Developer Toolkit is used.

#### **ANT\_HOME**

Home directory for your Ant installation. The default is /usr/lpp/Apache/Ant/apache-ant-1.7.1. Change to match your Ant

installation. This directive is only required when the JAVA/J2EE build support is used with SCLM Developer Toolkit.

The following definitions are optional. If omitted, default values will be used:

#### **\_RSE\_PORTRANGE**

Specifies the port range that the RSE server can open for communication with a client. Any port can be used by default. See “Defining the PORTRANGE available for RSE server” on page 35 for more information about this definition. This is an optional directive.

#### **\_BPXK\_SETIBMOPT\_TRANSPORT**

Specifies the name of the TCP/IP stack to be used. The default is TCPIP. Uncomment and change to the requested TCP/IP stack name, as defined in the TCPIPJOBNAME statement in the related TCPIP.DATA. This is an optional directive.

#### **Note:**

- Coding a SYSTCPD DD statement in the server JCL does not set the requested stack affinity.
- When this directive is not active, RSE binds to every available stack on the system (BIND INADDRANY).

#### **TMPDIR**

Specifies the path used to store temporary files. The default is /tmp. Uncomment and change to use the requested path. This is an optional directive.

#### **\_RSE\_FEK\_SAF\_CLASS**

Specifies the security class where FEK.\* profiles are defined. The default is FACILITY. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **\_RSE\_LDAP\_SERVER**

Specifies the LDAP server host name used by the push-to-client function. The default is the current z/OS host name. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **\_RSE\_LDAP\_PORT**

Specifies the LDAP server port used by the push-to-client function. The default is 389. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **\_RSE\_LDAP\_PTC\_GROUP\_SUFFIX**

Specifies the “O=<organization>,C=<country>” suffix needed to find the push-to-client groups within the LDAP server. The default is “O=PTC,C=DeveloperForZ”. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **GSK\_CRL\_SECURITY\_LEVEL**

Specifies the level of security SSL applications will use when contacting LDAP servers to check CRLs for revoked certificates during certificate validation. The default is MEDIUM. Uncomment and change to enforce the usage of the specified value. This is an optional directive. The following values are valid:

- LOW - Certificate validation will not fail if the LDAP server cannot be contacted.
- MEDIUM - Certificate validation requires the LDAP server to be contactable, but does not require a CRL to be defined. This is the default

- HIGH - Certificate validation requires the LDAP server to be contactable and a CRL to be defined.

**Note:** This directive requires z/OS 1.9 or higher.

#### **GSK\_LDAP\_SERVER**

Specifies one or more blank-separated LDAP server host names. Uncomment and change to enforce the usage of the specified LDAP servers to obtain their CRL. This is an optional directive.

The host name can either be a TCP/IP address or an URL. Each host name can contain an optional port number separated from the host name by a colon (:).

#### **GSK\_LDAP\_PORT**

Specifies the LDAP server port. The default is 389. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **GSK\_LDAP\_USER**

Specifies the distinguished name to use when connecting to the LDAP server. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

#### **GSK\_LDAP\_PASSWORD**

Specifies the password to use when connecting to the LDAP server. Uncomment and change to enforce the usage of the specified value. This is an optional directive.

The following definitions are required, and should not be changed unless directed by the IBM support center:

#### **\_CEE\_RUNOPTS**

Language Environment (LE) runtime options. The default is "ALL31(ON) HEAP(32M,32K,ANYWHERE,KEEP,,) TRAP(ON)". Do not modify.

#### **\_BPX\_SHAREAS**

Run foreground processes in the same address space as the shell. The default is YES. Do not modify.

#### **\_BPX\_SPAWN\_SCRIPT**

Run shell scripts directly from the spawn() function. The default is YES. Do not modify.

#### **\_EDC\_ADD\_ERRNO2**

Show the reason code in z/OS UNIX error messages. The default is 1. Do not modify.

#### **JAVA\_PROPAGATE**

Propagates the security and workload context during thread creation (Java version 1.4 and older only). The default is NO. Do not modify.

#### **RSE\_LIB**

RSE library path. The default is \$RSE\_HOME/lib. Do not modify.

#### **PATH**

Command path. The default is .:\$JAVA\_HOME/bin:\$RSE\_HOME/bin:\$\_CMDSERV\_BASE\_HOME/bin:\$PATH. Do not modify.

#### **LIBPATH**

Library path. The default is too long to repeat. Do not modify.

#### **CLASSPATH**

Class path. The default is too long to repeat. Do not modify.

#### **\_RSE\_CMDSERV\_OPTS**

Additional TSO Commands service-specific Java options. The default is "&SESSION=SPAWN\$\_RSE\_CMDSERV\_OPTS". Do not modify.

#### **\_RSE\_JAVAOPTS**

Additional RSE-specific Java options. The default is too long to repeat. Do not modify.

#### **\_RSE\_SERVER\_CLASS**

Java class for the RSE server. The default is `org.eclipse.dstore.core.server.Server`. Do not modify.

#### **\_RSE\_DAEMON\_CLASS**

Java class for the RSE daemon. The default is `com.ibm.etools.zos.server.RseDaemon`. Do not modify.

#### **\_RSE\_POOL\_SERVER\_CLASS**

Java class for the RSE thread pool. The default is `com.ibm.etools.zos.server.ThreadPoolProcess`. Do not modify.

#### **\_RSE\_LOCKD\_CLASS**

Java class for the RSE lock daemon. The default is `com.ibm.ftt.rse.mvs.server.miners.MVSLockDaemon`. Do not modify.

#### **\_RSE\_SERVER\_TIMEOUT**

Time out value for the RSE server (waiting on the client) in milliseconds. The default is 120000 (2 minutes). Do not modify.

#### **SCLMDT\_BASE\_HOME**

Home directory for SCLM Developer Toolkit code. The default is `$RSE_HOME`. Do not modify.

#### **SCLMDT\_WORK\_HOME**

SCLM Developer Toolkit base work directory. The default is `$_CMDSERV_WORK_HOME`. Do not modify.

#### **CGI\_DTWORk**

SCLM Developer Toolkit support for older clients. The default is `$_SCLMDT_WORK_HOME`. Do not modify.

#### **CGI\_ISPCONF**

ISPF TSO/ISPF Client Gateway service support. The default is `$_CMDSERV_CONF_HOME`. Do not modify.

#### **CGI\_ISPWORK**

ISPF TSO/ISPF Client Gateway service support. The default is `$_CMDSERV_WORK_HOME`. Do not modify.

## **Defining the PORTRANGE available for RSE server**

This is a part of `rsed.envvars` customization that specifies the ports on which the RSE server can communicate with the client. This range of ports has no connection with the RSE daemon port.

To help understand the port usage, a brief description of RSE's connection process follows:

1. The client connects to host port 4035, RSE daemon.
2. The RSE daemon creates an RSE server thread.

3. The RSE server opens a host port for the client to connect. The selection of this port can be configured by the user, either on the client in the subsystem properties tab (this is not recommended) or through the `_RSE_PORTRANGE` definition in `rsed.envvars`.
4. The RSE daemon returns the port number to the client.
5. The client connects to the host port.

**Note:**

- The process is similar for the (optional) alternative connection method using REXEC/SSH.
- Refer to "Understanding Developer for System z" in the *Host Configuration Reference* (SC14-7290) for more information.

To specify the port range, for the client to communicate with z/OS, uncomment and customize the following line in `rsed.envvars`:

```
#_RSE_PORTRANGE=8108-8118
```

**Note:** Before selecting a port range, verify that the range is available on your system with the **NETSTAT** and **NETSTAT PORTL** commands.

The format of `PORTRANGE` is: `_RSE_PORTRANGE=min-max` (max is non-inclusive; for example `_RSE_PORTRANGE=8108-8118` means port numbers from 8108 up to 8117 are usable). The port number used by the RSE server is determined in the following order:

1. If a nonzero port number is specified in the subsystem properties on the client, then the specified port number is used. If the port is not available connect will fail. This setup is not recommended.

**Note:** The host can deny this type of connection request by specifying the `deny.nonzero.port=true` directive in `rsed.envvars`. Refer to "Defining extra Java startup parameters with `_RSE_JAVAOPTS`" for more information about this directive.

2. If the port number in the subsystem properties is 0, and if `_RSE_PORTRANGE` is specified in `rsed.envvars`, then the port range specified by `_RSE_PORTRANGE` is used. If no port in the range is available, connect will fail.

Note that RSE server does not need the port exclusively for the duration of the client connection. It is only in the time span between the (server) bind and the (client) connect that no other RSE server can bind to the port. This means that most connections will be using the first port in the range, with the rest of the range being a buffer in case of multiple simultaneous logons.

3. If the port number in the subsystem properties is 0, and `_RSE_PORTRANGE` is not specified in `rsed.envvars`, then any available port is used.

## Defining extra Java startup parameters with `_RSE_JAVAOPTS`

With the different `_RSE_*OPTS` directives, `rsed.envvars` provides the possibility to give extra parameters to Java when it starts the RSE processes. The sample options included in `rsed.envvars` can be activated by uncommenting them.

`_RSE_JAVAOPTS` defines standard and RSE-specific Java options.

```
_RSE_JAVAOPTS=""
```

Variable initialization. Do not modify.

**`_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Xms1m -Xmx256m"`**

Set initial (Xms) and maximum (Xmx) heap size. The defaults are 1M and 256M respectively. Change to enforce the desired heap size values. If this directive is commented out, the Java default values will be used, which are 4M and 512M respectively (1M and 64M for Java 5.0).

**Note:** Refer to "Key resource definitions" in the *Host Configuration Reference* (SC14-7290) to determine the optimal values for this directive.

**`_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Ddaemon.log=/var/rdz/logs"`**

Directory holding the RSE daemon and server logging and RSE audit data. The default is /var/rdz/logs. Change to enforce the desired location. If this directive is commented out, the home directory of the user ID assigned to RSE daemon will be used. The home directory is defined in the OMVS security segment of the user ID.

**Note:** If this directive (or its counterpart, the home directory) does not specify an absolute path (the path does not start with a forward slash (/)), then the actual log location is relative to the configuration directory (by default /etc/rdz).

**`_RSE_JAVAOPTS="$_RSE_JAVAOPTS -Duser.log=/var/rdz/logs"`**

Directory leading to the user-specific logs. The default is /var/rdz/logs. Change to enforce the desired location. If this directive is commented out or the value is a null string, the home directory of the client user ID will be used. The home directory is defined in the OMVS security segment of the user ID.

**Note:**

- If this directive (or its counterpart, the home directory) does not specify an absolute path (the path does not start with a forward slash (/)), then the actual log location is relative to the configuration directory (by default /etc/rdz).
- The complete path to the user logs is userlog/dstorelog/\$LOGNAME/, where userlog is the value of the user.log directive, dstorelog is the value of the DSTORE\_LOG\_DIRECTORY directive and \$LOGNAME is the client's user ID in uppercase.
- Ensure that the permission bits for userlog/dstorelog are set so that each client can create \$LOGNAME.

**`_RSE_JAVAOPTS="$_RSE_JAVAOPTS -DDSTORE_LOG_DIRECTORY="`**

This directory is appended to the path specified in the user.log directive. Together they create the path leading to the user-specific logs. The default is a null-string. Change to enforce the usage of the specified directory. If this directive is commented out, .eclipse/RSE/ will be used.

**Note:**

- The complete path to the user logs is userlog/dstorelog/\$LOGNAME/, where userlog is the value of the user.log directive, dstorelog is the value of the DSTORE\_LOG\_DIRECTORY directive, and \$LOGNAME is the client's user ID in uppercase.
- The directory specified here is relative to the directory specified in user.log, and thus might not start with a forward slash (/).
- Ensure that the permission bits for userlog/dstorelog are set so that each client can create \$LOGNAME.



The following directives are commented out by default.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dmaximum.clients=60"**

Maximum amount of clients serviced by one thread pool. The default is 60. Uncomment and customize to limit the number of clients per thread pool. Note that other limits might prevent RSE from reaching this limit.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dmaximum.threads=1000"**

Maximum amount of active threads in one thread pool to allow new clients. The default is 1000. Uncomment and customize to limit the number of clients per thread pool based on the number of threads in use. Note that each client connection uses multiple threads (16 or more) and that other limits might prevent RSE from reaching this limit.

**Note:** This value must be lower than the setting for MAXTHREADS and MAXTHREADTASKS in SYS1.PARMLIB(BPXPRMxx).

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dminimum.threadpool.process=1"**

The minimum number of active thread pools. The default is 1. Uncomment and customize to start at least the listed number of thread pool processes. Thread pool processes are used for load balancing the RSE server threads. More new processes are started when they are needed. Starting the new processes up front helps prevent connection delays but uses more resources during idle times.

**Note:** If the single.logon directive is active, then there will be at least 2 thread pools started, even if minimum.threadpool.process is set to 1. The default setting for single.logon in rsed.envvars is active.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dmaximum.threadpool.process=100"**

The maximum number of active thread pools. The default is 100. Uncomment and customize to limit the number of thread pool processes. Thread pool processes are used for load balancing the RSE server threads, so limiting them will limit the amount of active client connections.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dipv6=true"**

TCP/IP version. The default is false, which means that an IPv4 interface will be used. Uncomment and specify true to use an IPv6 interface.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dkeep.last.log=true"**

Keep a copy of the host log files belonging to the previous session. The default is false. Uncomment and specify true to rename the previous log files to \*.last during server startup and client connect.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Denable.standard.log=true"**

Write the stdout and stderr streams of the thread pools to a log file. The default is false. Uncomment and specify true to save the stdout and stderr streams. The resulting log files are located in the directory referenced by the daemon.log directive.

**Note:**

- The **MODIFY RSESTANDARDLOG** operator command can be used to dynamically stop or start the update of the stream log files.
- There are no user-specific stdout.log and stderr.log log files when the enable.standard.log directive is active. The user-specific data is now written to the matching RSE thread pool stream.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Denable.port.of.entry=true"**

Port Of Entry (POE) check option. The default is false. Uncomment and



specify true to enforce POE checking for client connections. During POE checking, the IP address of the client is mapped into a network access security zone by your security software. The client user ID must have permission to use the profile that defines the security zone.

**Note:**

- POE checking must also be enabled in your security product.
- Enabling POE checking will enable it for other z/OS UNIX services also, such as INETD.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Denable.certificate.mapping=false"**

Use your security software to authenticate a logon with a X.509 certificate. The default is true. Uncomment and specify false to have RSE daemon do the authentication without relying on the X.509 support of your security software.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Denable.automount=true"**

Support home directories created by z/OS UNIX automount. The default is false. Uncomment and specify true to ensure that z/OS UNIX automount uses the client user ID as owner of the directory.

**Note:** z/OS UNIX automount uses the user ID of the process that invoked the service when creating a file system. If this option is disabled, this process is the RSE thread pool server (user ID STCRSE). If this option is enabled, a new, temporary process is created using the client user ID before invoking the service.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Denable.audit.log=true"**

Audit option. The default is false. Uncomment and specify true to enforce audit logging of actions done by clients. Audit logs are written to the RSE daemon log location. See the daemon.log option of the \_RSE\_JAVAOPTS variable to know where this is.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Daudit.cycle=30"**

Number of days stored in 1 audit log file. The default is 30. Uncomment and customize to control how much audit data is written to 1 audit log file. The maximum value is 365.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Daudit.action=<user exit>"**

Name of a user exit which will be invoked when an audit log file is closed. There is no default value, but a sample exit is provided in /usr/lpp/rdz/samples/process\_audit.rex. Uncomment and specify the full pathname of the user exit program to enable post-processing of audit logs.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Daudit.action.id=<userid>"**

User ID to be used for running the exit specified in the audit.action variable. The default is the user ID assigned to RSE daemon. Uncomment and specify a user ID to use the specified ID for executing the audit post-processing exit.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Daudit.retention.period=0"**

Number of days audit logs are kept. The default is 0 (no limit). Uncomment and customize to delete audit logs after a given number of days. The maximum value is 365.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Daudit.log.mode=RW.R."**

Access permission mask for audit logs. The default is RW.R., which allows

the owner read and write access. The owner's default group has read access and everyone else has no access. Uncomment and customize to set the desired access permissions.

UNIX standards dictate that permissions can be set for three types of users: owner, group, and other. The fields in the `audit.log.mode` mask match this order, and the fields are separated by a period (.). Each field can either be empty, or have R, W, or RW as value (R = read, W = write).

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Ddeny.nonzero.port=true"**

Disallow the client to choose the communication port number. The default is false. Uncomment and specify true to refuse connections where the client specifies which host port must be used by RSE server for the connection. Refer to "Defining the PORTRANGE available for RSE server" on page 35 for more information.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dsingle.logon=false"**

Disallow a user ID to log on multiple times. The default is true. Uncomment and specify false to allow a user ID to log on multiple times to a single RSE daemon.

**Note:**

- A second logon attempt will cause the first one to be cancelled by the host if this directive is not active or set to true. This cancel will be accompanied by console message FEK210I.
- If the `single.logon` directive is active, then there will be at least 2 thread pools started, even if `minimum.threadpool.process` is set to 1. The default setting for `minimum.threadpool.process` in `rsd.envvars` is 1.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -Dprocess.cleanup.interval=0"**

Automatically remove RSE thread pools that are in an unrecoverable error state. By default, erroneous RSE thread pools are not automatically removed. Uncomment and customize to automatically remove erroneous RSE thread pool servers at every interval (interval unit is seconds). Specifying 0 does not start an interval timer, but erroneous RSE thread pool servers are removed when the RSE daemon checks the RSE thread pools during a new client logon or the DISPLAY PROCESS command.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DCPP\_CLEANUP\_INTERVAL=60000"**

Cleanup interval for unused C/C++ header files in milliseconds. The default is 60000 (1 minute). Uncomment and customize to change the cleanup interval. Specifying 0 will prevent caching of C/C++ header files, reducing performance of remote content assist in the editor.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DAPPLID=FEKAPPL"**

RSE server application ID. The default is FEKAPPL. Uncomment and customize this option to enforce the use of the desired application ID.

**Note:**

- The application ID must be defined to your security software. Failure to do so will prevent the client from logging on.
- Refer to "Using PassTickets" in *Host Configuration Reference* (SC14-7290) for the security implications when changing this value.
- This value must match the application ID set for JES Job Monitor in the FEJJCNFG configuration file. If these values differ, RSE cannot connect the client to JES Job Monitor. Refer to "FEJJCNFG, JES Job Monitor configuration file" on page 22 to learn how to define the variable for JES Job Monitor.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DDENY\_PASSWORD\_SAVE=true"**

Password save option. The default is false. Uncomment and specify true to prevent users from saving their host password on the client. Previously saved passwords will be removed. This option only works with clients version 7.1 and higher.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DHIDE\_ZOS\_UNIX=true"**

Hide z/OS UNIX option. The default is false. Uncomment and specify true to prevent users from seeing z/OS UNIX elements (directory structure and command line) on the client. This option only works with clients version 7.6 and higher.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS  
-DDISABLE\_DELETE\_IN\_SUBPROJECT=true"**

Disable the Delete menu item in the context menu of z/OS subprojects. The default is false. Uncomment and specify true to prevent users from using the Delete menu item in the context menu of z/OS subprojects. This option only works with clients version 8.0.1 and higher.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS  
-DDSTORE\_IDLE\_SHUTDOWN\_TIMEOUT=3600000"**

Disconnect idle clients. By default, idle clients are not disconnected. Uncomment and customize to disconnect clients who are idle for the listed amount of milliseconds (3600000 equals 1 hour).

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DDSTORE\_TCP\_NO\_DELAY=true"**

Disable the TCP/IP DELAY ACK function. The default is false. Uncomment and specify true to stop TCP/IP from doing DELAY ACK for Developer for System z client-host communication.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DDSTORE\_TRACING\_ON=true"**

Start dstore tracing. Use only when directed by the IBM support center. Note that the resulting .dstoreTrace log file is created in Unicode (ASCII), not EBCDIC.

**#\_RSE\_JAVAOPTS="\$\_RSE\_JAVAOPTS -DDSTORE\_MEMLOGGING\_ON=true"**

Start dstore memory tracing. Use only when directed by the IBM support center. Note that the resulting .dstoreMemLogging log file is created in Unicode (ASCII), not EBCDIC.

## Defining extra Java startup parameters with \_RSE\_CMDSERV\_OPTS

With the different \_RSE\_\*OPTS directives, rsed.envvars provides the possibility to give extra parameters to Java when it starts the RSE processes. The sample options included in rsed.envvars can be activated by uncommenting them.

The \_RSE\_CMDSERV\_OPTS directives are RSE-specific Java options and are only in effect when ISPF's TSO/ISPF Client Gateway is used by the Developer for System z. (This is the default.)

**\_RSE\_CMDSERV\_OPTS=""**

Variable initialization. Do not modify.

**\_RSE\_CMDSERV\_OPTS="\$\_RSE\_CMDSERV\_OPTS &ISPROF=  
&SYSUID..ISPROF="**

Use an existing ISPF profile for the ISPF initialization. Uncomment and change the data set name to use the specified ISPF profile.

The following variables can be used in the data set name:

- &SYSUID, to substitute the developer's user ID
- &SYSPREF, to substitute the developer's TSO prefix

---

## ISPF.conf, ISPF's TSO/ISPF Client Gateway configuration file

ISPF's TSO/ISPF Client Gateway uses the definitions in ISPF.conf to create a valid environment to execute batch TSO and ISPF commands. Developer for System z uses this environment to run some MVS based services. These services include the TSO Commands service and SCLM Developer Toolkit.

ISPF.conf is located in /etc/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See "Customization setup" on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

Definitions must start in column 1. Comment lines start with an asterisk (\*) when using a US code page. Data lines can only have a directive and its assigned value. Comments are not allowed on the same line. Line continuations are not supported. When concatenating data set names, add them on the same line and separate the names with a comma (,).

In addition to providing the correct names for the ISPF data sets, you must also add the TSO Commands service data set name, FEK.SFEKPROC, to the SYSPROC or SYSEXEC statement, as shown in the following example.

```
* REQUIRED:
sysproc=ISP.SISPCLIB,FEK.SFEKPROC
ispmllib=ISP.SISPMENU
isptlib=ISP.SISPTENU
ispplib=ISP.SISPPENU
ispslib=ISP.SISPSLIB
ispllib=ISP.SISLOAD

* OPTIONAL:
*allocjob = ISP.SISPSAMP(ISPZISP2)
*ISPF_timeout = 900
```

*Figure 10. ISPF.conf - ISPF configuration file*

### Note:

- You can add your own DD-like statements and data set concatenations to customize the TSO environment, thus mimicking a TSO logon procedure. See "Customizing the TSO environment" in the *Host Configuration Reference* (SC14-7290) for more details.
- The TSO/ISPF Client Gateway might not function properly if you use a (third party) product that intercepts ISPF commands, such as **ISPSTART**. Check the documentation for that product on how it can be disabled for Developer for System z. If the product requires the allocation of a specific DD statement to DUMMY, you can simulate this in ISPF.conf by allocating that DD statement to nullfile.

For example:

```
ISPTRACE=nullfile
```

- When using the allocjob directive, be careful not to undo the DD definitions done earlier in ISPF.conf.
- System abend 522 for module ISPZTS0 is to be expected if the JWT parameter in the SMFPRMxx parmlib member is set lower than the ISPF\_timeout value in

ISPF.conf. This does not impact Developer for System z operations, as the TSO/ISPF Client Gateway is restarted automatically when needed.

- Changes are active for all new invocations. No server restart is needed.

---

## Optional components

This section combines a variety of optional customization tasks. Follow the instructions in the appropriate section to configure the desired service.

Customizations to Developer for System z stand-alone components:

- Chapter 3, “(Optional) Common Access Repository Manager (CARMA),” on page 45
- Chapter 4, “(Optional) SCLM Developer Toolkit,” on page 73
- Chapter 5, “(Optional) Application Deployment Manager,” on page 81

Customizations to Developer for System z configuration files:

- “(Optional) pushtoclient.properties, Host-based client control” on page 89
- “(Optional) (deprecated) FMIEXT.properties, File Manager integration” on page 92
- “(Optional) ssl.properties, RSE SSL encryption” on page 93
- “(Optional) rsecomm.properties, RSE tracing” on page 96

Developer for System z related customizations to (or for) other products:

- “(Optional) DB2 stored procedure” on page 97
- “(Optional) z/OS UNIX subprojects” on page 99
- “(Optional) Enterprise Service Tools support” on page 100
- “(Optional) CICS bidirectional language support” on page 100
- “(Optional) Diagnostic IRZ error messages” on page 101
- “(Optional) WORKAREA and /tmp cleanup” on page 102

---

## Installation verification

The detailed description of the various installation verification programs (IVPs) is located in Chapter 7, “Installation verification,” on page 103, because some of the IVPs are for the optional components.

You can test the basic functions with the following scenario:

1. Start the JMON started task (or user job). The startup information in DD STDOUT should end with the following message:  
JM200I Server initialization complete.  
If the job ends with return code 66, then FEK.SFEKAUTH is not APF authorized.
2. Start the LOCKD started task (or user job). The lock daemon issues the following console message upon successful startup:  
FEK501I Lock daemon started, port=4036, cleanup interval=1440, log level=1
3. Start the RSED started task (or user job) with the IVP=IVP parameter. With this parameter, the server will end after doing some installation verification tests. Check DD STDOUT for messages indicating that the following IVPs were successful:
  - Java startup
  - JES Job Monitor connection

- Lock daemon connection
  - TCP/IP setup
  - PassTicket generation
4. Start the RSED started task (or user job) without the IVP parameter. RSE daemon issues the following console message upon successful startup:  
FEK002I RseDaemon started. (port=4035)
  5. Issue the following operator commands and verify in the resulting console messages that the tests ran successfully:  
F RSED,APPL=IVP PASSTICKET,userid  
F RSED,APPL=IVP DAEMON,userid  
F RSED,APPL=IVP ISPF,userid  
Replace userid with a valid TSO user ID.

---

## Chapter 3. (Optional) Common Access Repository Manager (CARMA)

Common Access Repository Manager (CARMA) is a server platform for Repository Access Managers (RAMs). A RAM is an Application Programming Interface (API) for a z/OS based Software Configuration Manager (SCM). By wrapping the SCM functionality in a RAM, a single API is available for a client to access any supported SCM.

Developer for System z provides multiple pre-built RAMs, as well as source code examples for creating your own RAM.

---

### Requirements and checklist

You will need the assistance of a security administrator and a TCP/IP administrator to complete this customization task, which requires the following resources or special customization tasks:

- TCP/IP port range for internal communication
- (Optional) Security rule to allow developers update to CARMA VSAM files
- (Optional) Security rule to allow users to submit CRA\* jobs
- (Optional) LPA update

In order to start using CARMA at your site, you must perform the following tasks. Unless otherwise indicated, all tasks are mandatory.

1. Choose a method to start CARMA and choose which RAMs should be activated. Several combinations of RAMs and server startup methods are available as a preconfigured setup. For details, see “Select server startup method and active RAM” on page 46.
2. Create CARMA VSAM data sets. For details, see “CARMA VSAM data sets” on page 61 and “CARMA Repository Access Managers (RAMs)” on page 63.
3. Initial customization of RSE configuration files to interface with CARMA. The complete customization is dependent on the method chosen to start CARMA. For details, see “CRASRV.properties, RSE interface to CARMA” on page 56.
4. Depending on the chosen CARMA startup method and the chosen RAMs, do the required customization of the related configuration files. For details see:
  - “crastart\*.conf, CRASTART server startup” on page 58
  - “CRASUB\*, batch submit server startup” on page 60
5. Optionally customize CA Endeavor® SCM specific configuration members. For details see “CRASHOW and CRATMAP, CA Endeavor® SCM RAM configuration files” on page 65, “CRANDVRA, CA Endeavor® SCM RAM allocation exec” on page 65, and “CA Endeavor® SCM RAM batch actions” on page 66.
6. Optionally create a data set allocation exec. For details, see “(Optional) Custom allocation exec” on page 70.
7. Optionally create CRAXJCL as replacement for IRXJCL. For details, see “(Optional) IRXJCL versus CRAXJCL” on page 71.



**Note:** The sample members referenced in this chapter are located in FEK.#CUST.\* and /etc/rdz, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

---

## Select server startup method and active RAM

Developer for System z supports multiple methods to start a CARMA server. Developer for System z also provides multiple Repository Access Managers (RAMs), which can be divided into two groups, production RAMs and sample RAMs. This publication describes several possible combinations of RAMs and server startup methods. Each of the described configuration scenarios is available as a preconfigured setup.

### CARMA server startup

Developer for System z supports multiple methods to start a CARMA server. Each method has benefits and drawbacks.

#### CRASTART

The "CRASTART" method starts the CARMA server as a subtask within RSE. It provides a very flexible setup by using a separate configuration file that defines data set allocations and program invocations needed to start a CARMA server. This method provides the best performance and uses the fewest resources, but requires that module CRASTART is located in LPA.

#### Batch submit

The "batch submit" method starts the CARMA server by submitting a job. This is the default method used in the provided sample configuration files. The benefit of this method is that the CARMA logs are easily accessible in the job output. It also allows the use of custom server JCL for each developer, which is maintained by the developer himself. However, this method uses one JES initiator per developer starting a CARMA server.

#### (deprecated) TSO/ISPF Client Gateway

The "TSO/ISPF Client Gateway" method uses ISPF's TSO/ISPF Client Gateway to create a TSO or ISPF environment, in which the CARMA server is started. It allows for flexible data set allocations using the possibilities of ISPF.conf. However, this method is not suited to access SCMs that interfere with normal TSO or ISPF operations.

**Note:** The "TSO/ISPF Client Gateway" connection method has been marked as deprecated. Although it is still supported, this function will no longer be enhanced, and the documentation has moved to a white paper, *Using ISPF Client Gateway to provide CARMA services* (SC14-7292), available in the Developer for System z library, <http://www-01.ibm.com/software/awdtools/rdz/library/>.

### Production RAMs

Production type RAMs are fully functional, pre-built RAMs that can be used to access a SCM in a production environment.

#### CA Endevor® SCM RAM

The IBM® Rational® Developer for System z Interface for CA Endevor® Software Configuration Manager gives Developer for System z clients direct access to CA Endevor® SCM. From here on, IBM® Rational® Developer for System z Interface for CA Endevor® SCM is abbreviated to CA Endevor® SCM RAM.



## **CA Endeavor® SCM packages RAM**

The CA Endeavor® SCM packages RAM gives Developer for System z clients direct access to CA Endeavor® SCM packages.

## **Sample RAMs**

Sample RAMs are provided for the purpose of testing the configuration of your CARMA environment and as examples for developing your own RAMs (source code is included).

Do NOT use the provided sample RAMs in a production environment.

### **PDS RAM**

The PDS RAM gives a data set list similar to **MVS Files -> My Data Sets** in the Remote Systems view.

### **Skeleton RAM**

The skeleton RAM gives a functional framework that can be used as starting point to develop your own RAM.

### **SCLM RAM**

The SCLM RAM gives a basic entry into SCLM, ISPF's Software Configuration Manager. The SCLM RAM is not enabled by default.

## **Preconfigured RAM and server startup combinations**

Several combinations of RAMs and server startup methods are available as a preconfigured setup. The listed scenarios only need minor customization to fit your environment.

- “CRASTART with CA Endeavor® SCM RAM”
- “CRASTART with sample RAMs” on page 50
- “Batch submit with CA Endeavor® SCM RAM” on page 51
- “Batch submit with sample RAMs” on page 54

Detailed information on the different steps of each scenario can be found in “CARMA configuration details” on page 55.

Note that it is possible to add a RAM to any CARMA setup, now or somewhere in the future. Refer to “(Optional) Supporting multiple RAMs” on page 69 for more information on adding a RAM to an existing setup.

---

## **CRASTART with CA Endeavor® SCM RAM**

The information in this section describes how to set up CARMA with the following specifications:

- Server startup: CRASTART method (requires that CRASTART is in LPA)
- RAM: CA Endeavor® SCM RAM

This customization step can be bypassed if you want to use one of the other scenarios with different specifications.

## Create CARMA VSAM data sets

Customize and submit the following JCL jobs to define and populate the CARMA related VSAM data sets. Refer to the documentation within the member for customization instructions. Note that existing VSAM data sets will be replaced if present.

Refer to “CARMA VSAM data sets” on page 61 for more details on this step.

- FEK.#CUST.JCL(CRA\$VCAD)
- FEK.#CUST.JCL(CRA\$VCAS)
- FEK.#CUST.JCL(CRA\$VMSG)

## Customize CRASRV.properties

RSE server uses the settings in `/etc/rdz/CRASRV.properties` to start and connect to a CARMA server. You can edit the file with the TSO **OEDIT** command. Note that the RSED started task must be restarted before changes are in effect.

When you use the default file locations, the only required changes are changing the value of the `clist.dsname` directive to `*CRASTART` and changing the value of `crastart.configuration.file` to `/etc/rdz/crastart.endevor.conf`. Refer to “CRASRV.properties, RSE interface to CARMA” on page 56 for more information on the different directives.

```
port.start=5227
port.range=100
startup.script.name=/usr/lpp/rdz/bin/carma.startup.rex
clist.dsname=*CRASTART
crastart.stub=/usr/lpp/rdz/bin/CRASTART
crastart.configuration.file=/etc/rdz/crastart.endevor.conf
crastart.syslog=Partial
crastart.timeout=420
#crastart.steplib=FEK.SFEKLPA
#crastart.tasklib=TASKLIB
```

*Figure 11. CRASRV.properties - CRASTART with CA Endevor® SCM RAM*

## Customize crastart.endevor.conf

CRASTART uses the definitions in `/etc/rdz/crastart.endevor.conf` to create a valid (TSO/ISPF) environment to start a CARMA server. You can edit the file with the TSO **OEDIT** command. Note that changes are in effect for all CARMA servers started after the update.

Refer to the documentation within the file for customization instructions. Refer to “crastart\*.conf, CRASTART server startup” on page 58 for more information on the CRASTART startup method.

**Note:** Due to page width limitations, some lines in the following sample wrapped onto the next line. All lines that start with an indentation should be added to the end of the previous line.

```

* DD used by RAM
TYPEMAP = FEK.#CUST.PARMLIB(CRATMAP)
SHOWVIEW= FEK.#CUST.PARMLIB(CRASHOW)
* uncomment CRABCFG and CRABSKEL to use batch actions
*CRABCFG = FEK.#CUST.PARMLIB(CRABCFG)
*CRABSKEL= FEK.#CUST.CNTL
CONLIB = CA.NDVR.CONLIB * NDVR R12
*CONLIB = CA.NDVR.CSIQLOAD * NDVR R14
-COMMAND=ALLOC FI(JCLOUT) SYSOUT(A) WRITER(INTRDR) RECFM(F) LRECL(80)
  BLKSIZE(80)
-COMMAND=ALLOC FI(EXT1ELM) NEW DELETE DSORG(PS) RECFM(V,B) LRECL(4096)
  BLKSIZE(27998) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(EXT2ELM) NEW DELETE DSORG(PS) RECFM(V,B) LRECL(4096)
  BLKSIZE(27998) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(EXT1DEP) NEW DELETE DSORG(PS) RECFM(V,B) LRECL(4096)
  BLKSIZE(27998) SPACE(5,5) TRACKS UNIT(SYSALLDA)
CIEXMSG= SYSOUT(H)
CIMSG1 = SYSOUT(H)
MSG3FILE= DUMMY

* DD used by CARMA server (CRASERV)
TASKLIB = FEK.SFEKLOAD,CA.NDVR.AUTHLIB,CA.NDVRU.AUTHLIB * NDVR R12
*TASKLIB = FEK.SFEKLOAD,CA.NDVR.CSIQAUTH,CA.NDVR.CSIQAUTU * NDVR R14
CRADEF = FEK.#CUST.CRADEF
CRAMSG = FEK.#CUST.CRAMSG
CASTRS = FEK.#CUST.CASTRS
CARMALOG= SYSOUT(H)
SYSPRINT= SYSOUT(H)

* DD used by ISPF (via NDVRC1)
-COMMAND=ALLOC FI(ISPCTL0) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPCTL1) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPPROF) NEW DELETE DSORG(PO) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA) DIR(5)
ISPTABL = -ISPPROF
ISPTLIB = -ISPPROF,ISP.SISPTENU
ISPMLIB = ISP.SISPMENU
ISPPLIB = ISP.SISPPENU
ISPSLIB = ISP.SISPSENU

* DD used by TSO (IKJEFT01)
SYSPROC = FEK.SFEKPROC * CRANDVRA
SYSTSIN = DUMMY
SYSPRTP= SYSOUT(H)

PROGRAM=IKJEFT01 %CRANDVRA NDVRC1 PGM(CRASERV) PARM(&CRAPRM1. &CRAPRM2.)

```

Figure 12. *crastart.endevor.conf* - *CRASTART* with CA Endeavor® SCM RAM

## (Optional) Additional CA Endeavor® SCM RAM customization

The CA Endeavor® SCM RAM has additional components that can be customized if you want to customize them.

- The CA Endeavor® SCM RAM has two configuration files, FEK.#CUST.PARMLIB(CRASHOW) and FEK.#CUST.PARMLIB(CRATMAP), that can be customized. Refer to “CRASHOW and CRATMAP, CA Endeavor® SCM RAM configuration files” on page 65 for more information.
- The CA Endeavor® SCM RAM has an allocation exec, FEK.SFEKPROC (CRANDVRA), that can be customized. Refer to “CRANDVRA, CA Endeavor® SCM RAM allocation exec” on page 65 for more information.

- The CA Endeavor® SCM RAM supports doing CA Endeavor® SCM actions in batch mode. Batch-actions requires a configuration file, FEK.#CUST.PARMLIB(CRABCFG), and a skeleton JCL, FEK.#CUST.CNTL(CRABATCA), that must be customized. See “CA Endeavor® SCM RAM batch actions” on page 66 for more information.

---

## CRASTART with sample RAMs

The information in this section describes how to set up CARMA with the following specifications:

- Server startup: CRAFTSTART method (requires that CRAFTSTART is in LPA)
- RAM: sample RAMs (not for production purposes)

This customization step can be bypassed if you want to use one of the other scenarios with different specifications.

### Create CARMA VSAM data sets

Customize and submit the following JCL jobs to define and populate the CARMA related VSAM data sets. Refer to the documentation within the member for customization instructions. Note that existing VSAM data sets will be replaced if present.

Refer to “CARMA VSAM data sets” on page 61 and “CARMA Repository Access Managers (RAMs)” on page 63 for more details on this step.

#### CARMA

- FEK.#CUST.JCL(CRA\$VDEF)
- FEK.#CUST.JCL(CRA\$VMSG)
- FEK.#CUST.JCL(CRA\$VSTR)

#### Sample RAMs

- FEK.#CUST.JCL(CRA#VPDS)

### Customize CRASRV.properties

RSE server uses the settings in /etc/rdz/CRASRV.properties to start and connect to a CARMA server. You can edit the file with the TSO OEDIT command. Note that the RSED started task must be restarted before changes are in effect.

When using the default file locations, the only required change is changing the value of the clist.dsname directive to \*CRAFTSTART. Refer to “CRASRV.properties, RSE interface to CARMA” on page 56 for more information on the different directives.

```
port.start=5227
port.range=100
startup.script.name=/usr/lpp/rdz/bin/carma.startup.rex
clist.dsname=*CRAFTSTART
craftstart.stub=/usr/lpp/rdz/bin/CRAFTSTART
craftstart.configuration.file=/etc/rdz/craftstart.conf
craftstart.syslog=Partial
craftstart.timeout=420
#craftstart.steplib=FEK.SFEKLPA
#craftstart.tasklib=TASKLIB
```

*Figure 13. CRASRV.properties - CRAFTSTART with sample RAMs*

## Customize crastart.conf

CRASTART uses the definitions in /etc/rdz/crastart.conf to create a valid (TSO/ISPF) environment to start a CARMA server. You can edit the file with the TSO **OEDIT** command. Note that changes are in effect for all CARMA servers started after the update.

Refer to the documentation within the file for customization instructions. Refer to “crastart\*.conf, CRASTART server startup” on page 58 for more information on the CRASTART startup method.

```
* DD used by RAM
CRARAM1 = FEK.#CUST.CRARAM1
*CRARAM2 = FEK.#CUST.CRARAM2
* PDS RAM
* SCLM RAM

* DD used by CARMA server (CRASERV)
TASKLIB = FEK.SFEKLOAD
CRADEF = FEK.#CUST.CRADEF
CRAMSG = FEK.#CUST.CRAMSG
CRASTRS = FEK.#CUST.CRASTRS
CARMALOG= SYSOUT(H)
SYSPRINT= SYSOUT(H)

* DD used by ISPF (ISPSTART)
-COMMAND=ALLOC FI(ISPCTL0) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPCTL1) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPPROF) NEW DELETE DSORG(PO) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA) DIR(5)
ISPTABL = -ISPPROF
ISPTLIB = -ISPPROF,ISP.SISPTENU
ISPTLIB = ISP.SISPMENU
ISPTLIB = ISP.SISPPENU
ISPTLIB = ISP.SISPSENU

* DD used by TSO (IKJEFT01)
SYSTSIN = DUMMY
SYSTSPRT= SYSOUT(H)

PROGRAM=IKJEFT01 ISPSTART PGM(CRASERV) PARM(&CRAPRM1. &CRAPRM2.)
```

Figure 14. crastart.conf - CRASTART with sample RAMs

**Note:** Due to page width limitations, some lines in the sample wrapped onto the next line. All lines that start with an indentation should be added to the end of the previous line.

---

## Batch submit with CA Endeavor® SCM RAM

The information in this section describes how to set up CARMA with the following specifications:

- Server startup: batch submit method (requires JES initiators)
- RAM: CA Endeavor® SCM RAM

This customization step can be bypassed if you want to use one of the other scenarios with different specifications.

## Create CARMA VSAM data sets

Customize and submit the following JCLs to define and populate the CARMA related VSAM data sets. Refer to the documentation within the member for customization instructions. Note that existing VSAM data sets will be replaced if present.

Refer to “CARMA VSAM data sets” on page 61 for more details on this step.

- FEK.#CUST.JCL(CRA\$VCAD)
- FEK.#CUST.JCL(CRA\$VCAS)
- FEK.#CUST.JCL(CRA\$VMSG)

## Customize CRASRV.properties

RSE server uses the settings in `/etc/rdz/CRASRV.properties` to start and connect to a CARMA server. You can edit the file with the TSO **OEDIT** command. Note that the RSED started task must be restarted before changes are in effect.

When using default file locations, the only required change is changing the value of the `clist.dsname` directive to `FEK.#CUST.CNTL(CRASUBCA)`. Refer to “CRASRV.properties, RSE interface to CARMA” on page 56 for more information on the different directives.

```
port.start=5227
port.range=100
startup.script.name=/usr/lpp/rdz/bin/carma.startup.rex
clist.dsname='FEK.#CUST.CNTL(CRASUBCA)'
```

*Figure 15. CRASRV.properties - batch submit with CA Endevor® SCM RAM*

## Customize CRASUBCA

The `FEK.#CUST.CNTL(CRASUBCA)` CLIST and embedded JCL submits a CARMA server. Note that changes are in effect for all CARMA servers started after the update.

Refer to the documentation within the member for customization instructions. Refer to “CRASUB\*, batch submit server startup” on page 60 for more information on the batch submit startup method.

```

PROC 1 PORT TIMEOUT(420)
SUBMIT * END($$)
//CRA&PORT JOB CLASS=A,MSGCLASS=A,MSGLEVEL=(1,1)
//*
//RUN      EXEC PGM=IKJEFT01,DYNAMNBR=125,REGION=0M,TIME=NOLIMIT
//*
//* DD used by RAM
//TYPEMAP DD DISP=SHR,DSN=FEK.#CUST.PARMLIB(CRATMAP)
//SHOWVIEW DD DISP=SHR,DSN=FEK.#CUST.PARMLIB(CRASHOW)
//* uncomment CRABCFG and CRABSKEL to use batch actions
//*CRABCFG DD DISP=SHR,DSN=FEK.#CUST.PARMLIB(CRABCFG)
//*CRABSKEL DD DISP=SHR,DSN=FEK.#CUST.CNTL
//CONLIB DD DISP=SHR,DSN=CA.NDVR.CONLIB * NDVR R12
//*CONLIB DD DISP=SHR,DSN=CA.NDVR.CSIQLOAD * NDVR R14
//JCLOUT DD SYSOUT=(A,INTRDR),DCB=(LRECL=80,RECFM=F,BLKSIZE=80)
//EXT1ELM DD DISP=(NEW,DELETE),UNIT=SYSALLDA,
//          RECFM=VB,LRECL=4096,BLKSIZE=27998,SPACE=(TRK,(5,5))
//EXT2ELM DD DISP=(NEW,DELETE),UNIT=SYSALLDA,
//          RECFM=VB,LRECL=4096,BLKSIZE=27998,SPACE=(TRK,(5,5))
//EXT1DEP DD DISP=(NEW,DELETE),UNIT=SYSALLDA,
//          RECFM=VB,LRECL=4096,BLKSIZE=27998,SPACE=(TRK,(5,5))
//C1MSGSG1 DD SYSOUT(H)
//C1EXMSGSG DD SYSOUT(H)
//MSG3FILE DD DUMMY
//*
//* DD used by CARMA server (CRASERV)
//STEPLIB DD DISP=SHR,DSN=FEK.SFEKLOAD
//          DD DISP=SHR,DSN=CA.NDVR.AUTHLIB * NDVR R12
//          DD DISP=SHR,DSN=CA.NDVRU.AUTHLIB * NDVR R12
//*          DD DISP=SHR,DSN=CA.NDVR.CSIQAUTH * NDVR R14
//*          DD DISP=SHR,DSN=CA.NDVR.CSIQAUTU * NDVR R14
//CRADEF DD DISP=SHR,DSN=FEK.#CUST.CRADEF
//CRAMSG DD DISP=SHR,DSN=FEK.#CUST.CRAMSG
//CRASTRS DD DISP=SHR,DSN=FEK.#CUST.CRASTRS
//CARMALOG DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//*
//* DD used by ISPF (via NDVRC1)
//ISPPROF DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(1,1,5))
//ISPCTL0 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPCTL1 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPLIB DD DISP=SHR,DSN=ISP.SISPMENU
//ISPLIB DD DISP=SHR,DSN=ISP.SISPPENU
//ISPSLIB DD DISP=SHR,DSN=ISP.SISPSENU
//ISPTLIB DD DISP=SHR,DSN=ISP.SISPTENU
//*
//* DD used by TSO (IKJEFT01)
//SYSPROC DD DISP=SHR,DSN=FEK.SFEKPROC * CRANDVRA
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
%CRANDVRA NDVRC1 PGM(CRASERV) PARM(&PORT &TIMEOUT)
$$
EXIT CODE(0)

```

Figure 16. CRASUBCA - batch submit with CA Endeavor® SCM RAM

## (Optional) Additional CA Endeavor® SCM RAM customization

The CA Endeavor® SCM RAM has additional components that can be customized if you want to customize them.

- The CA Endeavor® SCM RAM has two configuration files, FEK.#CUST.PARMLIB(CRASHOW) and FEK.#CUST.PARMLIB(CRATMAP), that can be customized. Refer to “CRASHOW and CRATMAP, CA Endeavor® SCM RAM configuration files” on page 65 for more information.
- The CA Endeavor® SCM RAM has an allocation exec, FEK.SFEKPROC(CRANDVRA), that can be customized. Refer to “CRANDVRA, CA Endeavor® SCM RAM allocation exec” on page 65 for more information.
- The CA Endeavor® SCM RAM supports doing CA Endeavor® SCM actions in batch mode. Batch-actions requires a configuration file, FEK.#CUST.PARMLIB(CRABCFG), and a skeleton JCL, FEK.#CUST.CNTL(CRABATCA), that must be customized. See “CA Endeavor® SCM RAM batch actions” on page 66 for more information.

---

## Batch submit with sample RAMs

The information in this section describes how to set up CARMA with the following specifications:

- Server startup: batch submit method (requires JES initiators)
- RAM: sample RAMs (not for production purposes)

This customization step can be bypassed if you want to use one of the other scenarios with different specifications.

## Create VSAM data sets

Customize and submit the following JCL jobs to define and populate the CARMA related VSAM data sets. Refer to the documentation within the member for customization instructions. Note that existing VSAM data sets will be replaced if present.

Refer to “CARMA VSAM data sets” on page 61 and “CARMA Repository Access Managers (RAMs)” on page 63 for more details on this step.

### CARMA

- FEK.#CUST.JCL(CRA\$VDEF)
- FEK.#CUST.JCL(CRA\$VMSG)
- FEK.#CUST.JCL(CRA\$VSTR)

### Sample RAMs

- FEK.#CUST.JCL(CRA#VPDS)

## Customize CRASRV.properties

RSE server uses the settings in /etc/rdz/CRASRV.properties to start and connect to a CARMA server. You can edit the file with the TSO OEDIT command. Note that the RSED started task must be restarted before changes are in effect.

As this is the default scenario for Developer for System z, there are no changes required when starting from an unmodified copy of the file. Refer to “CRASRV.properties, RSE interface to CARMA” on page 56 for more information on the different directives.



```

port.start=5227
port.range=100
startup.script.name=/usr/lpp/rdz/bin/carma.startup.rex
clist.dsname='FEK.#CUST.CNTL(CRASUBMT)'

```

Figure 17. CRASRV.properties - batch submit with sample RAMs

## Customize CRASUBMT

The FEK.#CUST.CNTL(CRASUBMT) CLIST and embedded JCL submits a CARMA server. Note that changes are in effect for all CARMA servers started after the update.

Refer to the documentation within the member for customization instructions. Refer to “CRASUB\*, batch submit server startup” on page 60 for more information on the batch submit startup method.

```

PROC 1 PORT TIMEOUT(420)
SUBMIT * END($$)
//CRA&PORT JOB CLASS=A,MSGCLASS=A,MSGLEVEL=(1,1)
//*
//RUN      EXEC PGM=IKJEFT01,DYNAMNBR=125,REGION=0M,TIME=NOLIMIT
//*
//* DD used by RAM
//CRARAM1 DD DISP=SHR,DSN=FEK.#CUST.CRARAM1          * PDS RAM
//*CRARAM2 DD DISP=SHR,DSN=FEK.#CUST.CRARAM2          * SCLM RAM
//*
//* DD used by CARMA server (CRASERV)
//STEPLIB DD DISP=SHR,DSN=FEK.SFEKLOAD
//CRADEF  DD DISP=SHR,DSN=FEK.#CUST.CRADEF
//CRAMSG  DD DISP=SHR,DSN=FEK.#CUST.CRAMSG
//CRASTRS DD DISP=SHR,DSN=FEK.#CUST.CRASTRS
//CARMALOG DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//*
//* DD used by ISPF (ISPSTART)
//ISPPROF DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(1,1,5))
//ISPCTL0 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPCTL1 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPLIB  DD DISP=SHR,DSN=ISP.SISPMENU
//ISPPLIB DD DISP=SHR,DSN=ISP.SISPPENU
//ISPSLIB DD DISP=SHR,DSN=ISP.SISPSENU
//ISPTLIB DD DISP=SHR,DSN=ISP.SISPTENU
//*
//* DD used by TSO (IKJEFT01)
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
ISPSTART PGM(CRASERV) PARM(&PORT &TIMEOUT)
$$
EXIT CODE(0)

```

Figure 18. CRASUBMT - batch submit with sample RAMs

---

## CARMA configuration details

The different configuration scenarios that are documented in this publication share many of the CARMA configuration files. The details of these configuration files are documented here, and they are referenced from within the various scenarios.

## CRASRV.properties, RSE interface to CARMA

The CARMA server provides a standard API for other host-based products to access one or more Software Configuration Managers (SCMs). However, it does not provide methods for direct communication with a client PC. For this, it relies on other products, such as the RSE server. The RSE server uses the settings in CRASRV.properties to start and connect to a CARMA server.

CRASRV.properties is located in /etc/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details. You can edit the file with the TSO OEDIT command.

**Note:** The RSED started task must be restarted before changes are in effect.

```
# CRASRV.properties - CARMA configuration options
#
port.start=5227
port.range=100
startup.script.name=/usr/lpp/rdz/bin/carma.startup.rex
clist.dsname='FEK.#CUST.CNTL(CRASUBMT) '
crastart.stub=/usr/lpp/rdz/bin/CRASTART
crastart.configuration.file=/etc/rdz/crastart.conf
crastart.syslog=Partial
crastart.timeout=420
#crastart.steplib=FEK.SFEKLPA
#crastart.tasklib=TASKLIB
```

Figure 19. CRASRV.properties – CARMA configuration file

### port.start

First port used for communication between CARMA and the RSE server. The default port is 5227. Communication on this port is confined to your host machine.

**Note:** Before selecting a port, verify that the port is available on your system with the **NETSTAT** and **NETSTAT PORTL** commands. See “Reserved TCP/IP ports” in the *Host Configuration Reference* (SC14-7290) for more information.

### port.range

Range of ports, starting at port.start, which will be used for CARMA communication. The default is 100. For example, when using the defaults, port 5227 until 5326 (inclusive) can be used by CARMA.

### startup.script.name

Defines the absolute path of the CARMA startup script. The default is /usr/lpp/rdz/bin/carma.startup.rex. This REXX exec will trigger the startup of a CARMA server.

### clist.dsname

Defines the startup method for the CARMA server. Refer to “Select server startup method and active RAM” on page 46 for more details about the different startup methods.

- \*CRASTART indicates that the CARMA server should be started as a subtask within RSE using CRASTART. If you specify \*CRASTART, you must also specify the crastart.\* directives.
- \*ISPF indicates that the CARMA server should be started using ISPF's TSO/ISPF Client Gateway. This startup method is deprecated.

- Any other value defines the location of the CRASUBMT CLIST, using TSO-like naming conventions. With quotes (') the data set name is an absolute reference, without quotes (') the data set name is prefixed with the client's user ID, not the TSO prefix. The latter requires that all CARMA users must maintain their own CRASUBMT CLIST.

The default is FEK.#CUST.CNTL(CRASUBMT). This CLIST will use the batch submit method to start a CARMA server that supports the sample RAMs.

The default is 'FEK.#CUST.CNTL(CRASUBMT)'. This CLIST will start a CARMA server when opening a connection using the batch submit method.

#### **crastart.stub**

z/OS UNIX stub for calling CRASTART. The default is /usr/lpp/rdz/bin/CRASTART. This stub makes the MVS based CRASTART load module available to z/OS UNIX processes. This directive is only used if the clist.dsname directive has \*CRASTART as value.

#### **crastart.configuration.file**

Specifies the name of the CRASTART configuration file. The default is /etc/rdz/crastart.conf. This file specifies the data set allocations and program invocations needed to start a CARMA server. This directive is only used if the clist.dsname directive has \*CRASTART as value.

#### **crastart.syslog**

Specifies how much information is written to the system log while CRASTART starts a CARMA server. The default is Partial. Valid values are:

A (All)	All tracing information is printed to SYSLOG
P (Partial)	Only connect, disconnect, and error information is printed to SYSLOG
anything else	Only error conditions are printed to SYSLOG

This directive is only used if the clist.dsname directive has \*CRASTART as value.

#### **crastart.timeout**

The length of time, in seconds, before a CARMA server ends due to lack of activity. The default is 420 (7 minutes). This directive is only used if the clist.dsname directive has \*CRASTART as value.

**Note:** System abend 522 for module CRASERV will occur if the JWT parameter in the SMFPRMxx parmlib member is set to a value lower than the crastart.timeout value in CRASRV.properties. This does not impact CARMA operations, because the server is restarted automatically if needed.

#### **crastart.steplib**

The location of the CRASTART module when accessed through the STEPLIB directive in rsed.envvars. The default is FEK.SFEKLPA. Uncomment and customize this directive if the CRASTART module cannot be part of LPA or LINKLIST. Note that program control and APF issues might arise if the CRASTART module is not in LPA. This directive is only used if the clist.dsname directive has \*CRASTART as value.

#### **crastart.tasklib**

Alternate name for the TASKLIB DD name in crastart.conf. The default is TASKLIB. Uncomment and customize this directive if DD name TASKLIB

has a special meaning for your SCM or RAM and cannot be used as STEPLIB replacement. This directive is only used if the `clist.dsnname` directive has `*CRASTART` as value.

## **crastart\*.conf, CRASTART server startup**

RSE invokes load module CRASTART, which uses the definitions in `crastart*.conf` to create a valid environment to execute batch TSO and ISPF commands. Developer for System z uses this environment to run the CARMA server, CRASERV.

`crastart*.conf` is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

**Note:** Changes are in effect for all CARMA servers started after the update.

Developer for System z provides multiple `crastart*.conf` configuration files. Each of these sample files is preconfigured for a specific customization scenario:

- `crastart.endevor.conf` is configured for CRASTART startup with CA Endevor® SCM RAM.
- `crastart.conf` is configured for CRASTART startup with sample RAMs.

The function of the `crastart*.conf` file is similar in concept to a JCL job stream, but is more restrictive.

- The following samples show valid line formats:
  - `* comment`
  - `ddname=dsn1,dsn2,dsn3`                      `* comment`
  - `ddname=SYSOUT(c)`                              `* comment`
  - `ddname=DUMMY`                                  `* comment`
  - `-COMMAND=<any bpxwdyn command>` `* comment`
  - `PROGRAM = progname parms`                  `* comment`

**Note:** The **BPXWDYN** command is documented in *Using REXX and z/OS UNIX System Services* (SA22-7806) and allows complex allocation constructs.

- All input is translated to upper case.
- Line continuations are not supported.
- There is no limitation on line length.
- One or more blank spaces ( ) are allowed around the equal sign (=).
- DD allocations must precede the related PROGRAM statement.
- DD names allocated here are freed at the end of program execution (they do not accumulate).
- DD names allocated by the invoked programs are NOT freed.
- Multiple data sets can be concatenated to a DD name. The data set names must be separated by a comma (,), and the concatenation will be searched in the listed order.
- All data set allocations are done with `DISP=SHR`, except for allocations done using `-COMMAND`.
- Inline data is not supported, all data must be in cataloged files.
- Variables can only be used on the right side of the equal sign (=)
- The following variables are supported:

&CRAUSER.	client user ID
&CRADATE.	current date in Dyyyymmdd format (7 char Julian)
&CRATIME.	current time in Thhmmss format (hour min sec)
&CRAPRM1.	port number
&CRAPRM2.	timeout value
System symbol	any SYS1.PARMLIB(IEASYMxx) system symbol
-<ddname>	A dash (-) followed by a previously defined DD name acts like a *.ddname backward reference in JCL. The original DD must be allocated using the -COMMAND statement.

**Note:** There is no variable for the TSO prefix, because TSO is not active when the configuration file is interpreted. Refer to “(Optional) Custom allocation exec” on page 70 if you have a need for the TSO prefix or other variable that is not available.

Figure 20 shows a basic crastart\*.conf skeleton that includes ISPF services.

```
* DD used by RAM

* DD used by CARMA server (CRASERV)
TASKLIB = FEK.SFEKLOAD
CRADEF  = FEK.#CUST.CRADEF
CRAMSG  = FEK.#CUST.CRAMSG
CRASTRS = FEK.#CUST.CRASTRS
CARMALOG= SYSOUT(H)
SYSPRINT= SYSOUT(H)

* DD used by ISPF (ISPSTART)
-COMMAND=ALLOC FI(ISPCTL0) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPCTL1) NEW DELETE DSORG(PS) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA)
-COMMAND=ALLOC FI(ISPPROF) NEW DELETE DSORG(PO) RECFM(F,B) LRECL(80)
  BLKSIZE(32720) SPACE(5,5) TRACKS UNIT(SYSALLDA) DIR(5)
ISPTABL = -ISPPROF
ISPTLIB = -ISPPROF,ISP.SISPTENU
ISPMLIB = ISP.SISPMENU
ISPPLIB = ISP.SISPPENU
ISPSLIB = ISP.SISPSENU

* DD used by TSO (IKJEFT01)
SYSTSIN = DUMMY
SYSPRINT= SYSOUT(H)

PROGRAM=IKJEFT01 ISPSTART PGM(CRASERV) PARM(&CRAPRM1. &CRAPRM2.)
```

*Figure 20. crastart\*.conf - CARMA server startup using CRAFTART*

**Note:**

- Due to page width limitations, some lines in the sample wrapped onto the next line. All lines that start with an indentation should be added to the end of the previous line.
- You can add your own DD statements and data set concatenations to customize the CARMA TSO environment, thus mimicking a TSO logon procedure.
- DD name TASKLIB acts like STEPLIB in JCL. Its DD name must match the value specified for crastart.tasklib in CRASRV.properties, which is described in “CRASRV.properties, RSE interface to CARMA” on page 56.

- Regular APF rules apply for TASKLIB allocations. Libraries lose their APF authorization when a non-APF authorized library is part of the concatenation.
- System abend 522 for module CRASERV will occur if the JWT parameter in the SMFPRMxx parmlib member is set to a value lower than the crastart.timeout value in CRASRV.properties. This does not impact CARMA operations, because the server is restarted automatically if needed.
- Details of the CARMA server startup are shown in rsecomm.log (when the server ends). Refer to “(Optional) rsecomm.properties, RSE tracing” on page 96 for more information on setting the detail level of rsecomm.log.

## Collecting CRASTART log files

CRASTART creates a TSO environment as a child process of RSE, which will run in a separate address space. Non-trivial actions might be needed to keep the CARMA output sent to SYSOUT(\*), which complicates collecting log files. This can be resolved by writing the log files to a (user-specific) data set, as shown in the following sample allocation:

```
-COMMAND=ALLOC FI(CARMALOG) MOD CATALOG DSORG(PS) RECFM(F,B) LRECL(133)
  BLKSIZE(27930) SPACE(5,5) TRACKS UNIT(SYSALLDA)
  DA(&CRAUSER..&SYSNAME..CRA.CARMALOG)
```

### Note:

- Due to page width limitations, some lines in the sample wrapped onto the next line. All lines that start with an indentation should be added to the end of the previous line.
- This log file must be allocated using the -COMMAND statement to be able to create user specific log files.
- You can also allocate the log data sets in an allocation exec if you need more flexibility (for example, only send the log to a data set for specific users). Refer to “(Optional) Custom allocation exec” on page 70 for more information on allocation execs.

When writing log files to SYSOUT, you should be aware that SYSOUT allocated by z/OS UNIX processes is treated as special output in JES. This is similar to SYSOUT allocated by APPC transactions.

- While the CARMA server is still active, the output can be seen using the **DA** command in SDSF. The job will have the user's user ID followed by a random one-digit number as job name and an STC job ID. The user will be the job owner.
- When the CARMA server ends, due to inactivity or the user ending the connection, the output can be seen using the **APPC ON** and **H ALL** commands in SDSF, if the output was written to a HOLD output class. The job name, job ID, and job owner remain the same. Each DD will show up as a separate spool file, without any indication which DD it is.

## CRASUB\*, batch submit server startup

RSE invokes CLIST CRASUB\*, which in turn submits an embedded JCL to create a valid environment to execute batch TSO and ISPF commands. Developer for System z uses this environment to run the CARMA server, CRASERV.

CRASUB\* is located in FEK.#CUST.CNTL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

**Note:** Changes are in effect for all CARMA servers started after the update.

Developer for System z provides multiple CRASUB\* JCL jobs. Each of these sample files is pre-configured for a specific customization scenario:

- CRASUBCA is configured for batch startup with CA Endeavor® SCM RAM
- CRASUBMT is configured for batch startup with sample RAMs

Figure 21 shows a basic CRASUB\* skeleton that includes ISPF services.

```
PROC 1 PORT TIMEOUT(420)
SUBMIT * END($$)
//CRA&PORT JOB CLASS=A,MSGCLASS=A,MSGLEVEL=(1,1)
//*
//RUN      EXEC PGM=IKJEFT01,DYNAMNBR=125,REGION=0M,TIME=NOLIMIT
//*
//* DD used by RAM
//*
//* DD used by CARMA server (CRASERV)
//STEPLIB DD DISP=SHR,DSN=FEK.SFEKLOAD
//CRADEF  DD DISP=SHR,DSN=FEK.#CUST.CRADEF
//CRAMSG  DD DISP=SHR,DSN=FEK.#CUST.CRAMSG
//CRASTRS DD DISP=SHR,DSN=FEK.#CUST.CRASTRS
//CARMALOG DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//*
//* DD used by ISPF (ISPSTART)
//ISPPROF DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(1,1,5))
//ISPCTL0 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPCTL1 DD DISP=(NEW,DELETE,DELETE),UNIT=SYSALLDA,
//          LRECL=80,RECFM=FB,SPACE=(TRK,(5,5))
//ISPMLIB DD DISP=SHR,DSN=ISP.SISPMENU
//ISPPLIB DD DISP=SHR,DSN=ISP.SISPPENU
//ISPSLIB DD DISP=SHR,DSN=ISP.SISPSENU
//ISPTLIB DD DISP=SHR,DSN=ISP.SISPTENU
//*
//* DD used by TSO (IKJEFT01)
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
ISPSTART PGM(CRASERV) PARM(&PORT &TIMEOUT)
$$
EXIT CODE(0)
```

*Figure 21. CRASUB\* - CARMA startup using batch submit*

**Note:**

- You can add your own DD statements and data set concatenations to customize the CARMA TSO environment, thus mimicking a TSO login procedure.
- You can optionally change CARMA's timeout value by modifying the PROC 1 PORT TIMEOUT(420) line in the CRASUB\* CLIST. The timeout value is the number of seconds CARMA will wait for the next command from the client. Setting a value of 0 results in the default timeout value, currently 420 seconds (7 minutes).
- Details of the CARMA startup process are shown in rsecomm.log (when the server ends). Refer to “(Optional) rsecomm.properties, RSE tracing” on page 96 for more information on setting the detail level of rsecomm.log.

## CARMA VSAM data sets

The CARMA server requires READ access to three VSAM data sets. The sample members to create and populate these VSAM data sets are located in



FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

**Note:**

- Refer to sample job FEK.#CUST.JCL(CRA#UADD) if you need to merge the definitions for a (custom) RAM into an existing VSAM configuration. This job must be customized and submitted for each CARMA VSAM file that changes. Refer to the *Common Access Repository Manager Developer’s Guide* (SC23-7660) for more information on the record structure used by the different CARMA VSAM files.
- Use sample job FEK.#CUST.JCL(CRA#UQRY) to extract the active definitions from a VSAM to a sequential data set.

### **CRADEF, configuration data set**

This VSAM data set describes the functions supported by the defined RAMs. Note that RAM developers require UPDATE access to this data set. The data set can be created by one of these sample jobs:

- CRA\$VCAD populates the data set with CA Endeavor® SCM RAM data.
- CRA\$VDEF populates the data set with sample RAM data.

### **CRAMSG, message data set**

This VSAM data set holds messages issued by the CARMA server itself. The data set can be created by one of these sample jobs:

- CRA\$VMSG populates the data set with generic server data.

### **CRASTRS, custom string data set**

This VSAM data set holds the messages issued by the defined RAMs. Note that RAM developers require UPDATE access to this data set. The data set can be created by one of these sample jobs:

- CRA\$VCAS populates the data set with CA Endeavor® SCM RAM data.
- CRA\$VSTR populates the data set with sample RAM data.

### **CARMA VSAM migration notes**

Beginning with version 7.6.1, Developer for System z supports a new data structure layout for the CARMA custom information VSAM data set, CRASTRS, to remove message length limitations.

Prior to Developer for System z version 7.6.1, strings defined in the CARMA custom information VSAM data set are limited to predefined lengths. This limitation forces RAM developers to shorten descriptive strings, or to use client-side plug-ins to display full-length strings.

The new VSAM record structure supports a variable-length data structure layout for the CARMA custom information VSAM data set, CRASTRS, where strings are separated by a delimiter character instead of being fixed length.

Customize and submit the FEK.SFEKSAMP(CRA#VS2) JCL to convert your existing, fixed-length, CARMA custom information VSAM data set, CRASTRS, to the new variable-length format.

**Note:**

- Beginning with version 7.6.1, the sample CARMA custom information VSAM data set is shipped in variable-length format.



- Beginning with version 7.6.1, the CARMA load module, CRASERV, supports both the fixed-length format and the variable-length format for the CARMA custom information VSAM data set.
- Older versions of the CARMA load module do not support the variable-length format and will produce garbled strings when used with a variable-length CARMA custom information VSAM data set.

## CARMA Repository Access Managers (RAMs)

A Repository Access Manager (RAM) is an Application Programming Interface (API) for a z/OS based Software Configuration Manager (SCM). In turn, Developer for System z (or user-written applications) can start a CARMA server which loads the RAMs and provides a standard interface to access any supported SCM.

The CARMA server must be able to find the RAM load modules, either through LINKLIST or STEPLIB/TASKLIB.

The CRAR\* RAM load modules provided by Developer for System z are located in FEK.SFEKLOAD, and the sample source code and compile jobs are located in FEK.SFEKSAMP, unless you used a different high level qualifier during the SMP/E install of Developer for System z.

The following sections have customization notes for the RAMs that are available with Developer for System z. The referenced sample members are located in FEK.#CUST.\*, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

See *Common Access Repository Manager Developer's Guide* (SC23-7660) for in-depth knowledge of CARMA and for more information on the sample RAMs and sample source code provided.

### CA Endeavor® SCM RAM

- Production-type RAM.
- The CA Endeavor® SCM RAM gives Developer for System z clients direct access to CA Endeavor® SCM.
- The load module name is CRARNDVR.
- The CA Endeavor® SCM RAM has many additional settings compared to a vanilla CARMA setup. You should use one of the preconfigured setups that support the CA Endeavor® SCM RAM as starting point, and customize it further to fit your needs.
- The (deprecated) TSO/ISPF Client Gateway startup method can not be used together with the CA Endeavor® SCM RAM.
- The CA Endeavor® SCM RAM has two configuration files, FEK.#CUST.PARMLIB(CRASHOW) and FEK.#CUST.PARMLIB(CRATMAP), that can be customized. Refer to “CRASHOW and CRATMAP, CA Endeavor® SCM RAM configuration files” on page 65 for more information.
- The CA Endeavor® SCM RAM has an allocation exec, FEK.SFEKPROC(CRANDVRA), that can be customized. Refer to “CRANDVRA, CA Endeavor® SCM RAM allocation exec” on page 65 for more information.
- The CA Endeavor® SCM RAM supports doing CA Endeavor® SCM actions in batch (background) mode. Batch-actions requires a configuration file,

FEK.#CUST.PARMLIB(CRABCFG), and a skeleton JCL, FEK.#CUST.CNTL(CRABATCA), that must be customized. See “CA Endeavor® SCM RAM batch actions” on page 66 for more information.

## CA Endeavor® SCM packages RAM

- Production-type RAM.
- The CA Endeavor® SCM packages RAM gives Developer for System z clients direct access to CA Endeavor® SCM packages.
- The load module name is CRARPKGS.
- The CA Endeavor® SCM packages RAM has no customizable settings, and must be used in combination with the CA Endeavor® SCM RAM.

## PDS RAM

- Sample RAM, do not use in a production environment.
- The PDS RAM gives a data set list similar to **MVS Files -> My Data Sets** in the Remote Systems view.
- The load module name is CRARPDS.
- The PDS RAM expects that ISPF services are available.
- The PDS RAM requires an additional VSAM data set to be allocated to DD CRARAM1. This VSAM data set can be allocated and primed with sample job FEK.#CUST.JCL(CRA#VPDS). Refer to the documentation within the member for customization instructions.
- Source code and compile jobs are available in FEK.SFEKSAMP. See *Common Access Repository Manager Developer's Guide* (SC23-7660) for more information.

## Skeleton RAM

- Sample RAM, do not use in a production environment.
- The skeleton RAM gives a functional framework that can be used as starting point to develop your own RAM.
- The load module name is CRARTEST.
- Source code and compile jobs are available in FEK.SFEKSAMP. See *Common Access Repository Manager Developer's Guide* (SC23-7660) for more information.

## SCLM RAM

- Sample RAM, do not use in a production environment.
- The SCLM RAM gives a basic entry into SCLM, ISPF's Software Configuration Manager. This RAM is not enabled by default.
- The load module name is CRARSCLM.
- The SCLM RAM expects that ISPF services are available.
- The SCLM RAM requires an additional VSAM data set to be allocated to DD CRARAM2. This VSAM data set can be allocated and primed with sample job FEK.#CUST.JCL(CRA#VSLM). Refer to the documentation within the member for customization instructions.
- The SCLM RAM expects that various user-specific data sets exist. Customize FEK.#CUST.JCL(CRA#ASLM) to allocate these data sets. Refer to the documentation within the member for customization instructions. Each user must submit CRA#ASLM once before using CARMA with the SCLM RAM. Failing to do so will result in an allocation error.
- The SCLM RAM is not enabled by default. To enable the RAM, it must be defined in the CARMA VSAM data sets referenced by DD CRADEF and CRASTRS. Use sample job FEK.#CUST.JCL(CRA#UADD) to merge FEK.SFEKVSM2(CRA0SLMD) into

CRADEF and FEK.SFEKVSM2(CRA0SLMS) into CRASTRS. Refer to the documentation within the member for customization instructions.

- Source code and compile jobs are available in FEK.SFEKSAMP. See *Common Access Repository Manager Developer's Guide* (SC23-7660) for more information.

## CRASHOW and CRATMAP, CA Endeavor® SCM RAM configuration files

The following CA Endeavor® SCM RAM specific CARMA components can be customized, regardless of the chosen server startup method. The sample members referenced below are located in FEK.#CUST.PARMLIB, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

### CRASHOW, CA Endeavor® SCM RAM default filters

CRASHOW defines default filters for CA Endeavor® SCM environments, systems, and so forth. Refer to the documentation within the member for customization instructions if you want to change the defaults.

```
ENV=*
TOENV=
STGID=*
TOSTGID=
SYS=*
SUBSYS=*
ELEM=*
TOELEM=
TYPE=*
```

Figure 22. CRASHOW - CA Endeavor® SCM RAM default filters

### CRATMAP, CA Endeavor® SCM RAM file extension mappings

CRATMAP overrides CA Endeavor® SCM type to file extension mappings. Refer to the documentation within the member for customization instructions if you want to change the defaults.

```
# *      = cbl
# COBOL  = cbl
# COPY   = cpy
# ASM    = asm
# MACRO  = asm
# PROCESS = jcl
```

Figure 23. CRATMAP - CA Endeavor® SCM RAM default filters

## CRANDVRA, CA Endeavor® SCM RAM allocation exec

Both the batch submit and the CRASTART startup method invoke REXX exec CRANDVRA to allocate user-specific data sets used by CA Endeavor® SCM RAM. The allocations are done in a separate exec, as an exec allows more flexibility than what is possible within the batch submit CRASUBCA JCL and CRASTART crastart.endeavor.conf configuration file.

DD	Data set name	Type
DEPEND	&SYSPREF..&SYSUID.. &SYSNAME..CRA\$NDVR.DEPEND	Permanent
BROWSE	&SYSPREF..&SYSUID.. &SYSNAME..CRA\$NDVR.BROWSE	Temporary

DD	Data set name	Type
C1PRINT	&SYSPREF..&SYSUID.. &SYSNAME..CRA\$NDVR.LISTING	Temporary
SPCLLIST	&SYSPREF..&SYSUID.. &SYSNAME..CRA\$NDVR.SPCLLIST	Temporary
PKGSCLS	&SYSPREF..&SYSUID.. &SYSNAME..CRA\$NDVR.PKGSCLS	Temporary

You can customize a copy of this allocation REXX exec if certain defaults, such as the data set name, do not match your site standards. CRANDVRA is located in FEK.SFEKPROC, unless you used a different high level qualifier during the SMP/E install of Developer for System z.

Refer to the documentation within the member for customization instructions. Refer to “(Optional) Custom allocation exec” on page 70 for more information on allocation execs.

**Note:** You should copy the sample allocation REXX to a new data set and customize this copy to avoid overwriting it when applying maintenance. When you do this, you must update the reference to SFEKPROC in the SYSEXEC DD of your chosen CARMA startup method to match your new data set name.

## CA Endeavor® SCM RAM batch actions

Normally, CA Endeavor® SCM actions like “Generate Element” are executed “online”, in the CARMA server address space. This causes problems if your CA Endeavor® SCM procedures invoke TSO, because TSO is already active and that means required DDs such as SYSTSIN and SYSTSPRT are in use.

To resolve this problem, the CA Endeavor® SCM RAM supports “batch actions” since version 8.0.3. When batch-actions is enabled, the CA Endeavor® SCM RAM will submit a (customizable) batch job to perform actions like “Generate Element”. This allows the allocation of DDs like SYSTSIN and SYSTSPRT by your CA Endeavor® SCM procedures, because the submitted JCL does not require TSO to be active.

Note that CA Endeavor® SCM RAM batch-actions are the Developer for System z equivalent of background CA Endeavor® SCM actions.

When a request is issued to execute an action that is supported by batch-actions, the CA Endeavor® SCM RAM will check for the existence of the CRABCFG DD (in CRASUBCA or crastart.endeavor.conf) and will check that the setup behind this DD is valid. If CRABCFG is there and the setup is valid, the action will be performed in batch. If CRABCFG is not there, the action will be performed online. Note that version 8.0.3 or higher clients can override this behavior.

For example:

```
//* uncomment CRABCFG and CRABSKEL to use batch actions
//*CRABCFG DD DISP=SHR,DSN=FEK.#CUST.PARMLIB(CRABCFG)
//*CRABSKEL DD DISP=SHR,DSN=FEK.#CUST.CNTL
```

**Note:**

- The TSO-free environment is only available for selected CA Endeavor® SCM actions. Batch-actions does not support a TSO-free environment outside this scope.

- The CRABCFG configuration file documents which CA Endeavor<sup>®</sup> SCM actions are currently supported.
- A functional sample job, FEK.#CUST.CNTL(CRABATCA), is provided to execute the batch actions, but the intent of batch-actions is that this sample is customized to invoke your current CA Endeavor<sup>®</sup> SCM procedures.
- Ensure that there are sufficient JES initiators available in the class used to submit the batch-action JCLs.
- When using JES in a SYSPLEX environment, ensure that the job runs on the current system, or that the completion information is routed back to the system hosting Developer for System z, so that the CA Endeavor<sup>®</sup> SCM RAM can check the status.

### **CRABCFG, CA Endeavor<sup>®</sup> SCM RAM batch-action configuration**

CRABCFG defines the configuration variables related to CA Endeavor<sup>®</sup> SCM RAM batch-actions.

CRABCFG is located in FEK.#CUST.PARMLIB, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

See the following sample CRABCFG file, which must be customized to match your system environment. Comment lines start with a pound sign (#), when using a US code page. Comments behind a directive and its assigned value are supported. Spaces around the equal sign (=) are supported. Line continuations are not supported.

**Note:** Changes are in effect for all CARMA servers started after the update.

```
# Location of batch action JCL
SKELETON-DD = CRABSKEL
#
# batch action JCL members within SKELETON-DD
ADD-ELEMENT      = CRABATCA
GENERATE-ELEMENT = CRABATCA
#
# Command substitution key within batch action JCL
BSTIPT01-KEY = <CRA_BSTIPT01>
```

*Figure 24. CRABCFG - CA Endeavor<sup>®</sup> SCM RAM batch-action configuration*

#### **SKELETON-DD**

Name of the DD statement that references one or more PDS(E) data sets holding the batch-action skeleton JCLs. The sample value is CRABSKEL. Can be changed if desired. This DD must be defined to the CARMA server in CRASUBCA or crastart.endevor.conf.

#### **GENERATE-ELEMENT and other CA Endeavor<sup>®</sup> SCM actions**

The key names represent the CA Endeavor<sup>®</sup> SCM actions that are supported by batch-action and cannot be changed. The value assigned to each key is the member name of the related skeleton JCL. The sample value is CRABTCA for all keys. Can be changed if desired.

#### **BSTIPT01-KEY**

Substitution key for the actual CA Endeavor<sup>®</sup> SCM command string. The sample value is <CRA\_BSTIPT01>. Can be changed if desired. The first occurrence (that is not part of a comment) of this substitution key within

the skeleton JCL will be replaced by the command string that will instruct CA Endeavor® SCM to do the requested action against the requested element.

## CRABATCA, CA Endeavor® SCM RAM batch action JCL

CRABATCA is a sample skeleton JCL used for batch-actions. See the documentation within the member for customization instructions if you want to change the defaults.

CRABATCA is located in FEK.#CUST.CNTL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP (FEKSETUP). See “Customization setup” on page 11 for more details.

**Note:** Changes are in effect for all CARMA servers started after the update.

```
//<USERID>B JOB CLASS=A,MSGCLASS=A,MSGLEVEL=(1,1)
//*
//CRABATCA EXEC PGM=NDVRC1,DYNAMNBR=1500,REGION=4096K,PARM='C1BM3000'
//STEPLIB DD DISP=SHR,DSN=CA.NDVRU.AUTHLIB * NDVR R12
// DD DISP=SHR,DSN=CA.NDVR.AUTHLIB * NDVR R12
//* DD DISP=SHR,DSN=CA.NDVR.CSIQAUTU * NDVR R14
//* DD DISP=SHR,DSN=CA.NDVR.CSIQAUTH * NDVR R14
//CONLIB DD DISP=SHR,DSN=CA.NDVR.CONLIB * NDVR R12
//*CONLIB DD DISP=SHR,DSN=CA.NDVR.CSIQLOAD * NDVR R14
//C1MSG1 DD SYSOUT=*
//C1MSG2 DD SYSOUT=*
//C1PRINT DD SYSOUT=*,DCB=(RECFM=FBA,LRECL=133)
//SYSOUT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSUDUMP DD SYSOUT=*
//SYMDUMP DD DUMMY
//SYSIN DD DUMMY
//BSTIPT01 DD *
SET STOPRC 16 .
<CRA_BSTIPT01>
//*
```

Figure 25. CRABATCA - CA Endeavor® SCM RAM batch-action JCL

## CARMA return codes

CARMA can report various error codes to the client or in the host logs. The details provided with the error, and the information in Table 10, can help you locate the error and work towards a resolution.

Table 10. CARMA return codes

Error range	Error type
4-99	Generic CARMA errors
100-199	Generic RAM errors
200-399	CRASERV (CARMA server) errors
400-499	RSE (CARMA miner) errors
500-899	RAM specific errors
900-999	TSO and TCP/IP errors

Some common return codes are:

- 220: CARMA server ends due to inactivity timeout (this is not an error)



- 990: CARMA server is unable to connect to the port on which CARMA miner is listening

---

## (Optional) Supporting multiple RAMs

CARMA allows that multiple RAMs are defined and can run them concurrently. However, since there is only one CARMA server active per user, even when there are multiple RAMs, some configuration changes might be required to make this setup work.

RAMs are defined by a RAM developer in the CARMA configuration VSAM data set, CRADEF. During startup, the CARMA server, CRASERV, will identify all defined RAMs and present the information to the CARMA client. The user can then select one or more RAMs, which will be loaded into the CARMA server.

Since RAMs are active as plug-ins of the CARMA server, you must ensure that all prerequisites (such as data set allocations) for each of the RAMs are available in the address space of the CARMA server. This might require changes to the CARMA configuration samples, such as CRASUBMT or crastart.conf, which are shipped with Developer for System z.

### Example

In the following example, you start from an existing setup with the CA Endevor<sup>®</sup> SCM RAM, using the CRASTART startup method, and add the sample PDS RAM.

Definitions for the CA Endevor<sup>®</sup> SCM RAM:

- FEK.SFEKVSM2(CRA0VCAD) - CRADEF definitions
- FEK.SFEKVSM2(CRA0VCAS) - CRASTRS definitions
- /etc/rdz/crastart.endevor.conf - CRASTART configuration file

Definitions for the PDS RAM:

- FEK.SFEKVSM2(CRA0VDEF) - CRADEF definitions
- FEK.SFEKVSM2(CRA0VSTR) - CRASTRS definitions
- FEK.#CUST.CRARAM1 - CRARAM1 definitions

The process starts with a RAM developer gathering the data and information needed by the system programmer to complete the setup.

1. Extract the data specific for the PDS RAM from the SFEKVSM2 members (these members hold definitions for all sample RAMs, not just the PDS RAM).
2. Merge this data with the CA Endevor<sup>®</sup> SCM RAM SFEKVSM2 members.
3. Create a list of PDS RAM specific prerequisites:
  - DD CRARAM1, linked to FEK.#CUST.CRARAM1
  - TSO environment

The system programmer then uses this data to create the updated CARMA VSAM data sets and uses the prerequisite information to create a CRASTART configuration file that is capable of supporting both RAMs.

1. Use the combined data as input for the CRA\$VDEF and CRA\$VSTR jobs to create the updated CARMA configuration and custom information VSAM data sets, CRADEF and CRASTRS. The CRAMSG VSAM is specific for the CARMA server, and thus identical for both RAMs.
2. Add a CRARAM1 definition to crastart.endevor.conf:

```
CRARAM1 = FEK.#CUST.CRARAM1
```

3. Verify the PROGRAM statement in crastart.endevor.conf to ensure it is capable of providing the environment needed by both RAMs:

```
PROGRAM=IKJEFT01 %CRANDVRA NDVRC1 PGM(CRASERV)  
PARM(&CRAPRM1. &CRAPRM2.)
```

- IKJEFT01: TSO, used to allow certain authorized calls in a non-authorized environment, and used as environment to run the CA Endeavor® SCM RAM pre-allocation exec.
- %CRANDVRA: CA Endeavor® SCM RAM pre-allocation exec (located in FEK.SFEKPROC), that allocates temporary user-specific working data sets.
- NDVRC1: CA Endeavor® back end, which has a built in mechanism to execute TSO and ISPF commands.
- PGM(CRASERV): command to start a CARMA server, in ISPF command format
- PARM(&CRAPRM1. &CRAPRM2.): parameters for CRASERV, in ISPF command format. &CRAPRM1 is the port to be used and &CRAPRM2 is the timeout value.

The CA Endeavor® SCM RAM is active in an ISPF environment, which implies that the TSO environment required by the PDS RAM is also available.

---

## (Optional) Custom allocation exec

All CARMA server startup methods have limitations when it comes to data set allocation. For example, TSO prefix substitution is not available in JCL or CRASTART.

However, by creating an exec that is invoked after TSO starts (or ISPF, depending on your needs) and before CARMA is started, you can use the whole range of variables and services available in TSO (or ISPF) to do the desired allocations.

To simplify the setup, the allocation exec should accept the actual startup command as argument and execute it after all allocations are done.

**Note:** When creating an allocation exec, ensure you do not destroy allocations done earlier in the CARMA startup process by CRASTART or your startup JCL.

FEK.SFEKPROC(CRANDVRA), the allocation exec for CA Endeavor® SCM RAM, uses this technique to allocate cataloged temporary data sets that have the user's TSO prefix as high level qualifier.

The following samples show how to invoke an allocation exec that only requires TSO. Refer to FEK.SFEKPROC(CRANDVRA) for a sample on how to code the exec.

crastart\*.conf

```
SYSPROC = my.exec.library  
PROGRAM = IKJEFT01 %myexec ISPSTART PGM(CRASERV) PARM(&CRAPRM1.  
&CRAPRM2.)
```

CRASUB\*

```
//SYSPROC DD DISP=SHR,DSN=my.exec.library  
//SYSTSIN DD *  
%myexec ISPSTART PGM(CRASERV) PARM(&PORT &TIMEOUT)  
/*
```

**Note:** Output generated by the allocation exec is shown in DD SYSTSPRT of the CARMA server.



---

## (Optional) IRXJCL versus CRAXJCL

If the CARMA server is started using TSO (IKJEFTxx), you might experience problems if your RAMs call services which in turn call the IRXJCL REXX batch interface. The problem can occur when the processors called by the RAM previously ran either without TSO, or only in online TSO and dynamically allocates DD SYSTSIN or SYSTSPRT. A sample program, CRAXJCL, is provided to work around this problem.

Your processor might fail if it attempts to allocate SYSTSIN or SYSTSPRT (required for IRXJCL) because batch TSO (required for CARMA) already has those DD names allocated and open. The CRAXJCL replacement module attempts to allocate SYSTSIN and SYSTSPRT to DUMMY but ignores the errors which occur if the allocations fail. It then calls IRXJCL to do the actual work.

This means that when your processors run in a CARMA environment started by TSO, the allocations to SYSTSIN and SYSTSPRT are the same as those used by CARMA. When the processors are run outside of TSO/CARMA, the SYSTSIN and SYSTSPRT allocations will be created by CRAXJCL. Therefore, your processors must not rely on the contents of the data set allocated to SYSTSIN.

It is assumed that calls to IRXJCL use the PARM field to pass the REXX name and startup parameters, as documented in *TSO/E REXX Reference* (SA22-7790). This means that SYSTSIN can safely be used by CARMA. Any output sent to SYSTSPRT by IRXJCL will end up in CARMA's log.

Processors that call the CRAXJCL replacement module should not attempt to allocate DD SYSTSIN or SYSTSPRT before calling CRAXJCL.

### Create CRAXJCL

The CRAXJCL replacement module is shipped in source format because you will need to customize it to specify the specific allocations you want to use for SYSTSPRT. SYSTSIN should usually be allocated to a dummy data set.

Sample assembler source code and a sample compile/bind job are available as FEK.#CUST.ASM(CRAXJCL) and FEK.#CUST.JCL(CRA#CIRX) respectively, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See "Customization setup" on page 11 for more details.

Customize the CRAXJCL assembler source code per your needs, using the documentation within the member. Afterwards, customize and submit the CRA#CIRX JCL to create the CRAXJCL load module. See the documentation within the member for customization instructions.

If you want to, you can rename IRXJCL to something else, adjust the CRAXJCL source to call this new name for IRXJCL and compile it, and then rename the CRAXJCL load module to IRXJCL. This setup might be easier than changing all your calls to IRXJCL.



---

## Chapter 4. (Optional) SCLM Developer Toolkit

SCLM Developer Toolkit provides the tools needed to extend the capabilities of SCLM to the client. SCLM itself is a host-based source code manager that is shipped as part of ISPF.

The SCLM Developer Toolkit has an Eclipse-based plugin that interfaces to SCLM and provides for access to all SCLM processes for legacy code development as well as support for full Java and J2EE development on the workstation with synchronization to SCLM on the mainframe including building, assembling, and deployment of the J2EE code from the mainframe.

---

### Requirements and checklist

You will need assistance of an SCLM administrator and optionally a security administrator to complete this customization task, which requires the following resources and special customization tasks:

- APF and LINKLIST updates
- Define SCLM language translators for JAVA/J2EE support
- Define SCLM types for JAVA/J2EE support
- (Optional) Security rule to allow users update to an SCLM VSAM
- (Optional) Installation of Ant

In order to start using SCLM Developer Toolkit at your site, you must perform the following tasks. Unless otherwise indicated, all tasks are mandatory.

1. Verify and adjust prerequisites and PARMLIB updates. For details, see “Prerequisites.”
2. Customize Developer for System z configuration files. For details see:
  - “ISPF.conf updates for SCLMDT” on page 74
  - “rsed.envvars updates for SCLMDT” on page 75
3. Optionally define long/short name translation support. For details, see “(Optional) Long/short name translation” on page 75.
4. Optionally install and customize Ant to use the JAVA/J2EE build support. For details, see “(Optional) Install and customize Ant” on page 78.
5. Update SCLM to define SCLMDT-specific parts. For details, see “SCLM updates for SCLMDT” on page 79.
6. Optionally set up automation to periodically clean up the SCLMDT work area. For details, see “Remove old files from WORKAREA and /tmp” on page 80.

---

### Prerequisites

Refer to *IBM Rational Developer for System z Prerequisites* (SC23-7659) for a list of required SCLM maintenance.

This publication also documents the Ant specifications needed for JAVA/J2EE builds in SCLM Developer Toolkit.

**Attention:** SCLM Developer Toolkit requires the usage of ISPF's TSO/ISPF Client Gateway, which implies that z/OS 1.8 or higher is required.

As described in “PARMLIB changes” on page 12, SCLM Developer Toolkit requires additional customization of system settings. These changes include:

- (BPXPRMxx) Increase the maximum number of processes per z/OS UNIX user ID.
- (PROGxx) APF authorize SYS1.LINKLIB and the REXX runtime, REXX.V1R4M0.SEAGLPA or REXX.V1R4M0.SEAGALT.
- (PROGxx/LPALSTxx) Place ISP.SISPLPA, ISP.SISLOAD, SYS1.LINKLIB and the REXX runtime in LINKLIST/LPALIB.

Also, SCLM Developer Toolkit uses SDSF or the TSO **OUTPUT** command to retrieve job completion status and job output. Both methods require some additional attention:

- SDSF must be ordered, installed, and configured separately. It also requires the usage of JES2.
- The default settings for the TSO **OUTPUT** command let a user retrieve job output that begins with his user ID only. If you want to use the **OUTPUT** facility fully, then the sample TSO/E exit IKJEFF53 might need to be modified so that a user can retrieve job output he owns, but that does not begin with his user ID. For more information about this exit, refer to *TSO/E Customization* (SA22-7783).

Users require READ, WRITE, and EXECUTE permission to the z/OS UNIX directories /tmp/ and /var/rdz/WORKAREA/. Directory WORKAREA/ is located in /var/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

---

## ISPF.conf updates for SCLMDT

SCLM Developer Toolkit uses the standard ISPF/SCLM skeletons, so ensure that skeleton library ISP.SISPLIB is allocated to the ISPSLIB concatenation in ISPF.conf. The usage of the ISP.SISPSENU data set is optional.

ISPF.conf is located in /etc/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

**Note:** Changes are in effect for all clients connecting to the host after the update.

The following sample code shows the ISPF.conf file, which must be customized to match your system environment. Comment lines start with an asterisk (\*). Add data sets to the concatenation on the same line and separate the names with a comma (.). See “ISPF.conf, ISPF's TSO/ISPF Client Gateway configuration file” on page 42 for more details on customizing ISPF.conf.

```

* REQUIRED:
sysproc=ISP.SISPLIB,FEK.SFEKPROC
isplib=ISP.SISPMENU
isptlib=ISP.SISPTENU
ispplib=ISP.SISPPENU
ispslib=ISP.SISPSLIB
ispllib=ISP.SISPLLOAD

```

```

* OPTIONAL:
*allocjob = ISP.SISPSAMP(ISPZISP2)
*ISPF_timeout = 900

```

Figure 26. ISPF.conf updates for SCLMDT

**Note:**

- You can add your own DD-like statements and data set concatenations to customize the TSO environment, thus mimicking a TSO logon procedure. See "Customizing the TSO environment" in the *Host Configuration Reference* (SC14-7290) for more details.
- When you are doing batch builds, ensure that the customized version of the FLMLIBS skeleton is concatenated before the ISPF/SCLM skeleton library.  
ispslib=h1q.USERSKEL,ISP.SISPSLIB

---

## rsed.envvars updates for SCLMDT

SCLM Developer Toolkit uses some directives set in rsed.envvars to locate data sets and directories.

rsed.envvars is located in /etc/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP (FEKSETUP). See "Customization setup" on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

**Note:** The RSED started task must be restarted to pick up any changes you make.

The following code sample shows the SCLMDT directives in rsed.envvars, which must be customized to match your system environment. See "rsed.envvars, RSE configuration file" on page 27 for more details on customizing rsed.envvars.

```

_SCLMDT_CONF_HOME=/var/rdz/sclmdt
#STEPLIB=$STEPLIB:FEK.SFEKAUTH:FEK.SFEKLOAD
#_SCLMDT_TRANTABLE=FEK.#CUST.LSTRANS.FILE
#ANT_HOME=/usr/lpp/apache/Ant/apache-ant-1.7.1
_SCLMDT_BASE_HOME=$RSE_HOME
_SCLMDT_WORK_HOME=$_CMDSEV_WORK_HOME
CGI_DTWORk=$_SCLMDT_WORK_HOME

```

Figure 27. rsed.envvars updates for SCLMDT

---

## (Optional) Long/short name translation

SCLM Developer Toolkit provides the ability to store long name files (which are files with names greater than 8 characters or in mixed case) into SCLM. This is achieved through the use of a VSAM file that contains the mapping of the long file name to the 8 character member name used in SCLM.

**Note:**

- For versions previous to z/OS 1.8, this facility is provided through a base ISPF/SCLM PTF that addresses APAR OA11426.

- The long/short name translation is also used by other SCLM-related products, such as IBM SCLM Administrator Toolkit.

## **Create LSTRANS.FILE, the long/short name translation VSAM**

Customize and submit sample member FLM02LST in the ISPF sample library ISP.SISPSAMP, to create the long/short name translation VSAM. The configuration steps in this publication expect the VSAM to be named FEK.#CUST.LSTRANS.FILE, as shown in the following sample setup JCL.

```

//FLM02LST JOB <job parameters>
/*
/* CAUTION: This is neither a JCL procedure nor a complete job.
/* Before using this sample, you will have to make the following
/* modifications:
/* 1. Change the job parameters to meet your system requirements.
/* 2. Change ***** to the volume that will hold the VSAM.
/* 3. Change all references of FEK.#CUST.LSTRANS.FILE to
/*     match your naming convention for the SCLM translate VSAM.
/*
//CREATE EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
DELETE FEK.#CUST.LSTRANS.FILE
SET MAXCC=0
DEFINE CLUSTER(NAME(FEK.#CUST.LSTRANS.FILE) -
               VOLUMES(*****)) -
               RECORDSIZE(58 2048) -
               SHAREOPTIONS(3 3) -
               CYLINDERS(1 1) -
               KEYS(8 0) -
               INDEXED) -
DATA (NAME(FEK.#CUST.LSTRANS.FILE.DATA)) -
INDEX (NAME(FEK.#CUST.LSTRANS.FILE.INDEX))

/* DEFINE ALTERNATE INDEX WITH NONUNIQUE KEYS -> ESDS */

DEFINE ALTERNATEINDEX(-
               NAME(FEK.#CUST.LSTRANS.FILE.AIX) -
               RELATE(FEK.#CUST.LSTRANS.FILE) -
               RECORDSIZE(58 2048) -
               VOLUMES(*****)) -
               CYLINDERS(1 1) -
               KEYS(50 8) -
               UPGRADE -
               NONUNIQUEKEY) -
DATA (NAME(FEK.#CUST.LSTRANS.FILE.AIX.DATA)) -
INDEX (NAME(FEK.#CUST.LSTRANS.FILE.AIX.INDEX))

/*
/*
//PRIME EXEC PGM=IDCAMS,COND=(0,LT)
//SYSPRINT DD SYSOUT=*
//INITREC DD *
INITREC1
/*
//SYSIN DD *
REPRO INFILE(INITREC) -
      OUTDATASET(FEK.#CUST.LSTRANS.FILE)
IF LASTCC = 4 THEN SET MAXCC=0

BLDINDEX IDS(FEK.#CUST.LSTRANS.FILE) -
          ODS(FEK.#CUST.LSTRANS.FILE.AIX)

IF LASTCC = 0 THEN -
  DEFINE PATH (NAME(FEK.#CUST.LSTRANS.FILE.PATH) -
              PATHENTRY (FEK.#CUST.LSTRANS.FILE.AIX))
/*

```

Figure 28. FLM02LST - long/short name translation setup JCL

**Note:** Users need UPDATE authority to this VSAM data set, as described in "Security considerations" in *Host Configuration Reference* (SC14-7290).

## rsed.envvars updates for long/short name translation

Before using the long/short name translation, uncomment and set the `rsed.envvars` environment variable `_SCLMDT_TRANTABLE` to match the name of the long/short name translation VSAM.

`rsed.envvars` is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job `FEK.SFEKSAMP(FEKSETUP)`. See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

**Note:** The RSED started task must be restarted to pick up any changes you make.

---

## (Optional) Install and customize Ant

This step is only required if you plan to use the JAVA/J2EE build support in SCLM.

Apache Ant is an open source Java build tool and can be downloaded from <http://ant.apache.org/>. Ant consists of text files and scripts which are distributed in ASCII format and thus require an ASCII/EBCDIC translation to run in z/OS UNIX.

Perform the following steps to implement Ant on z/OS, and to define it to Developer for System z:

- Download, in binary format, the latest Ant compressed file into the z/OS UNIX file system. It is recommended that you download the .zip version of ANT due to problems that might be encountered on z/OS when extracting versions of suffix format `tar.gz` or `tar.bz2`.
- Open a z/OS UNIX command-line session to continue the installation, for example with the **TSO OMVS** command.
- Make a home directory for the Ant install with the **mkdir -p /home-dir** command and make it your current directory with the **cd /home-dir** command.
- Use the JAR extract command **jar -xf apache-ant-1.7.1.zip** to extract the file to the current directory. A Java bin directory must be in your local z/OS UNIX PATH to use the **jar** command. Otherwise, fully qualify the command with the Java bin location (for example, **/usr/lpp/java/J5.0/bin/jar -xf apache-ant-1.7.1.zip**).
- Convert all Ant text files to EBCDIC by (optionally customizing and) executing sample script `/usr/lpp/rdz/samples/BWBTRANT`.

**Note:** Execute this script only once. Multiple runs will corrupt your Ant install.

- To check for successful translation, locate and browse a text file within the ANT directory, such as `apache-ant-1.7.1/README`. If the file is readable, then the translation was successful.
- Use the **chmod -R 755 \*** command to enable all users to READ and EXECUTE files in the ANT directory.
- Before using Ant, set the `rsed.envvars` environment variables `JAVA_HOME` and `ANT_HOME`.
  - `JAVA_HOME` is required to point to the Java home directory, for example:  
`JAVA_HOME=/usr/lpp/java/IBM/J5.0`
  - `ANT_HOME` is required to point to the Ant home directory, for example:  
`ANT_HOME=/usr/lpp/Apache/Ant/apache-ant-1.7.1`

For example:



- TSO OMVS
- `mkdir -p /usr/lpp/apache/Ant`
- `cd /usr/lpp/apache/Ant`
- `jar -xf /u/userid/apache-ant-1.7.1`
- `/usr/lpp/rdz/samples/BWBTRANT`
- `cat ./apache-ant-1.7.1/README`
- `chmod -R 755 *`
- `oedit /etc/rsed.envvars`

To test that the Ant initialization has been successful:

- Add the Ant and Java bin directories to the environment variable PATH.

Example:

```
export PATH=/usr/lpp/apache/Ant/apache-ant-1.7.1/bin:$PATH
export PATH=/usr/lpp/java/J5.0/bin:$PATH
```

- Execute **ant -version** to display the version, if successfully installed.

Example:

```
ant -version
```

**Note:** Setting the PATH statement in this way is necessary for testing only, not for operational use.

---

## SCLM updates for SCLMDT

SCLM itself also requires customization to work with SCLM Developer Toolkit. Refer to *IBM Rational Developer for System z SCLM Developer Toolkit Administrator's Guide* (SC23-9801) for more information about the required customization tasks:

- Define language translators for JAVA/J2EE support
- Define SCLM types for JAVA/J2EE support

To complete the customization and project definition tasks, the SCLM administrator needs to know several Developer for System z customizable values, as described in Table 11.

Table 11. SCLM administrator checklist

Description	<ul style="list-style-type: none"> <li>• Default value</li> <li>• Where to find the answer</li> </ul>	Value
Developer for System z sample library	<ul style="list-style-type: none"> <li>• FEK.SFEKSAMV</li> <li>• SMP/E installation</li> </ul>	
Developer for System z sample directory	<ul style="list-style-type: none"> <li>• /usr/lpp/rdz/samples</li> <li>• SMP/E installation</li> </ul>	
Java bin directory	<ul style="list-style-type: none"> <li>• /usr/lpp/java/J5.0/bin</li> <li>• rsed.envvars - \$JAVA_HOME/bin</li> </ul>	
Ant bin directory	<ul style="list-style-type: none"> <li>• /usr/lpp/apache/Ant/apache-ant-1.7.1/bin</li> <li>• rsed.envvars - \$ANT_HOME/bin</li> </ul>	
WORKAREA home directory	<ul style="list-style-type: none"> <li>• /var/rdz</li> <li>• rsed.envvars - \$_CMDSERV_CONF_HOME</li> </ul>	

Table 11. SCLM administrator checklist (continued)

Description	<ul style="list-style-type: none"> <li>• Default value</li> <li>• Where to find the answer</li> </ul>	Value
SCLMDT project configuration home directory	<ul style="list-style-type: none"> <li>• /var/rdz/sclmdt</li> <li>• rsed.envvars - \$_SCLMDT_CONF_HOME</li> </ul>	
Long/short name translation VSAM	<ul style="list-style-type: none"> <li>• FEK.#CUST.LSTRANS.FILE</li> <li>• rsed.envvars - \$_SCLMDT_TRANTABLE</li> </ul>	

---

## Remove old files from WORKAREA and /tmp

SCLM Developer Toolkit and ISPF's TSO/ISPF Client Gateway share the same WORKAREA and /tmp directory, both of which might need a periodic cleanup. Refer to “(Optional) WORKAREA and /tmp cleanup” on page 102 for more information about this.

---

## Chapter 5. (Optional) Application Deployment Manager

Developer for System z uses certain functions of Application Deployment Manager as a common deployment approach for various components. The customization steps listed in this chapter are required if your developers use any of the following functions:

- Enterprise Service Tools
- BMS Screen Designer
- MFS Screen Designer
- CICSTS Code Generation

**Note:** Enterprise Service Tools encompasses multiple tools, such as the Service Flow Modeler (SFM) and XML Services for the Enterprise.

Customizing Application Deployment Manager adds the CICS Resource Definition (CRD) server, which runs as a CICS application on z/OS to support the following functions:

- CICS resource queries
- CICS resource definition install and uninstall requests in both CICSplex SM and non-CICSplex SM environments
- Program and mapset phase-in requests
- Pipeline scan requests
- Manifest export, import, and update requests

CICS administrators can find more information about the CRD server in "CICSTS considerations" in the *Host Configuration Reference* (SC14-7290).

---

### Requirements and checklist

You will need assistance of a CICS administrator, a TCP/IP administrator and a security administrator to complete this customization task, which requires the following resources or special customization tasks:

- TCP/IP port for external communication
- Update CICS region JCL
- Update CICS region CSD
- Define group to CICS region
- Security rule to allow administrators update to an Application Deployment Manager VSAM
- CICSTS security setup
- (Optional) Define CICS transaction names
- (Optional) Security rule to allow users update to an Application Deployment Manager VSAM

In order to start using Application Deployment Manager at your site, you must perform the following tasks. Unless otherwise indicated, all tasks are mandatory.

1. Create the CRD repository. For details, see "CRD repository" on page 82.
2. Choose the CICS interface (RESTful or Web Service) to be used. (The interfaces can co-exist). For details see "RESTful versus Web Service" on page 83.

3. If desired, do the RESTful specific customizations. For details see “CRD server using the RESTful interface” on page 83.
  - Define the CRD server to the CICS primary connection region
  - Optionally define the CRD server to CICS non-primary connection regions.
  - Optionally customize the CRD server transaction IDs.
4. If desired, do the Web Service specific customizations. For details see “CRD server using the Web Service interface” on page 84.
  - Add the (possibly customized) pipeline message handler to the CICS RPL concatenation.
  - Define the CRD server to the CICS primary connection region.
  - Optionally define the CRD server to CICS non-primary connection regions.
5. Optionally create the manifest repository. For details, see “(Optional) Manifest repository” on page 86.

---

## CRD repository

Customize and submit job ADNVCRD to allocate and initialize the CRD repository VSAM data set. Refer to the documentation within the member for customization instructions.

ADNVCRD is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

You should create a separate repository for each CICS primary connection region. Sharing the repository implies that all related CICS regions will use the same values stored in the repository.

### Note:

- An existing CRD server repository must be enlarged to enable the URIMAP support added to the Administrative utility in Developer for System z version 7.6.1. See “Administrative utility migration notes” in the *Host Configuration Reference* (SC14-7290) for more details.
- Unless notified otherwise, your current CRD server repository (holding your customized values) can be reused across Developer for System z releases.

Users require READ access to the CRD repository, CICS administrators require UPDATE access.

## CICS administrative utility

Developer for System z provides the administrative utility to let CICS administrators provide the default values for CICS resource definitions. These defaults can be read-only, or can be editable by the application developer.

The administrative utility is invoked by sample job ADNJSPAU. The usage of this utility requires UPDATE access to the CRD repository.

ADNJSPAU is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

More information is available in “CICSTS considerations” in the *Host Configuration Reference* (SC14-7290).

---

## RESTful versus Web Service

CICS Transaction Server provides in version 4.1 and higher support for an HTTP interface designed using Representational State Transfer (RESTful) principles. This RESTful interface is now the strategic CICSTS interface for use by client applications. The older Web Service interface has been stabilized, and enhancements will be for the RESTful interface only.

Application Deployment Manager follows this statement of direction and requires the RESTful CRD server for all services that are new to Developer for System version 7.6 or higher.

The RESTful and Web Service interfaces can be active concurrently in a single CICS region, if desired. In this case, there will be two CRD servers active in the region. Both servers will share the same CRD repository. Note that CICS will issue some warnings about duplicate definitions when the second interface is defined to the region.

---

## CRD server using the RESTful interface

The information in this section describes how to define the CRD server that uses the RESTful interface to communicate with the Developer for System z client.

The RESTful and Web Service interfaces can be active concurrently in a single CICS region, if desired. In this case, there will be two CRD servers active in the region. Both servers will share the same CRD repository. Note that CICS will issue some warnings about duplicate definitions when the second interface is defined to the region.

### CICS primary connection region

The CRD server must be defined to the primary connection region. This is the Web Owning Region (WOR) that will process Web Service requests from Developer for System z.

- Place the load modules FEK.SFEKLOAD(ADNCRD\*, ADNANAL and ADNREST) in the CICS RPL concatenation (DD statement DFHRPL) of the CICS primary connection region. You should do this by adding the installation data set to the concatenation so that applied maintenance is automatically available to CICS.
- Customize and submit job ADNCSDRS to update the CICS System Definition (CSD) for the CICS primary connection region. Refer to the documentation within the member for customization instructions.

ADNCSDRS is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

- Use the appropriate CEDA command to install the Application Deployment Manager group for this region, for example:

```
CEDA INSTALL GROUP(ADNPCRGP)
```

### CICS non-primary connection regions

The CRD server can also be used with one or more additional non-primary connection regions, which are usually Application Owning Regions (AOR).

**Note:** It is not necessary to perform these steps if CICSplex® SM Business Application Services (BAS) is used to manage your CICS resource definitions.

- Place the Application Deployment Manager load module FEK.SFEKLOAD(ADNCRD\*) in the CICS RPL concatenation (DD statement DFHRPL) of these non-primary connection regions. It is recommended that you do this by adding the installation data set to the concatenation so that applied maintenance is automatically available to CICS.
- Customize and submit job ADNCSDAR to update the CSD for these non-primary, connection regions. Refer to the documentation within the member for customization instructions.  
ADNCSDAR is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.
- Use the appropriate CEDA command to install the Application Deployment Manager group for these regions, for example:  
CEDA INSTALL GROUP(ADNARRGP)

## (Optional) Customize CRD server transaction IDs

Developer for System z supplies multiple transactions that are used by the CRD server when defining and inquiring CICS resources.

Table 12. Default CRD server transaction IDs

Transaction	Description
ADMS	For requests from the Manifest Processing tool to change CICS resources. Typically, this is intended for CICS administrators.
ADMI	For requests that define, install, or uninstall CICS resources.
ADMR	For all other requests that retrieve CICS environmental or resource information.

You can change the transaction IDs to match your site standards by following these steps:

1. Customize and submit ADNTXNC to create load module ADNRCUST. Refer to the documentation within the member for customization instructions.
2. Place the resulting ADNRCUST load module in the CICS RPL concatenation (DD statement DFHRPL) of the CICS regions where the CRD server is defined.
3. Customize and submit ADNCSDTX to define ADNRCUST as program to the CICS regions where the CRD server is defined. Refer to the documentation within the member for customization instructions.

**Note:** The RESTful CRD server will always try to load the ADNRCUST load module. So you can get a small performance benefit by creating and defining the ADNRCUST load module, even if you do not change the transaction IDs.

---

## CRD server using the Web Service interface

The information in this section describes how to define the CRD server that uses the Web Service interface to communicate with the Developer for System z client.

The RESTful and Web Service interfaces can be active concurrently in a single CICS region, if desired. In this case, there will be two CRD servers active in the region. Both servers will share the same CRD repository. Note that CICS will issue some warnings about duplicate definitions when the second interface is defined to the region.

## Pipeline message handler

The pipeline message handler (ADNTMSGH) is used for security by processing the user ID and password in the SOAP header. ADNTMSGH is referenced by the sample pipeline configuration file and must therefore be placed into the CICS RPL concatenation. Refer to "CICSTS considerations" in the *Host Configuration Reference* (SC14-7290) to learn more about the pipeline message handler and the required security setup.

Developer for System z supplies multiple transactions that are used by the CRD server when defining and inquiring CICS resources. These transaction IDs are set by ADNTMSGH, depending on the requested operation. Sample COBOL source code is provided to allow site-specific customizations to ADNTMSGH:

*Table 13. Default CRD server transaction IDs*

Transaction	Description
ADMS	For requests from the Manifest Processing tool to change CICS resources. Typically, this is intended for CICS administrators.
ADMI	For requests that define, install or uninstall CICS resources.
ADMR	For all other requests that retrieve CICS environmental or resource information.

Using the default:

- Place the FEK.SFEKLOAD(ADNTMSGH) load module in the CICS RPL concatenation (DD statement DFHRPL) of the CICS primary connection region. It is recommended that you do this by adding the installation data set to the concatenation so that applied maintenance is automatically available to CICS.

Customizing ADNTMSGH:

Sample members ADNMSGH\* are located in FEK.#CUST.JCL and FEK.#CUST.COBOLE, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See "Customization setup" on page 11 for more details.

- Customize the sample Pipeline Message Handler (COBOL) source code, FEK.#CUST.COBOLE(ADNMSGHS), to match your site's standards.
- Customize and submit job FEK.#CUST.JCL(ADNMSGHC) to compile the customized ADNMSGHS source. Refer to the documentation within ADNMSGHC for customization instructions. Note that the resulting load module must be named ADNTMSGH.
- Place the resulting ADNTMSGH load module in the CICS RPL concatenation (DD statement DFHRPL) of the CICS primary connection region.

**Note:** Ensure that the customized ADNTMSGH load module is located before any reference to FEK.SFEKLOAD, otherwise the default one will be used.

## CICS primary connection region

The CRD server must be defined to the primary connection region. This is the region that will process service requests from Developer for System z.

- Place the load modules FEK.SFEKLOAD(ADNCRD\*, ADNANAL and ADNREST) in the CICS RPL concatenation (DD statement DFHRPL) of the CICS primary connection region. It is recommended that you do this by adding the installation data set to the concatenation so that applied maintenance is automatically



available to CICS. Note that the pipeline message handler load module, ADNTMSGH, must also be placed in the RPL concatenation, as described in “Pipeline message handler” on page 85.

- Customize and submit job ADNCSDWS to update the CICS System Definition (CSD) for the CICS primary connection region. Refer to the documentation within the member for customization instructions. Note that the transaction IDs used in this job must match the ones used by the Pipeline message handler (which may have been customized).

ADNCSDWS is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

- Use the appropriate CEDA command to install the Application Deployment Manager group for this region, for example:

```
CEDA INSTALL GROUP(ADNPCRGP)
```

## CICS non-primary connection regions

The CRD server can also be used with one or more additional non-primary connection regions, which are usually Application Owning Regions (AOR).

**Note:** It is not necessary to perform these steps if CICSplex SM Business Application Services (BAS) is used to manage your CICS resource definitions.

- Place the Application Deployment Manager load modules FEK.SFEKLOAD(ADNCRD\*) in the CICS RPL concatenation (DD statement DFHRPL) of these non-primary connection regions. You should do this by adding the installation data set to the concatenation so that applied maintenance is automatically available to CICS.
- Customize and submit job ADNCSDAR to update the CSD for these non-primary, connection regions. Refer to the documentation within the member for customization instructions.

ADNCSDAR is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

- Use the appropriate CEDA command to install the Application Deployment Manager group for these regions, for example:

```
CEDA INSTALL GROUP(ADNARRGP)
```

---

## (Optional) Manifest repository

Developer for System z allows clients to browse and optionally change manifests describing selected CICS resources. Depending on permissions set by the CICS administrator, changes can be done directly or exported to the manifest repository for further processing by a CICS administrator.

**Note:**

- This step is only required for customers that export manifests from Developer for System z to be processed by the Manifest Processing tool.
- The Manifest Processing tool is a plug-in for IBM CICS Explorer.

Customize and submit job ADNVMFST to allocate and initialize the manifest repository VSAM data set, and to define it to the CICS primary connection region. Refer to the documentation within the member for customization instructions. A separate manifest repository must be created for each CICS primary connection region. All users need UPDATE access to the manifest repository.



ADNVMFST is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.



---

## Chapter 6. (Optional) Other customization tasks

This section combines a variety of optional customization tasks. Follow the instructions in the appropriate section to configure the desired service.

Customizations to Developer for System z configuration files:

- “(Optional) pushtoclient.properties, Host-based client control”
- “(Optional) (deprecated) FMIEXT.properties, File Manager integration” on page 92
- “(Optional) ssl.properties, RSE SSL encryption” on page 93
- “(Optional) rsecomm.properties, RSE tracing” on page 96

Developer for System z related customizations to (or for) other products:

- “(Optional) DB2 stored procedure” on page 97
- “(Optional) z/OS UNIX subprojects” on page 99
- “(Optional) Enterprise Service Tools support” on page 100
- “(Optional) CICS bidirectional language support” on page 100
- “(Optional) Diagnostic IRZ error messages” on page 101
- “(Optional) WORKAREA and /tmp cleanup” on page 102

---

### (Optional) pushtoclient.properties, Host-based client control

This customization task does not require assistance, special resources, or special customization tasks for a basic setup.

If you enable group support, you will need the assistance of a security administrator or an LDAP administrator to complete this customization task, which requires the following resources or special customization tasks:

- Security rule to allow users access to FEK.PTC.\* profiles
- Or define user membership of FEK.PTC.\* LDAP groups

Developer for System z clients version 8.0.1 and higher can pull client configuration files and product update information from the host when they connect, ensuring that all clients have common settings and that they are up-to-date.

z/OS Projects can be defined individually through the z/OS Projects perspective on the client or can be defined centrally on the host and propagated to the client on a per-user basis. These “host-based projects” look and function exactly like projects defined on the client except that their structure, members, and properties cannot be modified by the client, and they are accessible only when connected to the host.

pushtoclient.properties tells the client if these functions are enabled, and where the related data is stored. (The data is maintained by a Developer for System z client administrator or a development project manager.)

pushtoclient.properties is located in /etc/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details. You can edit the file with the TSO OEDIT command. Note that the RSED started task must be restarted before changes take effect.

Since version 8.0.3, the client administrator can create multiple client configuration sets and multiple client update scenarios to fit the needs of different developer groups. This allows users to receive a customized setup, based on criteria like membership of an LDAP group or permit to a security profile. See “Push-to-client considerations” in *Host Configuration Reference* (SC14-7290) for more information about supporting multiple groups.

The following code sample shows the pushtoclient.properties file, which must be customized to match your system environment. Comment lines start with a pound sign (#), when using a US code page. Data lines can only have a directive and its assigned value. Comments are not allowed on the same line. Line continuations are not supported.

```
#
# host-based client control
#
config.enabled=false
product.enabled=false
reject.config.updates=false
reject.product.updates=false
accept.product.license=false
primary.system=false
pushtoclient.folder=/var/rdz/pushtoclient
default.store=com.ibm.ftt.configurations.USS
file.permission=RWX.RWX.RX
```

Figure 29. pushtoclient.properties - Host-based client control configuration file

#### **config.enabled**

Indicates whether host-based client control is used for configuration files. The default is false. The valid values are true, false, LDAP, or SAF. See Table 14 on page 91 for the exact meaning of these values.

#### **product.enabled**

Indicates whether host-based client control is used for product updates. The default is false. The valid values are true, false, LDAP, or SAF. See Table 14 on page 91 for the exact meaning of these values.

#### **reject.config.updates**

Indicates whether a user is allowed to reject configuration updates that are pushed to the client. The default is false. The valid values are true, false, LDAP, or SAF. See Table 14 on page 91 for the exact meaning of these values.

#### **reject.product.updates**

Indicates whether a user is allowed to reject product updates that are pushed to the client. The default is false. The valid values are true, false, LDAP, or SAF. See Table 14 on page 91 for the exact meaning of these values.

#### **accept.product.license**

Indicates whether the product license is automatically accepted during updates initiated by push-to-client. If enabled, IBM Installation Manager does not ask to accept the license during client update. The default is false. The only valid values are true and false.

### **primary.system**

Host-based client control supports storing system specific data per system, while maintaining common data on a single system to reduce management effort. This directive indicates whether this is the system that stores global, non-system specific, client definitions. The default is false. The only valid values are true and false.

**Note:** Ensure you have one, and only one, system defined as primary system. Developer for System z client administrators will not be able to export global configuration data unless the target system is a primary system. Developer for System z clients might show erratic behavior when connecting to multiple primary systems with out-of-sync configurations.

### **pushtoclient.folder**

The base directory for the host-based client control definitions. The default is /var/rdz/pushtoclient.

### **default.store**

Host-based client control supports different methods for storing the data that is pushed to the client. This directive identifies the "driver", or store, that is used to access the data. The default is com.ibm.ftt.configurations.USS, which supports the data being stored in z/OS UNIX flat files.

Note that Developer for System z only provides the com.ibm.ftt.configurations.USS store. A third-party store is needed when the data is located somewhere else.

### **file.permission**

The com.ibm.ftt.configurations.USS store uses file.permission to determine the desired access permissions for files created by the store. The default is RWX.RWX.RX, which allows the owner and the owner's default group read and write access to the directory structure and the files within. Everyone else has only read access to the directory structure and the files within.

UNIX standards dictate that permissions can be set for three types of users: owner, group, and other. The fields in the file.permission mask match this order, and the fields are separated by a period (.). Each field can either be empty, or have R, W, RW, X, RX, WX, or RWX as value (R = read, W = write, X = execute or list directory content).

Table 14. Push-to-client group support

Key value	Is the related push-to-client function enabled?
False	No, disabled
True	Yes, enabled for all
LDAP	Yes, but availability is controlled by membership of LDAP groups
SAF	Yes, but availability is controlled by permit to security profiles

### **Note:**

- In order to activate host-based client control, a keymapping.xml file must exist in /var/rdz/pushtoclient. This file is created and maintained by a Developer for System z client administrator.
- See "Push-to-client considerations" in the *Host Configuration Reference* (SC14-7290) for more information about host-based projects, host-based client configuration, and upgrade control.

- When a file is created, z/OS UNIX uses by default the effective UID (user ID) of the creating thread and the GID (group ID) of the owning directory, not the effective GID of the creating thread. Refer to “z/OS UNIX directory structure” in *Host Configuration Reference* (SC14-7290) for more information on how to change this behavior or how to adjust your host-based client control setup to get the desired GID assignment.

---

## (Optional) (deprecated) FMEXT.properties, File Manager integration

You will need the assistance of a security administrator to complete this customization task, which requires the following resources or special customization tasks:

- Security rule to add program controlled data sets
- 

### Note:

- File Manager integration has been marked as deprecated. Although it is currently still supported, this function will no longer be enhanced, and the services provided by this function are being moved to different areas. Some functions, such as unformatted QSAM editing, are now part of regular data set handling by Developer for System z. More advanced functions, such as formatted data editing using copybooks or include files, require the IBM File Manager plug-in for Eclipse. This plug-in is available from the IBM Problem Determination Tools Plug-ins web page, <http://www-01.ibm.com/software/awdtools/deployment/pdtpplugins/>. Refer to the Developer for System z Information Center (<http://publib.boulder.ibm.com/infocenter/ratdevz/v8r0/index.jsp>) to learn which File Manager functions are now supported natively by Developer for System z.
- The IBM File Manager plug-in for Eclipse requires updates to `rsed.envvars`. Similar to the `fmnlisterport` directive in `FMEXT.properties`, the plug-in requires the definition of `FM_SERVER_PORT` in `rsed.envvars`.

Developer for System z supports direct access from the client to a limited set of IBM File Manager for z/OS functions. IBM File Manager for z/OS provides comprehensive tools for working with MVS data sets, z/OS UNIX files, DB2, IMS and CICS data. Refer to the Developer for System z Information Center (<http://publib.boulder.ibm.com/infocenter/ratdevz/v8r0/index.jsp>) to learn which File Manager functions are supported.

Note that the IBM File Manager for z/OS product must be ordered, installed and configured separately. Refer to *IBM Rational Developer for System z Prerequisites* (SC23-7659) to know which level of File Manager is required for your version of Developer for System z. The installation and customization of this product is not described in this manual.

### Note:

- Developer for System z uses the File Manager Server to access the File Manager services. This server is not used by the File Manager ISPF panel interface. This implies that you might have to perform additional File Manager setup tasks, specific for the File Manager Server. Refer to your File Manager documentation for more details.
- In addition to the normal File Manager Server setup tasks, Developer for System z requires that the server's STEPLIB data sets are program controlled. Refer to “Define MVS program controlled libraries for RSE” on page 129 for more information on program controlled libraries.

- The client user ID is used for all interaction with File Manager Server. In turn, the server will use the client user ID to execute the requested service. This implies that Developer for System z users must have the necessary permits to access resources used by File Manager Server. Refer to your File Manager documentation for more details.

The File Manager Integration definitions needed by Developer for System z are stored in `FMIEXT.properties`, which is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job `FEK.SFEKSAMP(FEKSETUP)`. See “Customization setup” on page 11 more details. You can edit the file with the TSO **OEDIT** command. Changes are active for all new invocations. No server restart is needed.

The following code sample shows the `FMIEXT.properties` file, which must be customized to match your system environment. Comment lines start with a pound sign (#), when using a US code page. Data lines can only have a directive and its assigned value. Comments are not allowed on the same line. Line continuations are not supported.

```
# File Manager Integration (FMI) Extension properties
#
enabled=false
fmlistenport=1960
```

*Figure 30. FMIEXT.properties – File Manager configuration file*

#### **enabled**

Indicates whether the File Manager Server is available on the same host system or not. The default value is false. The only values allowed are true and false.

#### **fmlistenport**

Port used by the File Manager Server. The default is 1960. Communication on this port is confined to your host machine.

---

## **(Optional) ssl.properties, RSE SSL encryption**

You will need assistance of a security administrator to complete this customization task, which requires the following resources or special customization tasks:

- LINKLIST update
  - Security rule to add program controlled data sets
  - (Optional) Security rule to add certificate for SSL
- 

External (client-host) communication can be encrypted using SSL (Secure Socket Layer). This feature is disabled by default and is controlled by the settings in `ssl.properties`.

**Note:** Client authentication with an X.509 certificate requires the use of SSL encrypted communication.

`ssl.properties` is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job `FEK.SFEKSAMP(FEKSETUP)`. See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command. Note that RSE must be restarted for the changes to take effect.

The client communicates with RSE daemon during connection setup and with RSE server during the actual session. Both data streams are encrypted when SSL is enabled.

RSE daemon and RSE server support different mechanisms to store certificates due to architectural differences between the two. This implies that SSL definitions are required for both RSE daemon and RSE server. A shared certificate can be used if RSE daemon and RSE server use the same certificate management method.

*Table 15. SSL certificate storage mechanisms*

Certificate storage	Created and managed by	RSE daemon	RSE server
key ring	SAF-compliant security product	supported	supported
key database	z/OS UNIX's gskkyman	supported	/
key store	Java's keytool	/	supported

**Note:**

- SAF-compliant key rings are the preferred method for managing certificates.
- SAF-compliant key rings can store the certificate's private key either in the security database or by using ICSF, the interface to System z cryptographic hardware. Access to ICSF is protected by profiles in the CSFSERV security class.

RSE daemon uses System SSL functions to manage SSL. This implies that SYS1.SIEALNKE must be program controlled by your security software and available to RSE using LINKLIST or the STEPLIB directive in rsed.envvars.

The following code sample shows the sample `ssl.properties` file, which must be customized to match your system environment. Comment lines start with a pound sign (#), when using a US code page. Data lines can only have a directive and its assigned value, comments are not allowed on the same line. Line continuations are not supported.

```
# ssl.properties – SSL configuration file
enable_ssl=false

# Daemon Properties

#daemon_keydb_file=
#daemon_keydb_password=
#daemon_key_label=

# Server Properties

#server_keystore_file=
#server_keystore_password=
#server_keystore_label=
#server_keystore_type=JCERACFKS
```

*Figure 31. ssl.properties – SSL configuration file*

The daemon and server properties only need to be set if you enable SSL. Refer to "Setting up SSL and X.509 authentication" in the *Developer for System z Host Configuration Reference* for more information about SSL setup.



**enable\_ssl**

Enable or disable SSL communication. The default is false. The only valid options are true and false.

**daemon\_keydb\_file**

RACF (or similar security product) key ring name. Provide the key database name if you used **gskkyman** to create a key database instead of using a key ring. Uncomment and customize this directive if SSL is enabled.

**daemon\_keydb\_password**

Leave commented out or blank if you use a key ring, otherwise provide the key database password. Uncomment and customize this directive if SSL is enabled and you are using a **gskkyman** key database.

**daemon\_key\_label**

The certificate label used in the key ring or key database, if it is not defined as the default one. Must be commented out if the default is used. Uncomment and customize this directive if SSL is enabled and you are not using the default security certificate. Note that key labels are case sensitive.

**server\_keystore\_file**

Name of the key store created by Java's **keytool** command, or the RACF (or similar security product) key ring name if `server_keystore_type=JCERACFKS`. Uncomment and customize this directive if SSL is enabled.

**server\_keystore\_password**

Leave commented out or blank if you use a key ring, otherwise provide the key store password. Uncomment and customize this directive if SSL is enabled and you are using a **keytool** key store.

**server\_keystore\_label**

The certificate label used in the key ring or key store. The default is the first valid certificate encountered. Uncomment and customize this directive if SSL is enabled and you are not using the default security certificate. Note that key labels are case sensitive.

**server\_keystore\_type**

Key store type. The default is JKS. Valid values are:

*Table 16. Valid keystore types*

Keyword	Key store type
JKS	Java key store
JCERACFKS	SAF-compliant key ring, where the certificate's private key is stored in the security database.
JCECCARACFKS	SAF-compliant key ring, where the certificate's private key is stored using ICSF, the interface to System z cryptographic hardware.

**Note:** At the time of publication, IBM z/OS Java requires an update of the `/usr/lpp/java/J5.0/lib/security/java.security` file to support JCECCARACFKS. The following line must be added:

```
security.provider.1=com.ibm.crypto.hdwrCCA.provider.IBMJCECCA
```

The resulting file will look like this:

```
security.provider.1=com.ibm.crypto.hdwrCCA.provider.IBMJCECCA
security.provider.2=com.ibm.jsse2.IBMJSSEProvider2
security.provider.3=com.ibm.crypto.provider.IBMJCE
security.provider.4=com.ibm.security.jgss.IBMJGSSProvider
security.provider.5=com.ibm.security.cert.IBMCertPath
security.provider.6=com.ibm.security.sasl.IBMSASL
```

---

## (Optional) rsecomm.properties, RSE tracing

This customization task does not require assistance, special resources, or special customization tasks.

---

Developer for System z supports different levels of tracing the internal program flow for problem solving purposes. RSE, and some of the services called by RSE, use the settings in `rsecomm.properties` to know the desired initial detail level in the output logs.

**Attention:** Changing these settings can cause performance degradations and should only be done under the direction of the IBM support center.

`rsecomm.properties` is located in `/etc/rdz/`, unless you specified a different location when you customized and submitted job `FEK.SFEKSAMP(FEKSETUP)`. See “Customization setup” on page 11 for more details. You can edit the file with the TSO **OEDIT** command.

The following code sample shows the `rsecomm.properties` file, which can be customized to match your tracing needs. Comment lines start with a pound sign (#), when using a US code page. Data lines can only have a directive and its assigned value, comments are not allowed on the same line. Line continuations are not supported.

```
# server.version - DO NOT MODIFY!
server.version=5.0.0

# Logging level
# 0 - Log error messages
# 1 - Log error and warning messages
# 2 - Log error, warning and info messages
debug_level=1
```

*Figure 32. rsecomm.properties – Logging configuration file*

### **server.version**

Logging server version. The default is 5.0.0. Do not modify.

### **debug\_level**

Detail level for output logs. The default is 1 (log error and warning messages). Note that `debug_level` controls the detail level of multiple services (and thus multiple output files). Increasing the detail level will cause performance degradations and should only be done under the direction of the IBM support center. Refer to “RSE tracing” in the *Host Configuration Reference* (SC14-7290) for more information about which logs are controlled by this directive.

The valid values are the following:

0	Log error messages only.
1	Log error and warning messages.
2	Log error, warning, and informational messages.

**Note:** `debug_level` can be changed dynamically for specific log files with the **modify rsecommlog**, **modify rseserverlog**, and **modify rsedaemonlog** operator commands, as described in Chapter 10, “Operator commands,” on page 155.

---

## (Optional) DB2 stored procedure

You will need the assistance of a WLM administrator and a DB2 administrator to complete this customization task, which requires the following resources or special customization tasks:

- WLM update
  - New PROCLIB member
  - DB2 update
- 

Developer for System z provides a sample DB2 stored procedure (PL/I and COBOL Stored Procedure Builder) for building COBOL and PL/I Stored Procedures from within the Developer for System z client.

**Note:** Sample members ELAXM\* are located in FEK.#CUST.JCL and FEK.#CUST.PROCLIB, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

## Workload Manager (WLM) changes

Use the workload management (WLM) panels to associate an application environment with the JCL procedure of the WLM address space for the PL/I and COBOL Stored Procedure Builder. Refer to *MVS Planning Workload Management* (SA22-7602) for information about how to do this.

**Note:** You can create a new application environment in WLM for the PL/I and COBOL Stored Procedure Builder, or you can add the necessary definitions to an existing one.

## PROCLIB changes

Customize the sample Stored Procedure task FEK.#CUST.PROCLIB(ELAXMSAM), as described within the member, and copy it to SYS1.PROCLIB. As shown in the following code sample, you have to provide the following:

- The name of the application environment defined in WLM for this Stored Procedure
- The DB2 subsystem name
- The high-level qualifier of various data sets

```

//ELAXMSAM PROC RGN=0M,
//          NUMTCB=1,
//          APPLENV=#w1mwd4z,
//          DB2SSN=#ssn,
//          DB2PRFX='DSN810',
//          COBPRFX='IGY.V3R4M0',
//          PLIPRFX='IBMZ.V3R6M0',
//          LIBPRFX='CEE',
//          LODPRFX='FEK'
//*
//DSNX9WLM EXEC PGM=DSNX9WLM,REGION=&RGN,TIME=NOLIMIT,DYNAMNBR=10,
//          PARM='&DB2SSN,&NUMTCB,&APPLENV'
//STEPLIB DD DISP=SHR,DSN=&DB2PRFX..SDSNEXIT
//          DD DISP=SHR,DSN=&DB2PRFX..SDSNLOAD
//          DD DISP=SHR,DSN=&LIBPRFX..SCEERUN
//          DD DISP=SHR,DSN=&COBPRFX..SIGYCOMP
//          DD DISP=SHR,DSN=&PLIPRFX..SIBMZCMP
//SYSEXEC DD DISP=SHR,DSN=&LODPRFX..SFEKPROC
//SYSTSPRT DD SYSOUT=*
//CEEDUMP DD SYSOUT=*
//SYSABEND DD DUMMY
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT2 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT4 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT6 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT7 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//*

```

Figure 33. ELAXMSAM - DB2 stored procedure task

**Note:**

- The DB2 stored procedure uses REXX exec ELAXMREX, located in FEK.SFEKPROC. Do not change this location if you want possible SMP/E maintenance to be activated automatically.
- See "Running multiple instances" in the *Host Configuration Reference* (SC14-7290) if you want to rename members ELAXMSAM or ELAXMREX.

## DB2 changes

Customize and submit sample member ELAXMJCL in data set FEK.#CUST.JCL to define the Stored Procedure to DB2. Refer to the documentation within the member for customization instructions.

```

//ELAXMJCL JOB <job parameters>
//JOB LIB DD DISP=SHR,DSN=#hlq.SDSNEXIT
//          DD DISP=SHR,DSN=#hlq.SDSNLOAD
//*
//RUNTIAD EXEC PGM=IKJEFT01,DYNAMNBR=20
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
DSN S(#ssn) R(1) T(1)
RUN PROGRAM(DSNTIAD) PLAN(#plan) -
LIB('#hlq.RUNLIB.LOAD')
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
CREATE PROCEDURE SYSPROC.ELAXMREX
( IN FUNCTION_REQUEST VARCHAR(20) CCSID EBCDIC
, IN SQL_ROUTINE_NAME VARCHAR(27) CCSID EBCDIC
, IN SQL_ROUTINE_SOURCE VARCHAR(32672) CCSID EBCDIC
, IN BIND_OPTIONS VARCHAR(1024) CCSID EBCDIC
, IN COMPILE_OPTIONS VARCHAR(255) CCSID EBCDIC
, IN PRECOMPILE_OPTIONS VARCHAR(255) CCSID EBCDIC
, IN PRELINK_OPTIONS VARCHAR(32672) CCSID EBCDIC
, IN LINK_OPTIONS VARCHAR(255) CCSID EBCDIC
, IN ALTER_STATEMENT VARCHAR(32672) CCSID EBCDIC
, IN SOURCE_DATASETNAME VARCHAR(80) CCSID EBCDIC
, IN BUILDOWNER VARCHAR(8) CCSID EBCDIC
, IN BUILDUTILITY VARCHAR(18) CCSID EBCDIC
, OUT RETURN_VALUE VARCHAR(255) CCSID EBCDIC )
PARAMETER STYLE GENERAL RESULT SETS 1
LANGUAGE REXX
EXTERNAL NAME ELAXMREX
COLLID DSNREXCS WLM ENVIRONMENT ELAXMSAM
PROGRAM TYPE MAIN MODIFIES SQL DATA
STAY RESIDENT NO COMMIT ON RETURN NO
ASUTIME NO LIMIT SECURITY USER;

COMMENT ON PROCEDURE SYSPROC.ELAXMREX IS
'PLI & COBOL PROCEDURE PROCESSOR (ELAXMREX), INTERFACE LEVEL 0.01';

GRANT EXECUTE ON PROCEDURE SYSPROC.ELAXMREX TO PUBLIC;
/*

```

*Figure 34. ELAXMJCL – DB2 stored procedure definition*

**Note:** Make sure the WLM ENVIRONMENT clause in the CREATE PROCEDURE statement specifies the name of the WLM environment procedure which has been defined for the PL/I and COBOL Stored Procedure Builder (default ELAXMSAM).

---

## (Optional) z/OS UNIX subprojects

This customization task does not require assistance, special resources, or special customization tasks.

---

REXEC (Remote Execution) is a TCP/IP service to let clients execute a command on the host. SSH (Secure Shell) is a similar service, but here all communication is encrypted using SSL (Secure Socket Layer). Developer for System z uses either service for doing remote (host-based) actions in z/OS UNIX subprojects.

**Note:**

- Developer for System z uses the z/OS UNIX version of REXEC, not the TSO version.
- If REXEC/SSH is not configured to use the default port, the Developer for System z client must define the correct port for use by z/OS UNIX subprojects.

This can be done by selecting the **Window > Preferences... > z/OS Solutions > USS Subprojects > Remote Action Options** preference page. Refer to “REXEC (or SSH) set up” to know which port is used.

## REXEC (or SSH) set up

REXEC and SSH rely on services provided by INETD (Internet Daemon), which is another TCP/IP service. *Communications Server IP Configuration Guide* (SC31-8775) describes the steps required to set up INETD, REXEC, and SSH. For more details and alternate setup methods, refer to white paper *Using INETD, REXEC and SSH with Rational Developer for System z* (SC14-7301), available in the Developer for System z library, <http://www.ibm.com/software/rational/products/developer/systemz/library/index.html>.

A common port used by REXEC is 512. To verify this, you can check `/etc/inetd.conf` and `/etc/services` to find the port number used.

- Find the service name (1st word, `exec` in this example) of the `rexecd` server (7th word) in `/etc/inetd.conf`.

```
exec stream tcp nowait OMVSKERN /usr/sbin/orexecd rexecd -LV
```

- Find the port (2nd word, 512 in this example) attached to this service name (1st word) in `/etc/services`.

```
exec 512/tcp #REXEC Command Server
```

The same principle applies to SSH. Its common port is 22, and the server name is `sshd`.

---

## (Optional) Enterprise Service Tools support

This customization task does not require assistance, special resources, or special customization tasks.

---

The Developer for System z client has a code generation component called Enterprise Service Tools. Depending on the type of code being generated, this code relies on functions provided by the Developer for System z host install. Making these host functions available is described in the following sections:

- Chapter 5, “(Optional) Application Deployment Manager,” on page 81
- “(Optional) CICS bidirectional language support”
- “(Optional) Diagnostic IRZ error messages” on page 101

**Note:** Enterprise Service Tools encompasses multiple tools, such as the Service Flow Modeler (SFM) and XML Services for the Enterprise.

---

## (Optional) CICS bidirectional language support

You will need the assistance of a CICS administrator to complete this customization task, which requires the following resources or special customization tasks:

- Update CICS region JCL
  - Define a program to CICS
- 

The Developer for System z Enterprise Service Tools component supports different formats of Arabic and Hebrew interface messages, as well as bidirectional data

presentation and editing in all editors and views. In terminal applications, both left-to-right and right-to-left screens are supported, as well as numeric fields and fields with opposite-to-screen orientation.

Additional bidirectional features and functionality include the following:

- The Enterprise Service Tools service requestor dynamically specifies bidirectional attributes of interface messages.
- Bidirectional data processing in service flows is based on bidirectional attributes (text type, text orientation, numeric swapping, and symmetric swapping). These attributes can be specified in different stages of flow creation for both interface and terminal flows.
- Enterprise Service Tools-generated runtime code includes conversion of data between fields in messages that have different bidirectional attributes.

Additionally, Enterprise Service Tools-generated code can support bidi transformation in environments other than CICS SFR (Service Flow Runtime). One example is batch applications. You can make the Enterprise Service Tools generators to include calls to the bidirectional conversion routines by specifying the appropriate bidi transformation options in the Enterprise Service Tools generation wizards and linking the generated programs with the appropriate bidirectional conversion library, FEK.SFEKLOAD.

Perform the following tasks to activate CICS Bidirectional language support:

1. Place the FEK.SFEKLOAD load modules FEJBDCMP and FEJBDTRX in the CICS RPL concatenation (DD statement DFHRPL). You should do this by adding the installation data set to the concatenation so that applied maintenance is automatically available to CICS.

**Note:** If you do not concatenate the installation data set but copy the modules into a new or existing data set, keep in mind that those modules are DLLs and MUST reside in a PDSE library.

2. Define FEJBDCMP and FEJBDTRX as programs to CICS using the appropriate CEDA command, for example:

```
CEDA DEF PROG(FEJBDCMP) LANG(LE) G(xxx)
CEDA DEF PROG(FEJBDTRX) LANG(LE) G(xxx)
```

---

## (Optional) Diagnostic IRZ error messages

This customization task does not require assistance, but does require the following resources or special customization tasks:

- LINKLIST update
  - Update CICS region JCL
- 

The Developer for System z client has a code generation component called Enterprise Service Tools. In order for code generated by Enterprise Service Tools to issue diagnostic error messages, all IRZM\* and IIRZ\* modules in the FEK.SFEKLOAD load library must be made available to the generated code. Enterprise Service Tools can generate code for the following environments:

- CICS
- IMS
- MVS batch

When the generated code is executed in a CICS transaction, then add all IRZM\* and IIRZ\* modules in FEK.SFEKLOAD to the DFHRPL DD of the CICS region. You should do this by adding the installation data set to the concatenation so that applied maintenance is automatically available.

In all other situations, make all IRZM\* and IIRZ\* modules in FEK.SFEKLOAD available either through STEPLIB or LINKLIST. You should do this by adding the installation data set to the concatenation so that applied maintenance is automatically available.

If you decide to use STEPLIB, you must define the modules not available through LINKLIST in the STEPLIB directive of the task that executes the code.

If the load modules are not available and an error is encountered by the generated code, then following message will be issued:

IRZ9999S Failed to retrieve the text of a Language Environment runtime message. Check that the Language Environment runtime message module for facility IRZ is installed in DFHRPL or STEPLIB.

**Note:** Module FEK.SFEKLOAD(IRZPWSIO) is statically linked during top-down IMS MPP code generation. Therefore, the module must not be available during runtime of the generated code. It should only be available during compile time.

---

## (Optional) WORKAREA and /tmp cleanup

This customization task does not require assistance, special resources, or special customization tasks.

---

ISPF's TSO/ISPF Client Gateway and the SCLM Developer Toolkit function use the WORKAREA and /tmp directories to store temporary work files, which are removed before the session is closed. However, temporary output is sometimes left behind, for example, if there is a communication error while processing. For this reason, it is recommended that you clear out the WORKAREA and /tmp directories from time to time.

z/OS UNIX provides a shell script, *skulker*, that deletes files based upon the directory they are in and their age. Combined with the z/OS UNIX cron daemon, which runs commands at specified dates and times, you can set up an automated tool that periodically cleans out the WORKAREA and /tmp directories. Refer to *UNIX System Services Command Reference (SA22-7802)* for more information about the *skulker* script and the cron daemon.

**Note:** WORKAREA is located in /var/rdz/, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.



---

## Chapter 7. Installation verification

After completing the product customization, you can use the Installation Verification Programs (IVPs) described in this chapter to verify the successful setup of key product components.

---

### Verify started tasks

#### JMON, JES Job Monitor

Start the JMON started task (or user job). The startup information in DD STDOUT should end with the following message:

```
JM200I Server initialization complete.
```

If the job ends with return code 66, then FEK.SFEKAUTH is not APF authorized.

**Note:** Start JES Job Monitor before continuing with the other IVP tests.

#### LOCKD, Lock daemon

Start the LOCKD started task (or user job). The lock daemon issues the following console message upon successful startup:

```
FEK501I Lock daemon started, port=4036, cleanup interval=1440,  
log level=1
```

**Note:** Start the lock daemon before continuing with the other IVP tests.

#### RSED, RSE daemon

Start the RSED started task (or user job) with the IVP=IVP parameter. With this parameter, the server will end after doing some installation verification tests. The output of these tests is available in DD STDOUT. In case of certain errors, data will also be available in DD STDERR. Check DD STDOUT for messages indicating that the following IVPs were successful:

- Java startup
- JES Job Monitor connection
- Lock daemon connection
- TCP/IP setup
- PassTicket generation

**Note:** The PassTicket IVP will fail with “pthread\_security\_np error : EACCES” if the user ID assigned to the RSED started task is protected, because no password activity is allowed for a protected ID.

The STDOUT data should look like the following sample:

```
-----  
RSE daemon startup script  
-----  
  
arguments: IVP -C/etc/rdz -P -T  
  
RSE daemon IVP test
```

CDFMVS08 -- Wed Nov 10 17:50:52 2010 UTC  
uid=8(STCRSE) gid=1(STCGROUP)

started from /nd/v80/usr/lpp/rdz/bin/rsed.sh  
startup script version Oct22,2010

configuration files located in /etc/rdz -- startup argument  
RSE daemon port is 4035 -- set in rsed.envvars  
Debug level is 1 -- set in rsecomm.properties  
TMPDIR=/tmp

-----  
current environment variables  
-----

@="/usr/lpp/rdz/bin/rsed.sh" @[1]="-C/etc/rdz" @[2]="-P" @[2]="-T"  
ANT\_HOME="/usr/lpp/Apache/Ant/apache-ant-1.7.1"  
CGI\_DWORK="/var/rdz"  
CGI\_ISPCONF="/etc/rdz"  
CGI\_ISPWORK="/var/rdz"  
CGI\_TRANTABLE="FEK.#CUST.LSTRANS.FILE"  
CLASSPATH=".:usr/lpp/rdz/lib:usr/lpp/rdz/lib/dstore\_core.jar:usr/lpp/  
ERRNO="0"  
HOME="/tmp"  
IFS=" "  
"  
JAVA\_HOME="/usr/lpp/java/J5.0"  
JAVA\_PROPAGATE="NO"  
LANG="C"  
LIBPATH=".:usr/lib:usr/lpp/java/J5.0/bin:usr/lpp/java/J5.0/bin/classi  
LINENO="66"  
LOGNAME="STCRSE"  
MAILCHECK="600"  
OLDPWD="/tmp"  
OPTIND="1"  
PATH=".:usr/lpp/java/J5.0/bin:usr/lpp/rdz/bin:usr/lpp/ispf/bin:bin:/  
PPID="33554711"  
PS1="\\$ "  
PS2="> "  
PS3="#? "  
PS4="+ "  
PWD="/etc/rdz"  
RANDOM="27298"  
RSE\_CFG="/etc/rdz"  
RSE\_HOME="/usr/lpp/rdz"  
RSE\_LIB="/usr/lpp/rdz/lib"  
SECONDS="0"  
SHELL="/bin/sh"  
STEPLIB="NONE"  
TMPDIR="/tmp"  
TZ="EST5EDT"  
X\_ARG="-T"  
X\_C="-- startup argument"  
X\_KEY="-T"  
X\_L="-- set in rsecomm.properties"  
X\_LOG="1"  
X\_P="-- set in rsed.envvars"  
X\_PORT="4035"  
X\_VAL=""  
="-----"  
\_BPX\_SHAREAS="YES"  
\_BPX\_SPAWN\_SCRIPT="YES"  
\_CEE\_DMPTARG="/tmp"  
\_CEE\_RUNOPTS="ALL31(ON) HEAP(32M,32K,ANYWHERE,KEEP,,) TRAP(ON)"  
\_CMDSERV\_BASE\_HOME="/usr/lpp/ispf"  
\_CMDSERV\_CONF\_HOME="/etc/rdz"  
\_CMDSERV\_WORK\_HOME="/var/rdz"  
\_EDC\_ADD\_ERRNO2="1"

```

_RSE_CMDSERV_OPTS="&SESSION=SPAWN"
_RSE_DAEMON_CLASS="com.ibm.etools.zos.server.RseDaemon"
_RSE_DAEMON_IVP_TEST="1"
_RSE_HOST_CODEPAGE="IBM-1047"
_RSE_JAVA_OPTS=" -DISPF_OPTS='&SESSION=SPAWN' -DA_PLUGIN_PATH=
_RSE_JMON_PORT="6715"
_RSE_LOCKD_CLASS="com.ibm.ftt.rse.mvs.server.miners.MVSLockDaemon"
_RSE_LOCKD_PORT="4036"
_RSE_LOG_LEVEL="1"
_RSE_POOL_SERVER_CLASS="com.ibm.etools.zos.server.ThreadPoolProcess"
_RSE_RSED_PORT="4035"
_RSE_SAF_CLASS="/usr/include/java_classes/IRRracf.jar"
_RSE_SCRIPT_VERSION="Oct22,2010"
_RSE_SERVER_CLASS="org.eclipse.dstore.core.server.Server"
_RSE_SERVER_TIMEOUT="120000"
_SCLMDT_BASE_HOME="/usr/lpp/rdz"
_SCLMDT_CONF_HOME="/var/rdz/sclmdt"
_SCLMDT_TRANSTABLE="FEK.#CUST.LSTRANS.FILE"
_SCLMDT_WORK_HOME="/var/rdz"
debug_level="1"

```

#### ----- Address Space size limits

```

current address space size limit is 1913626624 (1825.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)

```

#### ----- service history

```

Wed Nov 10 13:47:39 2010 -- COPY -- HHOP801 v8010 created 10 Nov 2010
Tue Mar 13 16:08:06 2011 -- COPY -- HHOP801 v8020 created 13 Mar 2011
Fri Sep 30 14:12:42 2011 -- COPY -- HHOP801 v8030 created 30 Sep 2011

```

#### ----- java service level

```

java full version "J2RE 1.5.0 IBM z/OS build pmz31dev-20100813 (SR12

```

#### ----- LE runtime options

```

Options Report for Enclave main 11/10/10 1:50:52 PM
Language Environment V01 R11.00

```

LAST WHERE SET	OPTION
Installation default	ABPERC(NONE)
Programmer default	ABTERMENC(RETCODE)
Installation default	NOAIXBLD
Invocation command	ALL31(ON)
Programmer default	ANYHEAP(32768,16384,ANYWHERE,FREE)
Installation default	NOAUTOTASK
Programmer default	BELOWHEAP(32768,16384,FREE)
Installation default	CBLOPTS(ON)
Installation default	CBLPSTHPOP(ON)
Installation default	CBLQDA(OFF)
Installation default	CEEDUMP(60,SYSOUT=*,FREE=END,SPIN=UNALL
Installation default	CHECK(ON)
Installation default	COUNTRY(US)
Installation default	NODEBUG
Installation default	DEPTHCONDLMT(10)
Installation default	DYNDUMP(*USERID,NODYNAMIC,TDUMP)
Installation default	ENVAR("")
Installation default	ERRCOUNT(0)
Installation default	ERRUNIT(6)

Installation default	FILEHIST
Installation default	FILETAG(NOAUTOCVT,NOAUTOTAG)
Default setting	NOFLOW
Invocation command	HEAP(33554432,32768,ANYWHERE,KEEP,16384
Installation default	HEAPCHK(OFF,1,0,0,0)
Installation default	HEAPPOLS(OFF,8,10,32,10,128,10,256,10,
Installation default	INFMSGFILTER(OFF,,))
Installation default	INQPCOPN
Installation default	INTERRUPT(OFF)
Programmer default	LIBSTACK(32768,16384,FREE)
Installation default	MSGFILE(SYSOUT,FBA,121,0,NOENQ)
Installation default	MSGQ(15)
Installation default	NATLANG(ENU)
Ignored	NONONIPSTACK(See THREADSTACK)
Installation default	OCSTATUS
Installation default	NOPC
Installation default	PLITASKCOUNT(20)
Programmer default	POSIX(ON)
Installation default	PROFILE(OFF,"")
Installation default	PRTUNIT(6)
Installation default	PUNUNIT(7)
Installation default	RDRUNIT(5)
Installation default	RECPAD(OFF)
Invocation command	RPTOPTS(ON)
Installation default	RPTSTG(OFF)
Installation default	NORTEREUS
Installation default	NOSIMVRD
Programmer default	
STACK(65536,65536,ANYWHERE,KEEP,524288,131072)	
Installation default	STORAGE(NONE,NONE,NONE,0)
Installation default	TERMTHDACT(TRACE,,96)
Installation default	NOTEST(ALL,"*","PROMPT","INSPREF")
Installation default	THREADHEAP(4096,4096,ANYWHERE,KEEP)
Installation default	
THREADSTACK(OFF,4096,4096,ANYWHERE,KEEP,131072,	
Installation default	TRACE(OFF,4096,DUMP,LE=0)
Invocation command	TRAP(ON,SPIE)
Installation default	UPSI(00000000)
Installation default	NOUSRHDLR(,)
Installation default	VCTRSAVE(OFF)
Installation default	XPLINK(OFF)
Installation default	XUFLOW(AUTO)

-----  
java startup test...

-----  
java full version "J2RE 1.5.0 IBM z/OS build pmz31dev-20100701a (SR12  
java version "1.5.0"  
Java(TM) 2 Runtime Environment, Standard Edition (build pmz31dev-2010070

IBM J9 VM (build 2.3, J2RE 1.5.0 IBM J9 2.3 z/OS s390-31 j9vmmz3123-2010  
J9VM - 20100629\_60535\_bHdSMr  
JIT - 20100623\_16197\_r8  
GC - 20100211\_AA)  
JCL - 20100813

-----  
JES Job Monitor test...

-----  
executed on CDFMVS08 -- Wed Nov 10 17:50:52 EDT 2010  
executed by uid=8(STCRSE) gid=1(STCGROUP)  
using /etc/rdz/rsed.envvars

current address space size limit is 1913626624 (1825.0 MB)  
maximum address space size limit is 2147483647 (2048.0 MB)

```
testing JES Job Monitor on port 6715...
hostName=CDFMVS08
hostAddr=9.42.112.75
Waiting for JES Job Monitor response...
ACKNOWLEDGE01v03
Success
```

```
-----
Lock Daemon test...
-----
```

```
executed on CDFMVS08 -- Wed Nov 10 17:50:53 EDT 2010
executed by uid=8(STCRSE) gid=1(STCGROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1913626624 (1825.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
testing RSE Lock Daemon on port 4036...
hostName=CDFMVS08
hostAddr=9.42.112.75
```

```
Registering user STCRSE to Lock Daemon...
Waiting for Lock Daemon response...
```

```
Querying to Lock Daemon...
Waiting for Lock Daemon response...
STCRSE
```

```
Unregistering user STCRSE from Lock Daemon...
Waiting for Lock Daemon response...
```

```
Querying to Lock Daemon...
Waiting for Lock Daemon response...
```

```
Success
```

```
-----
TCP/IP IVP test...
-----
```

```
executed on CDFMVS08 -- Wed Nov 10 17:50:53 EDT 2010
executed by uid=8(STCRSE) gid=1(STCGROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1913626624 (1825.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
-----
TCP/IP resolver configuration (z/OS UNIX search order):
-----
```

```
Resolver Trace Initialization Complete -> 2010/11/10 17:50:54.208378
```

```
res_init Resolver values:
Global Tcp/Ip Dataset = None
Default Tcp/Ip Dataset = None
Local Tcp/Ip Dataset = /etc/resolv.conf
Translation Table = Default
UserId/JobName = STCRSE
Caller API = LE C Sockets
Caller Mode = EBCDIC
(L) DataSetPrefix = TCPIP
(L) HostName = CDFMVS08
(L) TcpIpJobName = TCPIP
(L) DomainOrigin = RALEIGH.IBM.COM
(L) NameServer = 9.42.206.2
                  9.42.206.3
(L) NsPortAddr = 53 (L) ResolverTimeout = 10
```

```

(L) ResolveVia      = UDP                (L) ResolverUdpRetries = 1
(*) Options NDots   = 1
(*) SockNoTestStor
(*) AlwaysWto       = NO                 (L) MessageCase      = MIXED
(*) LookUp          = DNS LOCAL
res_init Succeeded
res_init Started: 2010/11/10 17:50:54.229888
res_init Ended: 2010/11/10 17:50:54.229898
*****
MVS TCP/IP NETSTAT CS V1R11      TCPIP Name: TCPIP          17:50:54
Tcpiip started at 11:31:40 on 11/10/2010 with IPv6 enabled

-----
host IP address:
-----
hostName=CDFMVS08
hostAddr=9.42.112.75
bindAddr=9.42.112.75
localAddr=9.42.112.75

Success, addresses match

-----
PassTicket IVP test...
-----

executed on CDFMVS08 -- Wed Nov 10 17:50:52 EDT 2010
executed by uid=8(STCRSE) gid=1(STCGROUP)
the default applid=FEKAPPL
Success, PassTicket IVP finished normally

-----
RSE daemon IVP ended -- return code 0 -- Wed Nov 10 17:50:55 EDT 2010
-----

```

**Note:** Start the RSE daemon, without the IVP parameter, before continuing with the other IVP tests. RSE daemon issues the following console message upon successful startup:

```
FEK002I RseDaemon started. (port=4035)
```

---

## IVP operator commands

An active RSE daemon supports the **IVP** modify command, which allows you to do selected IVPs from the console.

### PassTicket reusability

Developer for System z requires that the PassTickets it generates are reusable, because PassTicket generation is limited to one per user per second. Verify PassTicket reusability by executing the following operator command. Replace userid with a valid user ID.

```
MODIFY RSED,APPL=IVP PASSTICKET,userid
```

The command should return an output like that in the following sample:

```

MODIFY RSED,APPL=IVP PASSTICKET,IBMUSER

+FEK900I PASSTICKET IVP: the default applid=FEKAPPL
+FEK900I PASSTICKET IVP: Success, PassTicket IVP finished normally
+FEK901I PASSTICKET IVP Exit code = 0

```

## RSE daemon connection

Verify the RSE daemon connection by executing the following command. Replace userid with a valid user ID.

```
MODIFY RSED,APPL=IVP DAEMON,userid
```

Note that this command is functionally identical to the fekfivpd IVP described in “Verify services” on page 110, but with the benefit that no password is required. RSE will generate a PassTicket and use this as password. The command should return an output like that in the following sample:

```
F RSED,APPL=IVP DAEMON,IBMUSER

+FEK900I DAEMON IVP: SSL is disabled
+FEK900I DAEMON IVP: connected
+FEK900I DAEMON IVP: 1343
+FEK900I DAEMON IVP: 8878350
+FEK900I DAEMON IVP: Success
+FEK901I DAEMON IVP Exit code = 0
```

## ISPF Client Gateway

Verify the ISPF Client Gateway connection by executing the following command. Replace userid with a valid user ID.

```
MODIFY RSED,APPL=IVP ISPF,userid
```

Note that this command is functionally identical to the fekfivpi IVP described in “Verify services” on page 110. The command should return an output like that in the following sample:

```
F RSED,APPL=IVP ISPF,IBMUSER

+FEK900I ISPF IVP: executed on CDFMVS08 -- Tue Sep 13 22:29:28 EDT 2011
+FEK900I ISPF IVP: executed by uid=1(IBMUSER) gid=0(SYS1)
+FEK900I ISPF IVP: using /etc/rdz/rsed.envvars
+FEK900I ISPF IVP: current address space size limit is 2147483647
(2048.0 MB)
+FEK900I ISPF IVP: maximum address space size limit is 2147483647
(2048.0 MB)
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: /etc/rdz/ISPF.conf content:
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: isplib=ISP.SISPLOAD
+FEK900I ISPF IVP: ispmplib=ISP.SISPMENU
+FEK900I ISPF IVP: isptlib=ISP.SISPTENU
+FEK900I ISPF IVP: ispplib=ISP.SISPPENU
+FEK900I ISPF IVP: ispslib=ISP.SISPSLIB
+FEK900I ISPF IVP: sysproc=ISP.SISPCLIB,FEK.SFEKPROC
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: Host install verification for RSE
+FEK900I ISPF IVP: Review IVP log messages from HOST below :
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: Service level 22Feb2011
+FEK900I ISPF IVP: RSE connection and base TS0/ISPF session initializati
on check only
+FEK900I ISPF IVP: *** CHECK : ENVIRONMENT VARIABLES - key variables
displayed below :
+FEK900I ISPF IVP: Server PATH = ./usr/lpp/java/J5.0/bin:/usr/l
pp/rdz/bin:/usr/lpp/ispf/bin:/bin:/usr/sbin
+FEK900I ISPF IVP: STEPLIB = NONE
+FEK900I ISPF IVP: Temporary directory = /tmp
```

```

+FEK900I ISPF IVP: _CMDSERV_BASE_HOME = /usr/lpp/ispf
+FEK900I ISPF IVP: _CMDSERV_CONF_HOME = /etc/rdz
+FEK900I ISPF IVP: _CMDSERV_WORK_HOME = /var/rdz
+FEK900I ISPF IVP: -----
+FEK900I ISPF IVP: *** CHECK : USS MODULES
+FEK900I ISPF IVP: Checking ISPF Directory : /usr/lpp/ispf
+FEK900I ISPF IVP: Checking modules in /usr/lpp/ispf/bin directory
+FEK900I ISPF IVP: Checking for ISPF configuration file ISPF.conf
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
+FEK900I ISPF IVP: *** CHECK : TSO/ISPF INITIALIZATION
+FEK900I ISPF IVP: ( TSO/ISPF session will be initialized )
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
+FEK900I ISPF IVP: *** CHECK: Shutting down TSO/ISPF IVP session
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
+FEK900I ISPF IVP: Host installation verification completed successfully
+FEK900I ISPF IVP: -----
+FEK901I ISPF IVP Exit code = 0

```

## Verify services

The Developer for System z installation provides several Installation Verification Programs (IVP) for the basic and optional services. The IVP scripts are located in the installation directory, default /usr/lpp/rdz/bin/.

Table 17. IVPs for services

fekfivpc	"(Optional) CARMA connection" on page 116
fekfivpd	"RSE daemon connection" on page 113
fekfivpi	"ISPF's TSO/ISPF Client Gateway connection" on page 115
fekfivpj	"JES Job Monitor connection" on page 114
fekfivpl	"Lock daemon connection" on page 114
fekfivps	"(Optional) SCLMDT connection" on page 117
fekfivpt	"TCP/IP setup" on page 112

The tasks described below expect you to be active in z/OS UNIX. This can be done by issuing the TSO command **OMVS**. Use the **exit** command to return to TSO.

A large region size is required for the user ID that executes the IVPs, because functions such as Java, which require a lot of memory, will be executed. You should set the region size to 131072 kilobytes (128 megabytes) or higher.

The following sample error is a clear indication of an insufficient region size. (But other errors can occur, too. For example, Java might fail to start.)



```
CEE5213S The signal SIGPIPE was received.
%z/OS UNIX command%: command was killed by signal number 13
%line-number% ** %REXX command%
+++ RC(137) +++
```

**Note:** The Developer for System z started tasks must be active before starting the IVP test.

## IVP initialization

All sample commands in this section expect that certain environment variables are set. This way, the IVP scripts are available through the PATH statement and the location of the customized configuration files is known. Use the **pwd** and **cd** commands to verify and change your current directory to the directory with the customized configuration files. The **ivpinit** shell script can then be used to set the RSE environment variables, such as in the following sample (\$ is the z/OS UNIX prompt):

```
$ pwd
/u/userid
$ cd /etc/rdz
$ . ./ivpinit
RSE configuration files located in /etc/rdz --default
added /usr/lpp/rdz/bin to PATH
```

The first "." (dot) in **./ivpinit** is a z/OS UNIX command to run the shell in the current environment, so that the environment variables set in the shell are effective even after exiting the shell. The second one is referring to the current directory.

### Note:

- If **./ivpinit** is NOT executed before the **fekfivp\*** scripts, the path to these scripts must be specified when calling them, as in the following sample:  
`/usr/lpp/rdz/bin/fekfivpr 512 USERID`

Also, all **fekfivp\*** scripts will ask for the location of the customized **rsed.envvars** if **./ivpinit** is not executed first.

- Some IVP tests use the TCP/IP REXX socket API, which requires that the TCP/IP load library, default **TCPIP.SEZALOAD**, is in **LINKLIST** or **STEPLIB**. The following commands might be necessary to be able to execute these IVP tests (\$ is the z/OS UNIX prompt):

```
$ EXPORT STEPLIB=$STEPLIB:TCPIP.SEZALOAD
```

Note that adding a non-APF authorized library to an existing **STEPLIB** removes the APF authorization for existing **STEPLIB** data sets.

Also note that if **CEE.SCEELKED** is in **LINKLIST** or **STEPLIB**, **TCPIP.SEZALOAD** must be placed before **CEE.SCEELKED**. Failure to do so will result in a 0C1 system abend for the TCP/IP REXX socket calls.

For information about diagnosing RSE connection problems, see "Troubleshooting configuration problems" in the *Host Configuration Reference* (SC14-7290) and the Technotes on the Developer for System z Support Page <http://www-306.ibm.com/software/awdtools/rdz/support/>.

## Port availability

The JES Job Monitor, RSE daemon, and Lock daemon port availability can be verified by issuing the **netstat** command. The result should show the ports used by these services, as in the following samples (\$ is the z/OS UNIX prompt):

## IPv4

```
$ netstat
MVS TCP/IP NETSTAT CS VxRy   TCPIP Name: TCPIP      13:57:36
User Id  Conn      Local Socket      Foreign Socket      State
-----  ----  -----
RSED     0000004B 0.0.0.0..4035     0.0.0.0..0         Listen
LOCKD    0000004C 0.0.0.0..4036     0.0.0.0..0         Listen
JMON     00000037 0.0.0.0..6715     0.0.0.0..0         Listen
```

## IPv6

```
$ netstat
MVS TCP/IP NETSTAT CS VxRy   TCPIP Name: TCPIP      14:03:35
User Id  Conn      State
-----  ----  -----
RSED     0000004B Listen
Local Socket: 0.0.0.0..4035
Foreign Socket: 0.0.0.0..0
LOCKD    0000004C Listen
Local Socket: 0.0.0.0..4036
Foreign Socket: 0.0.0.0..0
JMON     00000037 Listen
Local Socket: 0.0.0.0..6715
Foreign Socket: 0.0.0.0..0
```

## TCP/IP setup

Developer for System z is dependent upon TCP/IP having the correct hostname when it is initialized. This implies that the different TCP/IP and Resolver configuration files must be set up correctly. Refer to "Setting up TCP/IP" in the *Host Configuration Reference* (SC14-7290) for more information about TCP/IP and Resolver setup. Verify the current settings by executing the following command:

```
fekfivpt
```

**Note:** This IVP issues the TCPIP **netstat** command, which might be protected against execution by your security software.

The command should return an output like that in this sample (\$ is the z/OS UNIX prompt):

```
$ fekfivpt

executed on CDFMVS08 -- Wed Jul  2 13:11:54 EDT 2008
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars

current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)

-----
TCP/IP resolver configuration (z/OS UNIX search order):
-----
Resolver Trace Initialization Complete -> 2008/07/02 13:11:54.745964

res_init Resolver values:
Global Tcp/Ip Dataset = None
Default Tcp/Ip Dataset = None
Local Tcp/Ip Dataset  = /etc/resolv.conf
Translation Table      = Default
UserId/JobName          = USERID
Caller API              = LE C Sockets
Caller Mode             = EBCDIC
(L) DataSetPrefix      = TCPIP
(L) HostName           = CDFMVS08
(L) TcpIpJobName       = TCPIP
```

```

(L) DomainOrigin = RALEIGH.IBM.COM
(L) NameServer   = 9.42.206.2
                  9.42.206.3
(L) NsPortAddr   = 53           (L) ResolverTimeout    = 10
(L) ResolveVia   = UDP         (L) ResolverUdpRetries = 1
(*) Options NDots = 1
(*) SockNoTestStor
(*) AlwaysWto    = NO          (L) MessageCase       = MIXED
(*) LookUp       = DNS LOCAL
res_init Succeeded
res_init Started: 2008/07/02 13:11:54.755363
res_init Ended: 2008/07/02 13:11:54.755371
*****
MVS TCP/IP NETSTAT CS V1R9      TCPIP Name: TCPIP      13:11:54
Tcpiip started at 01:28:36 on 06/23/2008 with IPv6 enabled

-----
host IP address:
-----
hostName=CDFMVS08
hostAddr=9.42.112.75
bindAddr=9.42.112.75
localAddr=9.42.112.75

Success, addresses match

```

## RSE daemon connection

Verify the RSE daemon connection by executing the following command.

```
fekfivpd
```

After prompting you for a password, the command should return an output similar to what appears in the following sample (\$ is the z/OS UNIX prompt):

```

$ fekfivpd

executed on CDFMVS08 -- Wed Jul  2 15:00:27 EDT 2008
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars

current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)

attempting to connect userid USERID using port 4035 ...

Password:
SSL is disabled
connected
8108
570655399
Success

```

When testing an SSL-enabled connection, ensure that the user ID executing the IVP has access to all certificates that are involved (including the CA certificates used to sign the Developer for System z certificate). Note that the operator command version of this IVP (F RSED,APPL=IVP DAEMON,userid) uses the SSL setup done for RSE host, and is therefore less error prone. The following list documents some common SSL-related errors:

- Verify that the user ID executing the IVP has access to all certificates that are involved if you get this error message: `gsk_environment_init() failed: Error detected while opening the certificate data base`

- Verify that the signing CA certificates are also on the keyring if you get this error message: `gsk_secure_socket_init() failed: Certificate validation error`

## JES Job Monitor connection

Verify the JES Job Monitor connection by executing the following command.

```
fekfivpj
```

The command should return the JES Job Monitor acknowledge message, similar to what appears in the following sample (\$ is the z/OS UNIX prompt):

```
$ fekfivpj
```

```
executed on CDFMVS08 -- Wed Jul  2 15:00:27 EDT 2008
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
testing JES Job Monitor on port 6715...
hostName=CDFMVS08
hostAddr=9.42.112.75
Waiting for JES Job Monitor response...
ACKNOWLEDGE01v03
```

```
Success
```

## Lock daemon connection

Verify the lock daemon connection by executing the following command.

```
fekfivpl
```

The command should return an output similar to what appears in the following sample (\$ is the z/OS UNIX prompt):

```
$ fekfivpl
```

```
executed on CDFMVS08 -- Mon Jun 29 08:00:38 EDT 2009
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
testing RSE Lock Daemon on port 4036...
hostName=CDFMVS08
hostAddr=9.42.112.75
```

```
Registering user to Lock Daemon...
Waiting for Lock Daemon response...
```

```
Querying to Lock Daemon...
Waiting for Lock Daemon response...
USERID
```

```
Unregistering user from Lock Daemon...
Waiting for Lock Daemon response...
```

```
Querying to Lock Daemon...
```

Waiting for Lock Daemon response...

Success

## ISPF's TSO/ISPF Client Gateway connection

Verify the connection to ISPF's TSO/ISPF client Gateway by executing the following command:

```
fekfivpi
```

The command should return the result of ISPF's TSO/ISPF client Gateway-related checks (variables, HFS modules, starting and stopping TSO/ISPF session), similar to what appears in the following sample (\$ is the z/OS UNIX prompt):

```
$ fekfivpi
```

```
executed on CDFMVS08 -- Wed Jul  2 15:00:27 EDT 2008
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
-----
/etc/rdz/ISPF.conf content:
-----
```

```
isplib=ISP.SISPMENU
isptlib=ISP.SISPTENU
isplib=ISP.SISPPENU
ispslib=ISP.SISPSLIB
ispllib=ISP.SISPLOAD
sysproc=ISP.SISPCLIB,FEK.SFEKPROC
```

```
-----
Host install verification for RSE
Review IVP log messages from HOST below :
-----
```

RSE connection and base TSO/ISPF session initialization check only

\*\*\* CHECK : ENVIRONMENT VARIABLES - key variables displayed below :

```
Server PATH          =
/usr/lpp/java/J5.0/bin:/usr/lpp/rdz/lib:/usr/lpp/ispf/bin:
/bin:/usr/sbin:.
```

```
STEPLIB              = FEK.SFEKAUTH:FEK.SFEKLOAD
```

```
_CMDSERV_BASE_HOME   = /usr/lpp/ispf
_CMDSERV_CONF_HOME    = /etc/rdz
_CMDSERV_WORK_HOME    = /var/rdz
-----
```

```
*** CHECK : USS MODULES
Checking ISPF Directory : /usr/lpp/ispf
Checking modules in /usr/lpp/ispf/bin directory
Checking for ISPF configuration file ISPF.conf
RC=0
MSG: SUCCESSFUL
```

```
-----
*** CHECK : TSO/ISPF INITIALIZATION
( TSO/ISPF session will be initialized )
RC=0
MSG: SUCCESSFUL
```

```
-----
*** CHECK: Shutting down TSO/ISPF IVP session
RC=0
MSG: SUCCESSFUL
-----
```

```
-----
Host installation verification completed successfully
-----
```

**Note:** If any of the ISPF checks fail, more detailed information will be shown.

fekfivpi has the following optional, non-positional, parameters:

**-file**    fekfivpi can produce large amounts of output (hundreds of lines). The -file parameter sends this output to a file, \$TMPDIR/fekfivpi.log, where \$TMPDIR is the value of the TMPDIR directive in rsed.envvars (default /tmp).

**-debug**

The -debug parameter creates detailed test output. Do not use this option unless directed by the IBM support center.

## (Optional) CARMA connection

Verify the connection to CARMA by executing the following command:

```
fekfivpc
```

The command should return the result of CARMA related checks, like in the following sample (\$ is the z/OS UNIX prompt):

```
$ fekfivpc
```

```
executed on CDFMVS08 -- Fri Aug 20 14:15:46 EDT 2010
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 140484608 ( 134.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
*** /etc/rdz/CRASRV.properties content:
port.start = 5227
port.range = 100
startup.script.name = /usr/lpp/rdz/bin/carma.startup.rex
clist.dsname = *CRASTART
crastart.stub = /usr/lpp/rdz/bin/CRASTART
crastart.configuration.file = /etc/rdz/crastart.endevor.conf
crastart.syslog = Partial
crastart.timeout = 420
```

```
*** Creating /tmp/fekfivpc.log
```

```
*** Verifying CARMA installation...
```

1. Creating CARMA connection (timeout after 60 seconds)
2. Initializing CARMA
3. Retrieving RAM list
  - The following RAMs were found
  - 00 CA Endevor SCM            Unique ID: COM.IBM.CARMA.ENDEVORRAM
4. Getting customization data for RAM 00
5. Initializing RAM 00
6. Retrieving Repository Instance List
  - Found 6 Repository Instance(s)
7. Terminating RAM 00
8. Terminating CARMA

```
*** IVP Successful!!!!
```

**Note:** Verify the content of /tmp/fekfivpc.log if the IVP fails. This log documents the communication between RSE and CARMA and can hold valuable clues to find the root cause of the failure.

fekfivpc has the following optional, non-positional, parameters:

**-noram**

By default, fekfivpc will start the first RAM that is defined in the CRADEF VSAM data set. If you do not want to test the RAM (for example, a third party RAM is listed first, and it requires unexpected input), you can use the -noram startup argument to skip the RAM specific steps (step 4 through 7) of the IVP test.

## (Optional) SCLMDT connection

Verify the connection to SCLM Developer Toolkit by executing the following command:

```
fekfivps
```

The command should return the result of SCLM Developer Toolkit related checks (variables, HFS modules, REXX runtime, starting and stopping TSO/ISPF session), like that in the following sample (\$ is the z/OS UNIX prompt):

```
$ fekfivps
```

```
executed on CDFMVS08 -- Wed Jul  2 15:00:27 EDT 2008
executed by uid=1(USERID) gid=0(GROUP)
using /etc/rdz/rsed.envvars
```

```
current address space size limit is 1914675200 (1826.0 MB)
maximum address space size limit is 2147483647 (2048.0 MB)
```

```
-----
/etc/rdz/ISPF.conf content:
-----
```

```
isplib=ISP.SISPMENU
isptlib=ISP.SISPTENU
ispplib=ISP.SISPPENU
ispslib=ISP.SISPSLIB
ispllib=ISP.SISPLOAD
sysproc=ISP.SISPCLIB,FEK.SFEKPROC
-----
```

```
Host install verification for RSE
Review IVP log messages from HOST below :
-----
```

```
*** CHECK : ENVIRONMENT VARIABLES - key variables displayed below :
```

```
Server PATH          = /usr/lpp/java/J5.0/bin:/usr/lpp/rdz/lib:/usr/lpp/ispf/bin:
/bin:/usr/sbin:.
```

```
STEPLIB              = FEK.SFEKAUTH:FEK.SFEKLOAD
```

```
_CMDSERV_BASE_HOME   = /usr/lpp/ispf
_CMDSERV_CONF_HOME   = /etc/rdz
_CMDSERV_WORK_HOME    = /var/rdz
_SCLMDT_CONF_HOME     = /var/rdz/sclmdt
_SCLMDT_WORK_HOME     = /var/rdz
_SCLMDT_TRANTABLE     = FEK.#CUST.LSTRANS.FILE
-----
```

```
*** CHECK : JAVA PATH SETUP VERIFICATION
RC=0
```

MSG: SUCCESSFUL

```
-----  
*** CHECK : USS MODULES  
Checking ISPF Directory : /usr/lpp/ispf  
Checking modules in /usr/lpp/ispf/bin directory  
Checking for ISPF configuration file ISPF.conf  
Checking install bin Directory : /usr/lpp/rdz/bin  
RC=0  
MSG: SUCCESSFUL
```

```
-----  
*** CHECK : REXX RUNTIME ENVIRONMENT  
RC=0  
MSG: SUCCESSFUL
```

```
-----  
*** CHECK : TSO/ISPF INITIALIZATION  
( TSO/ISPF session will be initialized )  
RC=0  
MSG: SUCCESSFUL
```

```
-----  
*** CHECK: Shutting down TSO/ISPF IVP session  
RC=0  
MSG: SUCCESSFUL
```

```
-----  
Host installation verification completed successfully  
-----
```

**Note:** If any of the SCLMDT checks fail, more detailed information will be shown.

fekfivps has the following optional, non-positional, parameters:

**-file**     fekfivps can produce large amounts of output (hundreds of lines). The -file parameter sends this output to a file, \$TMPDIR/fekfivps.log, where \$TMPDIR is the value of the TMPDIR directive in rsed.envvars (default /tmp).

**-debug**

The -debug parameter creates detailed test output. Do not use this option unless directed by the IBM support center.



---

## Chapter 8. Security definitions

Customize and submit sample member FEKRACF, which has sample RACF and z/OS UNIX commands to create the basic security definitions for Developer for System z.

FEKRACF is located in FEK.#CUST.JCL, unless you specified a different location when you customized and submitted job FEK.SFEKSAMP(FEKSETUP). See “Customization setup” on page 11 for more details.

Refer to the *RACF Command Language Reference* (SA22-7687), for more information about RACF commands.

### Note:

- For those sites that use CA ACF2™ for z/OS, please refer to your product page on the CA support site ( <https://support.ca.com>) and check for the related Developer for System z Knowledge Document, TEC492389. This Knowledge Document has details on the security commands necessary to properly configure Developer for System z.
- For those sites that use CA Top Secret® for z/OS, please refer to your product page on the CA support site (<https://support.ca.com>) and check for the related Developer for System z Knowledge Document, TEC492091. This Knowledge Document has details on the security commands necessary to properly configure Developer for System z.

The following sections describe the required steps, optional configuration and possible alternatives.

---

## Requirements and checklist

To complete the security setup, the security administrator needs to know the values listed in Table 18. These values were defined during previous steps of the installation and customization of Developer for System z.

Table 18. Security setup variables

Description	<ul style="list-style-type: none"><li>• Default value</li><li>• Where to find the answer</li></ul>	Value
Developer for System z product high level qualifier	<ul style="list-style-type: none"><li>• FEK</li><li>• SMP/E installation</li></ul>	
Developer for System z customization high level qualifier	<ul style="list-style-type: none"><li>• FEK.#CUST</li><li>• FEK.SFEKSAMP(FEKSETUP), as described in “Customization setup” on page 11.</li></ul>	
JES Job Monitor started task name	<ul style="list-style-type: none"><li>• JMON</li><li>• FEK.#CUST.PROCLIB(JMON), as described in “PROCLIB changes” on page 17.</li></ul>	

Table 18. Security setup variables (continued)

Description	<ul style="list-style-type: none"> <li>• <b>Default value</b></li> <li>• <b>Where to find the answer</b></li> </ul>	Value
RSE daemon started task name	<ul style="list-style-type: none"> <li>• RSED</li> <li>• FEK.#CUST.PROCLIB(RSED), as described in "PROCLIB changes" on page 17.</li> </ul>	
Lock daemon started task name	<ul style="list-style-type: none"> <li>• LOCKD</li> <li>• FEK.#CUST.PROCLIB(LOCKD), as described in "PROCLIB changes" on page 17.</li> </ul>	
Application ID	<ul style="list-style-type: none"> <li>• FEKAPPL</li> <li>• /etc/rdz/rsed.envvars, as described in "Defining extra Java startup parameters with _RSE_JAVAOPTS" on page 36</li> </ul>	

The following list is an overview of the required actions to complete the basic security setup of Developer for System z. As documented in the sections below, different methods can be used to fulfill these requirements, depending on the desired security level. Refer to the previous sections for information about the security setup of optional Developer for System z services.

- "Activate security settings and classes"
- "Define an OMVS segment for Developer for System z users" on page 122
- "Define data set profiles" on page 122
- "Define the Developer for System z started tasks" on page 126
- "Define JES command security" on page 127
- "Define RSE as a secure z/OS UNIX server" on page 129
- "Define MVS program controlled libraries for RSE" on page 129
- "Define application protection for RSE" on page 130
- "Define PassTicket support for RSE" on page 130
- "Define z/OS UNIX program controlled files for RSE" on page 132
- "Verify security settings" on page 132

## Activate security settings and classes

Developer for System z utilizes a variety of security mechanisms to ensure a secure and controlled host environment for the client. In order to do so, several classes and security settings must be active, as shown with the following sample RACF commands:

- Display current settings
  - 
  - SETROPTS LIST
- Activate facility class for z/OS UNIX and digital certificate profiles
  - 
  - SETROPTS GENERIC(FACILITY)

- - SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY)
- Activate started task definitions
  - 
  - SETROPTS GENERIC(STARTED)
  - 
  - RDEFINE STARTED \*\* STDATA(USER(=MEMBER) GROUP(STCGROUP) TRACE(YES))
  - 
  - SETROPTS CLASSACT(STARTED) RACLIST(STARTED)
- Activate console security for JES Job Monitor
  - 
  - SETROPTS GENERIC(CONSOLE)
  - 
  - SETROPTS CLASSACT(CONSOLE) RACLIST(CONSOLE)
- Activate operator command protection for JES Job Monitor
  - 
  - SETROPTS GENERIC(OPERCMDS)
  - 
  - SETROPTS CLASSACT(OPERCMDS) RACLIST(OPERCMDS)
- Activate application protection for RSE
  - 
  - SETROPTS GENERIC(APPL)
  - 
  - SETROPTS CLASSACT(APPL) RACLIST(APPL)
- Activate secured signon using PassTickets for RSE
  - 
  - SETROPTS GENERIC(PTKTDATA)
  - 
  - SETROPTS CLASSACT(PTKTDATA) RACLIST(PTKTDATA)
- Activate program control to ensure that only trusted code can be loaded by RSE
  - 
  - RDEFINE PROGRAM \*\* ADDMEM('SYS1.CMDLIB'//NOPADCHK) UACC(READ)
  - 
  - SETROPTS WHEN(PROGRAM)

**Note:** Do not create the \*\* profile if you already have a \* profile in the PROGRAM class. It obscures and complicates the search path used by your security software. In this case, you must merge the existing \* and the new \*\* definitions. IBM recommends to use the \*\* profile, as documented in *Security Server RACF Security Administrator's Guide* (SA22-7683).

**Attention:** Some products, such as FTP, require being program controlled if "WHEN PROGRAM" is active. Test this before activating it on a production system.
- (Optional) Activate X.509 HostIdMappings and extended Port Of Entry (POE) support
  - 
  - SETROPTS GENERIC(SERVAUTH)

---

## Define an OMVS segment for Developer for System z users

A RACF OMVS segment (or equivalent) that specifies a valid non-zero z/OS UNIX user ID (UID), home directory, and shell command must be defined for each user of Developer for System z. Their default group also requires an OMVS segment with a group id.

Replace in the following sample RACF commands the #userid, #user-identifier, #group-name and #group-identifier placeholders with actual values:

- 
- ```
ALTUSER #userid
OMVS(UID(#user-identifier) HOME(/u/#userid) PROGRAM(/bin/sh) NOASSIZEMAX)
```
- 
- ```
ALTGROUP #group-name OMVS(GID(#group-identifier))
```

Although it is advised not to do so, you can use the shared OMVS segment defined in the BPX.DEFAULT.USER profile of the FACILITY class to fulfill the OMVS segment requirement for Developer for System z.

---

## Define data set profiles

READ access for users and ALTER for system programmers suffices for most Developer for System z data sets. Replace the #sysprog placeholder with valid user IDs or RACF group names. Also ask the system programmer who installed and configured the product for the correct data set names. FEK is the default high-level qualifier used during installation and FEK.#CUST is the default high-level qualifier for data sets created during the customization process.

- 
- ```
ADDGROUP (FEK) OWNER(IBMUSER) SUPGROUP(SYS1)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - HLQ STUB')
```
- 
- ```
ADDSD 'FEK.*.**' UACC(READ)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- 
- ```
PERMIT 'FEK.*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```
- 
- ```
SETROPTS GENERIC(DATASET) REFRESH
```

### Note:

- You are strongly advised to protect FEK.SFEKAUTH against updates since this data set is APF authorized. The same is true for FEK.SFEKLOAD and FEK.SFEKLPA, but here because these data sets are program controlled.
- The sample commands in this publication and in the FEKRACF job assume that EGN (Enhanced Generic Naming) is active. This allows the usage of the \*\* qualifier to represent any number of qualifiers in the DATASET class. Substitute \* with \* if EGN is not active on your system. Refer to *Security Server RACF Security Administrator's Guide* (SA22-7683) for more information about EGN.

Some of the optional Developer for System z components require additional security data set profiles. Replace the #sysprog, #ram-developer and #cicsadmin placeholders with valid user ID's or RACF group names:

- If SCLM Developer Toolkit's long/short name translation is used, then users require UPDATE access to the mapping VSAM, FEK.#CUST.LSTRANS.FILE.

```

-
  ADDSD 'FEK.#CUST.LSTRANS.*.**' UACC(UPDATE)
    DATA('RATIONAL DEVELOPER FOR SYSTEM Z - SCLMDT')
-
  PERMIT 'FEK.#CUST.LSTRANS.*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
  SETROPTS GENERIC(DATASET) REFRESH

```

- CARMA RAM (Repository Access Manager) developers require UPDATE access to the CARMA VSAMs, FEK.#CUST.CRA\*.

```

-
  ADDSD 'FEK.#CUST.CRA*.**' UACC(READ)
    DATA('RATIONAL DEVELOPER FOR SYSTEM Z - CARMA')
-
  PERMIT 'FEK.#CUST.CRA*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
  PERMIT 'FEK.#CUST.CRA*.**' CLASS(DATASET) ACCESS(UPDATE) ID(#ram-developer)
-
  SETROPTS GENERIC(DATASET) REFRESH

```

- If Application Deployment Manager's CRD server (CICS Resource Definition) is used, then CICS administrators require UPDATE access to the CRD repository VSAM.

```

-
  ADDSD 'FEK.#CUST.ADNREP*.**' UACC(READ)
    DATA('RATIONAL DEVELOPER FOR SYSTEM Z - ADN')
-
  PERMIT 'FEK.#CUST.ADNREP*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
  PERMIT 'FEK.#CUST.ADNREP*.**' CLASS(DATASET) ACCESS(UPDATE) ID(#cicsadmin)
-
  SETROPTS GENERIC(DATASET) REFRESH

```

- If Application Deployment Manager's manifest repository is defined, then all CICS Transaction Server users require UPDATE access to the manifest repository VSAM.

```

-
  ADDSD 'FEK.#CUST.ADNMAN*.**' UACC(UPDATE)
    DATA('RATIONAL DEVELOPER FOR SYSTEM Z - ADN')
-
  PERMIT 'FEK.#CUST.ADNMAN*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
  SETROPTS GENERIC(DATASET) REFRESH

```

Use the following sample RACF commands for a more secure setup where READ access is also controlled.

- uacc(none) data set protection

```

-

```

```
ADDGROUP (FEK)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - HLQ STUB')
OWNER(IBMUSER) SUPGROUP(SYS1)"
```

```
—
ADDSD 'FEK.*.**' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.SFEKAUTH' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.SFEKLOAD' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.SFEKPROC' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.#CUST.PARMLIB' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.#CUST.CNTL' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```

```
—
ADDSD 'FEK.#CUST.LSTRANS.*.**' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - SCLMDT')
```

```
—
ADDSD 'FEK.#CUST.CRA*.**' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - CARMA')
```

```
—
ADDSD 'FEK.#CUST.ADNREP*.**' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - ADN')
```

```
—
ADDSD 'FEK.#CUST.ADNMAN*.**' UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z - ADN')
```

- permit system programmer to manage all libraries

```
—
PERMIT 'FEK.*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.SFEKAUTH' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.SFEKLOAD' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.SFEKLOAD' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.SFEKLOAD' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.SFEKPROC' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.#CUST.PARMLIB' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```
—
PERMIT 'FEK.#CUST.CNTL' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
```

```

-
PERMIT 'FEK.#CUST.LSTRANS.*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
PERMIT 'FEK.#CUST.CRA*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
PERMIT 'FEK.#CUST.ADNREP*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
-
PERMIT 'FEK.#CUST.ADNMAN*.**' CLASS(DATASET) ACCESS(ALTER) ID(#sysprog)
• permit clients to access the load and exec libraries
-
PERMIT 'FEK.SFEKAUTH' CLASS(DATASET) ACCESS(READ) ID(*)
-
PERMIT 'FEK.SFEKLOAD' CLASS(DATASET) ACCESS(READ) ID(*)
-
PERMIT 'FEK.SFEKPROC' CLASS(DATASET) ACCESS(READ) ID(*)
-
PERMIT 'FEK.#CUST.CNTL' CLASS(DATASET) ACCESS(READ) ID(*)

Note: No permits are needed for FEK.SFEKLPA, as all code that resides in LPA is
accessible by everyone.
• permit JES Job Monitor to access the load and parameter library
-
PERMIT 'FEK.SFEKAUTH' CLASS(DATASET) ACCESS(READ) ID(STCJMON)
-
PERMIT 'FEK.#CUST.PARMLIB' CLASS(DATASET) ACCESS(READ) ID(STCJMON)
• (optional) permit clients to update the long/short name translation VSAM for
SCLMDT
-
PERMIT 'FEK.#CUST.LSTRANS.*.**' CLASS(DATASET) ACCESS(UPDATE) ID(*)
• (optional) permit RAM developers to update the CARMA VSAMs for CARMA
-
PERMIT 'FEK.#CUST.CRA*.**' CLASS(DATASET) ACCESS(UPDATE) ID(#ram-developer)
• (optional) permit CICS users to read the CRD repository VSAM for Application
Deployment Manager
-
PERMIT 'FEK.#CUST.ADNREP*.**' CLASS(DATASET) ACCESS(READ) ID(*)
• (optional) permit CICS administrators to update the CRD repository VSAM for
Application Deployment Manager
-
PERMIT 'FEK.#CUST.ADNREP*.**' CLASS(DATASET) ACCESS(UPDATE) ID(#cicsadmin)
• (optional) permit CICS users to update the manifest repository VSAM for
Application Deployment Manager
-
PERMIT 'FEK.#CUST.ADNMAN*.**' CLASS(DATASET) ACCESS(UPDATE) ID(*)
• (optional) permit CICS TS server to access the load library for bidi and
Application Deployment Manager
-
PERMIT 'FEK.SFEKLOAD' CLASS(DATASET) ACCESS(READ) ID(#cicsts)

```

- (optional) permit DB2 server to access the exec library for DB2 stored procedure builder

—

```
PERMIT 'FEK.SFEKPROC' CLASS(DATASET) ACCESS(READ) ID(#db2)
```

- activate security profiles

—

```
SETROPTS GENERIC(DATASET) REFRESH
```

When controlling READ access to system data sets, you must provide Developer for System z servers and users permission to READ the following data sets:

- CEE.SCEERUN
- CEE.SCEERUN2
- CBC.SCLBDLL
- ISP.SISPLoad
- ISP.SISPLPA
- SYS1.LINKLIB
- SYS1.SIEALNKE
- REXX.V1R4M0.SEAGLPA

**Note:** When you use the Alternate Library for REXX product package, the default REXX runtime library name is REXX.\*.SEAGALT. instead of REXX.\*.SEAGLPA, as used in the sample above.

---

## Define the Developer for System z started tasks

The following sample RACF commands create the JMON, RSED, and LOCKD started tasks, with protected user IDs (STCJMON, STCRSE, and STCLOCK respectively) and group STCGROUP assigned to them. Replace the #group-id and #user-id-\* placeholders with valid OMVS IDs.

- ```
ADDGROUP STCGROUP OMVS(GID(#group-id))
DATA('GROUP WITH OMVS SEGMENT FOR STARTED TASKS')
```
- ```
ADDUSER STCJMON DFLTGROUP(STCGROUP) NOPASSWORD NAME('RDZ - JES JOBMONITOR')
OMVS(UID(#user-id-jmon) HOME(/tmp) PROGRAM(/bin/sh) NOASSIZEMAX
NOTHREADSMAX)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
ADDUSER STCRSE DFLTGROUP(STCGROUP) NOPASSWORD NAME('RDZ - RSE DAEMON')
OMVS(UID(#user-id-rse) HOME(/tmp) PROGRAM(/bin/sh) ASSIZEMAX(2147483647)
NOTHREADSMAX)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
ADDUSER STCLOCK DFLTGROUP(STCGROUP) NOPASSWORD NAME('RDZ - LOCK DAEMON')
OMVS(UID(#user-id-lock) HOME(/tmp) PROGRAM(/bin/sh) NOASSIZEMAX)
NOTHREADSMAX)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
RDEFINE STARTED JMON.* DATA('RDZ - JES JOBMONITOR')
STDATA(USER(STCJMON) GROUP(STCGROUP) TRUSTED(NO))
```
-



```
RDEFINE STARTED RSED.* DATA('RDZ - RSE DAEMON')
STDATA(USER(STCRSE) GROUP(STCGROUP) TRUSTED(NO))
```

•

```
RDEFINE STARTED LOCKD.* DATA('RDZ - LOCK DAEMON')
STDATA(USER(STCLOCK) GROUP(STCGROUP) TRUSTED(NO))
```

•

```
SETROPTS RACLIST(STARTED) REFRESH
```

**Note:**

- Ensure that the started tasks user IDs are protected by specifying the NOPASSWORD keyword.
- Ensure that RSE server has a unique OMVS uid due to the z/OS UNIX related privileges granted to this uid.
- RSE daemon requires a large address space size (2GB) for proper operation. You should set this value in the ASSIZEMAX variable of the OMVS segment for user ID STCRSE. This to ensure that RSE daemon will get the required region size, regardless of changes to MAXASSIZE in SYS1.PARMLIB(BPXPRMxx).
- RSE also requires a large number of threads for proper operation. You can set the limit in the THREADSMAX variable of the OMVS segment for user ID STCRSE. This ensures that RSE will get the required thread limit, regardless of changes to MAXTHREADS or MAXTHREADTASKS in SYS1.PARMLIB(BPXPRMxx). Refer to "Tuning considerations" in the *Host Configuration Reference* (SC14-7290) to determine the correct value for the thread limit.
- User ID STCJMON is another good candidate for setting THREADSMAX in the OMVS segment, because JES Job Monitor uses a thread per client connection.

You might want to consider making the STCRSE user ID restricted. Users with the RESTRICTED attribute cannot access protected (MVS) resources they are not specifically authorized to access.

```
ALTUSER STCRSE RESTRICTED
```

To ensure that restricted users do not gain access to z/OS UNIX file system resources through the "other" permission bits, you must define the RESTRICTED.FILESYS.ACCESS profile in the UNIXPRIV class with UACC(NONE). Refer to *Security Server RACF Security Administrator's Guide* (SA22-7683) for more information about restricting user IDs.

**Attention:** If you use restricted user IDs, you must explicitly add the permission to access a resource with the TSO **PERMIT** or the z/OS UNIX **setfacl** commands. This includes resources where the Developer for System z documentation uses UACC (such as the \*\* profile in the PROGRAM class) or where it relies on common z/OS UNIX conventions (such as everyone having read and execute permission for Java libraries). Test this before activating it on a production system.

---

## Define JES command security

JES Job Monitor issues all JES operator commands requested by a user through an extended MCS (EMCS) console, whose name is controlled with the CONSOLE\_NAME directive, as documented in "FEJJCNFG, JES Job Monitor configuration file" on page 22.

The following sample RACF commands give Developer for System z users conditional access to a limited set of JES commands (Hold, Release, Cancel, and

Purge). Users only have execution permission if they issue the commands through JES Job monitor. Replace the #console placeholder with the actual console name.

- RDEFINE OPERCMDS MVS.MCSOPER.#console UACC(READ)  
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
- RDEFINE OPERCMDS JES%.\*\* UACC(NONE)
- PERMIT JES%.\*\* CLASS(OPERCMDS) ACCESS(UPDATE) WHEN(CONSOLE(JMON)) ID(\*)
- SETROPTS RACLIST(OPERCMDS) REFRESH

**Note:**

- Usage of the console is permitted if no MVS.MCSOPER.#console profile is defined
- The CONSOLE class must be active for WHEN(CONSOLE(JMON)) to work, but there is no actual profile check in the CONSOLE class for EMCS consoles.
- Do not replace JMON with the actual console name in the WHEN(CONSOLE(JMON)) clause. The JMON keyword represents the point-of-entry application, not the console name.

**Attention:** Defining JES commands with universal access NONE in your security software might impact other applications and operations. Test this before activating it on a production system.

Table 19 and Table 20 show the operator commands issued for JES2 and JES3, and the discrete security profiles that can be used to protect them.

*Table 19. JES2 Job Monitor operator commands*

| Action  | Command                               | OPERCMDS profile                                                                    | Required access |
|---------|---------------------------------------|-------------------------------------------------------------------------------------|-----------------|
| Hold    | \$Hx(jobid)<br>with x = {J, S or T}   | jesname.MODIFYHOLD.BAT<br>jesname.MODIFYHOLD.STC<br>jesname.MODIFYHOLD.TSU          | UPDATE          |
| Release | \$Ax(jobid)<br>with x = {J, S or T}   | jesname.MODIFYRELEASE.BAT<br>jesname.MODIFYRELEASE.STC<br>jesname.MODIFYRELEASE.TSU | UPDATE          |
| Cancel  | \$Cx(jobid)<br>with x = {J, S or T}   | jesname.CANCEL.BAT<br>jesname.CANCEL.STC<br>jesname.CANCEL.TSU                      | UPDATE          |
| Purge   | \$Cx(jobid),P<br>with x = {J, S or T} | jesname.CANCEL.BAT<br>jesname.CANCEL.STC<br>jesname.CANCEL.TSU                      | UPDATE          |

*Table 20. JES3 Job Monitor operator commands*

| Action  | Command      | OPERCMDS profile   | Required access |
|---------|--------------|--------------------|-----------------|
| Hold    | *F,J=jobid,H | jesname.MODIFY.JOB | UPDATE          |
| Release | *F,J=jobid,R | jesname.MODIFY.JOB | UPDATE          |
| Cancel  | *F,J=jobid,C | jesname.MODIFY.JOB | UPDATE          |
| Purge   | *F,J=jobid,C | jesname.MODIFY.JOB | UPDATE          |

**Note:**

- The Hold, Release, Cancel, and Purge JES operator commands, and the Show JCL command, can only be executed against spool files owned by the client user ID, unless LIMIT\_COMMANDS= with value LIMITED or NOLIMIT is specified in the JES Job Monitor configuration file. Refer to "Actions against jobs - target limitations" in the *Host Configuration Reference* (SC14-7290) for more information about this.
- Users can browse any spool file, unless LIMIT\_VIEW=USERID is defined in the JES Job Monitor configuration file. Refer to "Access to spool files" in *Host Configuration Reference* (SC14-7290) for more information about this.
- Without being authorized for these operator commands, users will still be able to submit jobs and read job output through JES Job Monitor, if they have sufficient authority to possible profiles that protect these resources (such as those in the JESINPUT, JESJOBS and JESSPOOL classes).

Assuming the identity of the JES Job Monitor server by creating a JMON console from a TSO session is prevented by your security software. Even though the console can be created, the point of entry is different (JES Job Monitor versus TSO). JES commands issued from this console will fail the security check, if your security is set up as documented in this publication and the user does not have authority to the JES commands through other means.

---

## Define RSE as a secure z/OS UNIX server

RSE requires UPDATE access to the BPX.SERVER profile to create/delete the security environment for the client's thread. If this profile is not defined, UID(0) is required for RSE.

- RDEFINE FACILITY BPX.SERVER UACC(NONE)
- PERMIT BPX.SERVER CLASS(FACILITY) ACCESS(UPDATE) ID(STCRSE)
- SETROPTS RACLIST(FACILITY) REFRESH

**Attention:** Defining the BPX.SERVER profile makes z/OS UNIX as a whole switch from UNIX level security to z/OS UNIX level security, which is more secure. This might impact other z/OS UNIX applications and operations. Test this before activating it on a production system. Refer to *UNIX System Services Planning* (GA22-7800) for more information about the different security levels.

---

## Define MVS program controlled libraries for RSE

Servers with authority to BPX.SERVER must run in a clean, program-controlled environment. This implies that all programs called by RSE must also be program controlled. For MVS load libraries, program control is managed by your security software.

RSE uses system (SYS1.LINKLIB), Language Environment's runtime (CEE.SCEERUN\*) and ISPF's TSO/ISPF Client Gateway (ISP.SISPLOAD) load library.

- RALTER PROGRAM \*\* UACC(READ) ADDMEM('SYS1.LINKLIB'//NOPADCHK)
- RALTER PROGRAM \*\* UACC(READ) ADDMEM('CEE.SCEERUN'//NOPADCHK)
- RALTER PROGRAM \*\* UACC(READ) ADDMEM('CEE.SCEERUN2'//NOPADCHK)
- RALTER PROGRAM \*\* UACC(READ) ADDMEM('ISP.SISPLOAD'//NOPADCHK)
- SETROPTS WHEN(PROGRAM) REFRESH

**Note:** Do not use the \*\* profile if you already have a \* profile in the PROGRAM class. It obscures and complicates the search path used by your security software. In this case, you must merge the existing \* and the new \*\* definitions. IBM recommends using the \*\* profile, as documented in *Security Server RACF Security Administrator's Guide* (SA22-7683).

The following additional (prerequisite) libraries must be made program controlled to support the use of optional services. This list does not include data sets that are specific to a product that Developer for System z interacts with, such as IBM Debug Tool.

- Alternate REXX runtime library (for SCLM Developer Toolkit)
  - REXX.\*.SEAGALT
- System load library (for SSL encryption)
  - SYS1.SIEALNKE
- File Manager listener load library (for File Manager integration)
  - FMN.SFMNMODA

**Note:** Libraries that are designed for LPA placement also require program control authorizations if they are accessed through LINKLIST or STEPLIB. This publication documents the usage of the following LPA libraries:

- ISPF (for TSO/ISPF Client Gateway)
  - ISP.SISPLPA
- REXX runtime library (for SCLM Developer Toolkit)
  - REXX.\*.SEAGLPA
- Developer for System z (for CARMA)
  - FEK.SFEKLPA

---

## Define application protection for RSE

During client logon, RSE daemon verifies that a user is allowed to use the application.

- ```
RDEFINE APPL FEKAPPL UACC(READ) DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
SETROPTS RACLIST(APPL) REFRESH
```

**Note:**

- As described in more detail in “Define PassTicket support for RSE,” RSE supports the usage of an application ID other than FEKAPPL. The APPL class definition must match the actual application ID used by RSE.
- The client connection request will succeed if the application ID is not defined in the APPL class.
- The client connection request will only fail if the application ID is defined and the user lacks READ access to the profile.

---

## Define PassTicket support for RSE

The client's password (or other means of identification, such as an X.509 certificate) is only used to verify his identity upon connection. Afterwards, PassTickets are used to maintain thread security.

PassTickets are system-generated passwords with a lifespan of about 10 minutes. The generated PassTickets are based upon a secret key. This key is a 64 bit number (16 hex characters). Replace in the sample RACF commands below the key16 placeholder with a user-supplied 16 character hex string (characters 0-9 and A-F).

- ```
RDEFINE PTKTDATA FEKAPPL UACC(NONE) SSIGNON(KEYMASKED(key16))
APPLDATA('NO REPLAY PROTECTION – DO NOT CHANGE')
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
RDEFINE PTKTDATA IRRPTAUTH.FEKAPPL.* UACC(NONE)
DATA('RATIONAL DEVELOPER FOR SYSTEM Z')
```
- ```
PERMIT IRRPTAUTH.FEKAPPL.* CLASS(PTKTDATA) ACCESS(UPDATE) ID(STCRSE)
```
- ```
SETROPTS RACLIST(PTKTDATA) REFRESH
```

RSE supports the usage of an application ID other than FEKAPPL. Uncomment and customize the "APPLID=FEKAPPL" option in `rsed.envvars` to activate this, as documented in “Defining extra Java startup parameters with `_RSE_JAVAOPTS`” on page 36. The PTKTDATA class definitions must match the actual application ID used by RSE.

You should not use OMVSAPPL as application ID, because it will open the secret key to most z/OS UNIX applications. You should also not use the default MVS application ID, which is MVS followed by the system's SMF ID, because this will open the secret key to most MVS applications (including user batch jobs).

**Note:**

- If the PTKTDATA class is already defined, verify that it is defined as a generic class before creating the profiles listed above. The support for generic characters in the PTKTDATA class is new since z/OS release 1.7, with the introduction of a Java interface to PassTickets.
- Substitute the wildcard (\*) in the IRRPTAUTH.FEKAPPL.\* definition with a valid user ID mask to limit the user IDs for which RSE can generate a PassTicket.
- Depending on your RACF settings, the user defining a profile might also be on the access list of the profile. It is advised that you remove this permission for the PTKTDATA profiles.
- JES Job Monitor and RSE must have the same application ID to allow JES Job Monitor to evaluate the PassTickets presented by RSE.
- If the system has a cryptographic product installed and available, you can encrypt the secured signon application key for added protection. In order to do so, use the KEYENCRYPTED keyword instead of KEYMASKED. Refer to *Security Server RACF Security Administrator's Guide* (SA22-7683) for more information about this.

**Attention:** The client connection request will fail if PassTickets are not set up correctly.

---

## Define z/OS UNIX program controlled files for RSE

Servers with authority to BPX.SERVER must run in a clean, program-controlled environment. This implies that all programs called by RSE must also be program controlled. For z/OS UNIX files, program control is managed by the **extattr** command. To execute this command, you need READ access to BPX.FILEATTR.PROGCTL in the FACILITY class, or be UID(0).

RSE server uses RACF's Java shared library (/usr/lib/libIRRRacf\*.so).

- `extattr +p /usr/lib/libIRRRacf*.so`

### Note:

- Since z/OS 1.9, /usr/lib/libIRRRacf\*.so is installed program controlled during SMP/E RACF install.
- Since z/OS 1.10, /usr/lib/libIRRRacf\*.so is part of SAF, which ships with base z/OS, so it is available also to non-RACF customers.
- The setup might be different if you use a security product other than RACF. Consult the documentation of your security product for more information.
- The SMP/E install of Developer for System z sets the program control bit for internal RSE programs.
- Use the `ls -Eog z/OS UNIX` command to display the current status of the program control bit (the file is program controlled if the letter **p** shows in the second string).

```
$ ls -Eog /usr/lib/libIRRRacf*.so
-rwxr-xr-x  aps-  2      69632 Oct  5  2007 /usr/lib/libIRRRacf.so
-rwxr-xr-x  aps-  2      69632 Oct  5  2007 /usr/lib/libIRRRacf64.so
```

---

## Verify security settings

Use the following sample commands to display the results of your security-related customizations.

- Security settings and classes
  - `SETOPTS LIST`
- OMVS segment for users
  - `LISTUSER #userid NORACF OMVS`
  - `LISTGRP #group-name NORACF OMVS`
- Data set profiles
  - `LISTGRP FEK`
  - `LISTDSD PREFIX(FEK) ALL`
- Started tasks
  - `LISTGRP STCGROUP OMVS`
  - `LISTUSER STCJMON OMVS`
  - `LISTUSER STCRSE OMVS`
  - `LISTUSER STCLOCK OMVS`
  - `RLIST STARTED JMON.* ALL STDATA`
  - `RLIST STARTED RSED.* ALL STDATA`
  - `RLIST STARTED LOCKD.* ALL STDATA`
- JES command security
  - `RLIST CONSOLE JMON ALL`
  - `RLIST OPERCMDS MVS.MCSOPER.JMON ALL`

- RLIST OPERCMDS JES%.\*\* ALL
- RSE as a secure z/OS UNIX server
  - RLIST FACILITY BPX.SERVER ALL
- MVS program controlled libraries for RSE
  - RLIST PROGRAM \*\* ALL
- Application protection for RSE
  - RLIST APPL FEKAPPL ALL
- PassTicket support for RSE
  - RLIST PTKTDATA FEKAPPL ALL SSIGNON
  - RLIST PTKTDATA IRRPTAUTH.FEKAPPL.\* ALL
- z/OS UNIX program controlled files for RSE
  - ls -E /usr/lib/libIRRracf\*.so





---

## Chapter 9. Migration guide

---

### Migration considerations

This section highlights installation and configuration changes compared to previous releases of the product. It also gives some general guidelines to migrate to this release. Refer to the related sections in this manual for more information.

- If you are a previous user of IBM Rational Developer for System z, IBM WebSphere Developer for System z, IBM WebSphere Developer for zSeries or IBM WebSphere® Studio Enterprise Developer, it is recommended that you save the related customized files BEFORE installing the upgrade to this version of IBM Rational Developer for System z Version 8.0.3.
- Read "Running multiple instances" in the *Host Configuration Reference* (SC14-7290) if you plan on running multiple instances of Developer for System z.

**Note:** The migration information listed here is for Developer for System z versions that are still supported at the time of publication.

### Backing up previously configured files

If you are a previous user of Developer for System z, it is recommended that you save the related customized files before installing this version of IBM Developer for System z.

Customizable Developer for system z files can be found at the following locations:

- Version 7.6
  - FEK.#CUST.RDZ\*.\*\*, Configuration Utility work files
  - FEK.SFEKSAMP, some members are copied to FEK.#CUST.\* by the FEKSETUP sample job, where \* equals PARMLIB, PROCLIB, JCL, CNTL, ASM and COBOL
  - FEK.SFEKSAMV
  - /usr/lpp/rdz/samples/, some files are copied to /etc/rdz/ and /var/rdz/sc1mdt/\* by the FEKSETUP sample job, where \* equals CONFIG/, CONFIG/PROJECT/ and CONFIG/script/
- Version 7.5
  - FEK.SFEKSAMP, some members are copied to FEK.#CUST.\* by the FEKSETUP sample job, where \* equals PARMLIB, PROCLIB, JCL, CNTL, ASM and COBOL
  - FEK.SFEKSAMV
  - /usr/lpp/rdz/samples/, some files are copied to /etc/rdz/ and /etc/rdz/sc1mdt/\* by the FEKSETUP sample job, where \* equals CONFIG/, CONFIG/PROJECT/ and CONFIG/script/
- Version 7.1
  - FEK.SFEKSAMP
  - CRA.SCRASAMP
  - /usr/lpp/wd4z/rse/lib/, customizable files are advised to be copied to /etc/wd4z/

Previous Developer for system z setups also document changes to configuration files owned by other products.

- Version 7.5 and 7.6

- SYS1.PARMLIB(ASCHPMxx)  
define an APPC transaction class for the TSO Commands service
- SYS1.PARMLIB(BPXPRMxx)  
set z/OS UNIX system defaults
- SYS1.PARMLIB(COMMNDxx)  
start servers at IPL time
- SYS1.PARMLIB(LPALSTxx)  
add FEK.SFEKLPA to LPA
- SYS1.PARMLIB(PROGxx)  
APF authorize FEK.SFEKAUTH  
add FEK.SFEKAUTH and FEK.SFEKLOAD to LINKLIST
- (APPC)  
define an APPC transaction for the TSO Commands service
- (WLM)  
associate an APPC transaction program with a TSO performance group
- (WLM)  
assign an application environment for a DB2 stored procedure
- Version 7.1
  - SYS1.PARMLIB(ASCHPMxx)  
define an APPC transaction class for the TSO Commands service
  - SYS1.PARMLIB(BPXPRMxx)  
set z/OS UNIX system defaults
  - SYS1.PARMLIB(PROGxx)  
APF authorize FEK.SFEKLOAD
  - /etc/services  
define the RSE daemon port
  - /etc/inetd.conf  
define the RSE daemon service
  - /etc/SCLMDT/COMFIG/ISPF.conf  
define the location of the TSO Commands server
  - (APPC)  
define an APPC transaction for the TSO Commands service
  - (WLM)  
associate an APPC transaction program with a TSO performance group
  - (WLM)  
assign an application environment for a DB2 stored procedure

---

## Version 8.0.x migration notes

The following migration notes are version 8.0.x-specific. They are valid for migration from IBM Rational Developer for System z version 8.0.1 and version 8.0.2 to version 8.0.3, and are additions to the existing version 8.0.1 migration notes.

- CARMA - The CRAMSG VSAM must be updated (since version 8.0.3).

- CARMA - The CRADEF and CRASTRS VSAM files for the CA Endevor® SCM RAM must be updated to use the new support for CA Endevor® SCM batch-actions (since version 8.0.3) and CA Endevor® SCM packages (since version 8.0.3).
- CARMA - New sample members have been added (since version 8.0.3):
  - CRABCFG - configuration file for CA Endevor® SCM batch-actions.
  - CRABATCA - sample job for CA Endevor® SCM batch-actions.
- CARMA - The following customizable members have changed (since version 8.0.3):
  - CRANDVRA
- CARMA - Additional DD statements are added for the CA Endevor® SCM RAM (since version 8.0.3):
  - CRABCFG
  - CRABSKEL
  - PKGSCLS (allocated by CRANDVRA)
- File Manager Integration is deprecated.
- Host Configuration Utility - Added migration option (since version 8.0.2)
- PROCLIB - The following PROCLIB members have changed (since version 8.0.3):
  - ELAXFUOP
- RSE - New operator commands have been added to the LOCKD started task (since version 8.0.2):
  - MODIFY DISPLAY TABLE
- RSE - New operator commands have been added to the RSED started task (since version 8.0.2 and 8.0.3):
  - MODIFY IVP ISPF,userid
  - MODIFY IVP PASSTICKET,userid
- RSE - RSED started task operator commands have been enhanced (since version 8.0.2):
  - MODIFY DISPLAY CLIENT [{,LOGON | ,ID | ,USER}]
- RSE - The following console messages are new (since version 8.0.3):
  - FEK910I
- RSE - New non-customizable directives have been added to rsed.envvars (since version 8.0.3):
  - (\_RSE\_JAVAOPTS) -Dldap.server.address
  - (\_RSE\_JAVAOPTS) -Dldap.server.port
  - (\_RSE\_JAVAOPTS) -Dldap.ptc.group.name.suffix
  - \_RSE\_PTC
- RSE - New optional directives have been added to rsed.envvars (since version 8.0.3):
  - (\_RSE\_JAVAOPTS) -Daudit.action
  - (\_RSE\_JAVAOPTS) -Daudit.action.id
  - (\_RSE\_JAVAOPTS) -DCPP\_CLEANUP\_INTERVAL
  - (\_RSE\_JAVAOPTS) -DDSTORE\_TCP\_NO\_DELAY
  - \_RSE\_FEK\_SAF\_CLASS
  - \_RSE\_LDAP\_SERVER
  - \_RSE\_LDAP\_PORT
  - \_RSE\_LDAP\_PTC\_GROUP\_SUFFIX

- RSE - Interpretation of the following optional directives in rsed.envvars has changed (since version 8.0.3):
  - (`_RSE_JAVAOPTS`) -Dprocess.cleanup.interval
- RSE - New optional directives have been added to pushtoclient.properties (since version 8.0.3):
  - accept.product.license
- RSE - Interpretation of the following optional directives in pushtoclient.properties has changed (since version 8.0.3):
  - config.enabled
  - product.enabled
  - reject.config.updates
  - reject.product.updates
- RSE - New z/OS UNIX samples have been added (since version 8.0.3):
  - process\_audit.rex
- New publication, *Rational Developer for System z Messages and Codes* (SC14-7497).

---

## Migrate from version 7.6 to version 8.0.1

These notes are for a migration from a base version 7.6 to version 8.0.1. It includes changes that are already documented as part of version 7.6 maintenance. The changes that are part of the maintenance stream (and thus possibly already implemented) are marked with the release where they were introduced.

### IBM Rational Developer for System z, FMID HHOP801

- The default SMP/E install location for MVS and z/OS UNIX components did not change and thus remain FEK.\* and /usr/lpp/rdz/\*.
- Application Deployment Manager - Existing ADN\* modules in the CICS RPL concatenation must be updated (since version 7.6.1).
- Application Deployment Manager - The following sample members have been updated to add URIMAP support in the Administrative utility (since version 7.6.1):
  - ADNJSPAU
  - ADNVCRD
- Application Deployment Manager - An existing CRD repository VSAM must be replaced to enable URIMAP support (since version 7.6.1).
- CARMA - Added support for an universal unique RAM ID stored in the CARMA definition VSAM data set, CRADEF (since version 7.6.1). An existing CRADEF VSAM must be replaced to use it.
- CARMA - Added support for a variable-length layout for the CARMA custom information VSAM data set, CRASTRS (since version 7.6.1). An existing CRASTRS VSAM must be replaced to use it.
- CARMA - New sample members have been added (since version 7.6.1):
  - CRA#VS2 - migrate CRASTRS to variable-length format.
- CARMA - Existing sample members have been renamed:
  - CRA#VCAD -> CRA\$VCAD
  - CRA#VCAS -> CRA\$VCAS
- CARMA - The CRADEF and CRASTRS VSAMs for the CA Endeavor® SCM RAM must be updated.

- CARMA - Additional DD statements are added for the CA Endevor® SCM RAM (since version 7.6.1):
  - EXT2ELM
  - SPCLLIST (allocated by CRANDVRA)
- CARMA – The following customizable members have changed (since version 8.0.1).
  - CRANDVRA
  - CRASHOW
- JES Job Monitor - Usage of `_CEE_ENVFILE_S` in the started task JCL (since version 7.6.0.1).
- JES Job Monitor - The following FEJJCNFG directives became optional (since version 7.6.1):
  - HOST\_CODEPAGE
- JES Job Monitor - New optional directives have been added to FEJJCNFG (since version 8.0.1):
  - SUBMIT\_TIMEOUT
- JES Job Monitor – The following customizable members have changed (since version 8.0.1):
  - FEJTSO
- PROCLIB - New PROCLIB members have been added (since version 7.6.1):
  - ELAXFDCL
- PROCLIB - The following PROCLIB members have changed (since version 8.0.1):
  - LOCKD
  - RSED
- RSE - Usage of 64-bit Java is now supported (since version 7.6.1).
- RSE - Assume permission is granted when the application ID is not defined in the APPL security class (since version 8.0.1).
- RSE - The RSED and LOCKD started tasks now support TMPDIR (since version 8.0.1).
- RSE - The RSED started task now reads the RSED port number from `rsed.envvars` (since version 8.0.1).
- RSE - The LOCKD started task now reads the log level from `rsecomm.properties` (since version 8.0.1).
- RSE - New operator commands have been added (since version 7.6.1 and 8.0.1):
  - MODIFY DISPLAY PROCESS,DETAIL
  - MODIFY IVP DAEMON,userid
- RSE - The following non-customizable directives have changed or are new in `rsed.envvars` (since version 8.0.1):
  - (`_RSE_JAVAOPTS`) -DDSTORE\_KEEPALIVE\_RESPONSE\_TIMEOUT
  - (`_RSE_JAVAOPTS`) -DDSTORE\_IO\_SOCKET\_READ\_TIMEOUT
  - (`_RSE_JAVAOPTS`) -Djob.monitor.port
  - CGI\_ISPCONF
  - CGI\_ISPWORK
  - `_EDC_ADD_ERRNO2`
- RSE - New optional directives have been added to `rsed.envvars` (since version 7.6.0.1 and 8.0.1):
  - (`_RSE_JAVAOPTS`) -Daudit.log.mode

- (\_RSE\_JAVAOPTS) -Ddeny.nozero.port
- (\_RSE\_JAVAOPTS) -Dsingle.logon
- (\_RSE\_JAVAOPTS) -Dprocess.cleanup.interval
- (\_RSE\_JAVAOPTS) -DDISABLE\_DELETE\_IN\_SUBPROJECT
- TMPDIR
- RSE - New required directives have been added to rsed.envvars (since version 8.0.1):
  - RSE\_RSED\_PORT
  - RSE\_JMON\_PORT
- RSE - The following configuration files are no longer used and should be removed from /etc/rdz (since version 8.0.1):
  - projectcfg.properties
  - propertiescfg.properties
  - uchars.settings
- RSE - The following configuration files are new (since version 8.0.1):
  - pushtoclient.properties
- RSE - The following directories have been renamed (since version 8.0.1):
  - /var/rdz/properties -> /var/rdz/pushtoclient
- RSE - The following directories have been moved (since version 8.0.1):
  - /var/rdz/projects -> /var/rdz/pushtoclient/projects
- RSE - The following console messages have changed or are new (since version 7.6.0.1, 7.6.1 and 8.0.1):
  - FEK001I
  - FEK012I
  - FEK210I
  - FEK900I
  - FEK901I
- RSE - documentation in the FEKSETUP job has exact details on what the job creates, and documents differences between Developer for System z versions (since version 8.0.1).
- RSE - FEKLOGS is enhanced to require less customization and collect more information (since version 8.0.1).

## Configurable files

Table 21 on page 141 gives an overview of files that are customized in version 8.0.1. Note that the Developer for System z sample libraries, FEK.SFEKSAMP, FEK.SFEKSAMV and /usr/lpp/rdz/samples/, come with more customizable members than listed here, such as sample CARMA source code and jobs to compile them.

The following members and files are no longer customizable or no longer used.

- CRA#CRAM (customization no longer required)
- CRAISPRX (deprecated)
- FEKAPPCC (deprecated)
- FEKAPPCL (deprecated)
- FEKAPPCX (deprecated)
- propertiescfg.properties (no longer used)
- projectcfg.properties (no longer used)

- uchars.settings (no longer customizable)

**Note:** Sample job FEKSETUP copies all listed members to different data sets and directories, default FEK.#CUST.\* and /etc/rdz/\*.

*Table 21. Version 8.0.1 customizations*

| Member/File | Default location                              | Purpose                                                                            | Migration notes                                                                |
|-------------|-----------------------------------------------|------------------------------------------------------------------------------------|--------------------------------------------------------------------------------|
| FEKSETUP    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]               | JCL to create data sets and directories, and populate them with customizable files | Updated to include new customizable members and create new directory structure |
| JMON        | FEK.SFEKSAMP(FEJJJCL)<br>[FEK.#CUST.PROCLIB]  | JCL for JES Job Monitor                                                            | usage of _CEE_ENVFILE_S                                                        |
| FEJJJCL     | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(JMON)]     | Shipping name for JMON member                                                      | See JMON member                                                                |
| RSED        | FEK.SFEKSAMP(FEKRSED)<br>[FEK.#CUST.PROCLIB]  | JCL for RSE daemon                                                                 | TMPDIR support                                                                 |
| FEKRSED     | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(RSED)]     | Shipping name for RSED member                                                      | See RSED member                                                                |
| LOCKD       | FEK.SFEKSAMP(FEKLOCKD)<br>[FEK.#CUST.PROCLIB] | JCL for lock daemon                                                                | TMPDIR support                                                                 |
| FEKLOCKD    | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(LOCKD)]    | Shipping name for LOCKD member                                                     | See LOCKD member                                                               |
| ELAXF*      | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB]           | JCL for remote project builds, and so on                                           | New member ELAXFDCL                                                            |
| FEKRACF     | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]               | JCL for security definitions                                                       | None                                                                           |
| FEJJCNFG    | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB]           | JES Job Monitor configuration file                                                 | Some directives became optional and new optional directives have been added    |
| FEJTSO      | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]              | JCL for TSO submits                                                                | Older copies must be replaced by this one (customizations must be redone)      |
| CRA\$VMSG   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]               | JCL to create the CARMA message VSAM                                               | None                                                                           |
| CRA\$VDEF   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]               | JCL to create the CARMA configuration VSAM                                         | None                                                                           |

Table 21. Version 8.0.1 customizations (continued)

| Member/File | Default location                    | Purpose                                                                  | Migration notes                |
|-------------|-------------------------------------|--------------------------------------------------------------------------|--------------------------------|
| CRA\$VSTR   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA custom information VSAM                          | None                           |
| CRA\$VCAD   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA configuration VSAM for CA Endeavor® SCM RAM      | Renamed, was CRA#VCAS          |
| CRA\$VCAS   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA custom information VSAM for CA Endeavor® SCM RAM | Renamed, was CRA#VCAS          |
| CRASUBMT    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]    | CARMA batch startup CLIST                                                | Minor changes                  |
| CRASUBCA    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]    | CARMA batch startup CLIST for CA Endeavor® SCM RAM                       | Additional DD statements added |
| CRASHOW     | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB] | CARMA configuration for CA Endeavor® SCM RAM                             | New filters are added          |
| CRATMAP     | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB] | CARMA configuration for CA Endeavor® SCM RAM                             | None                           |
| CRANDVRA    | FEK.SFEKPROC                        | CARMA allocation REXX for CA Endeavor® SCM RAM                           | Additional DD statements added |
| CRA#VSLM    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the SCLM RAM's message VSAM                                | None                           |
| CRA#ASLM    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the SCLM RAM's data sets                                   | None                           |
| CRA#VPDS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the PDS RAM's message VSAM                                 | None                           |
| CRA#UADD    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to merge RAM definitions                                             | None                           |
| CRA#UQRY    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to extract RAM definitions                                           | None                           |
| CRAXJCL     | FEK.SFEKSAMP<br>[FEK.#CUST.ASM]     | Sample source code for IRXJCL replacement                                | None                           |
| CRA#CIRX    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to compile CRAXJCL                                                   | None                           |
| ADNCSDRS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define the RESTful CRD server to primary CICS region              | Minor changes                  |
| ADNCSDTX    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define alternate transaction IDs to CICS region                   | None                           |



Table 21. Version 8.0.1 customizations (continued)

| Member/File       | Default location                     | Purpose                                                          | Migration notes                                                            |
|-------------------|--------------------------------------|------------------------------------------------------------------|----------------------------------------------------------------------------|
| ADNTXNC           | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to create alternate transaction IDs                          | None                                                                       |
| ADNMSGHC          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to compile ADNMSGHS                                          | None                                                                       |
| ADNMSGHS          | FEK.SFEKSAMP<br>[FEK.#CUST.COBOL]    | Sample source code for the Pipeline Message Handler              | None                                                                       |
| ADNVCRD           | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to create the CRD repository                                 | Added URIMAP support, customizations must be redone                        |
| ADNCSDWS          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to define the Web Service CRD server to primary CICS region  | None                                                                       |
| ADNCSDAR          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to define the CRD server to non-primary CICS regions         | Minor changes                                                              |
| ADNJSPAU          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to update the CRD defaults                                   | Added URIMAP support, customizations must be redone                        |
| ADNVMFST          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to create and define the Manifest repository                 | None                                                                       |
| ELAXMSAM          | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB]  | JCL procedure of the WLM address space                           | None                                                                       |
| ELAXMJCL          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to define the PL/I and COBOL Stored Procedure Builder to DB2 | Minor changes                                                              |
| FEKLOGS           | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to collect log files                                         | Added additional checks (customization must be redone)                     |
| rsed.envvars      | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE environment variables                                        | Older copies must be replaced by this one (customizations must be redone). |
| ISPF.conf         | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | TSO/ISPF Client Gateway configuration file                       | Minor changes                                                              |
| CRASRV.properties | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file                                         | None                                                                       |
| crastart.conf     | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file for CRASTART usage                      | Minor changes                                                              |

Table 21. Version 8.0.1 customizations (continued)

| Member/File             | Default location                     | Purpose                                                             | Migration notes                 |
|-------------------------|--------------------------------------|---------------------------------------------------------------------|---------------------------------|
| crastart.endevor.conf   | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file for CRASTART usage for CA Endevor® SCM RAM | Additional DD statements added  |
| ssl.properties          | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE SSL configuration file                                          | None                            |
| rsecomm.properties      | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE trace configuration file                                        | Some directives became optional |
| pushtoclient.properties | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | Push information to the client configuration file                   | NEW, customization is optional  |
| FMEXT.properties        | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | File Manager Integration configuration file                         | None                            |

## Sample migration scenarios

The metadata for host-based projects moved in version 8.0.1 from /var/rdz/projects to /var/rdz/pushtoclient/projects. There are multiple options to migrate the existing metadata.

1. Create a symbolic link that makes /var/rdz/pushtoclient/projects point to /var/rdz/projects, as shown in the following sample z/OS UNIX command:  
ln -s /var/rdz/projects /var/rdz/pushtoclient/projects
2. The Developer for System z Client administrator can change the default location for the host-based projects (/var/rdz/pushtoclient/projects) to the actual location (/var/rdz/projects) when exporting the push-to-client metadata.
3. copy the host-based projects metadata from /var/rdz/projects to /var/rdz/pushtoclient/projects, as shown in the following sample z/OS UNIX command:  
cp -pr /var/rdz/projects /var/rdz/pushtoclient/projects

See *UNIX System Services Command Reference* (SA22-7802) for more information about the sample z/OS UNIX commands.

## Migrate from version 7.5 to version 7.6

### IBM Rational Developer for System z, FMID HHOP760

- The default SMP/E install location for MVS and z/OS UNIX components did not change and thus remain FEK.\* and /usr/lpp/rdz/\*.
- Application Deployment Manager - Existing ADN\* modules in the CICS RPL concatenation must be updated.
- Application Deployment Manager - New load modules, which must be part of the CICS RPL concatenation, have been added to support the CICS RESTful interface.
  - ADNANAL
  - ADNCRD41
  - ADNREST

- Application Deployment Manager - New sample members have been added to support the CICS RESTful interface.
  - ADNCSDRS
  - ADNCSDTX
  - ADNTXNC
- Application Deployment Manager - Existing sample members are renamed.
  - ADNARCSD -> ADNCSDAR
  - ADNCMSGH -> ADNMSGHC
  - ADNMFEST -> ADNVMFST
  - ADNPCCSD -> ADNCSDWS
  - ADNSMSGH -> ADNMSGHS
  - ADNVSAM -> ADNVCRD
- A new, production type, RAM is provided to access CA Endeavor<sup>®</sup> SCM.
  - CRARNDVR
- CARMA - New sample members have been provided to support the CA Endeavor<sup>®</sup> SCM RAM.
  - FEK.#CUST.JCL(CRA#VCAD)
  - FEK.#CUST.JCL(CRA#VCAS)
  - FEK.#CUST.CNTL(CRASUBCA)
  - FEK.#CUST.PARMLIB(CRASHOW)
  - FEK.#CUST.PARMLIB(CRATMAP)
  - FEK.SFEKPROC(CRANDVRA)
  - /etc/rdz/crastart.endevor.conf
- CARMA - New sample members have been provided to support merging RAM definitions.
  - CRA#UADD
  - CRA#UQRY
- File Manager Integration - The batch interface to access File Manager is no longer supported.
- File Manager Integration - The FMEXT.properties configuration file has changed completely and must be replaced.
- JES Job Monitor - LE options are embedded in the FEJJMON load module (since version 7.5.0.1), which might require changes to your started task definition. See the FEK.SFEKSAMP(FEJJJCL) sample JCL for more details.
- JES Job Monitor - New optional directives have been added to FEJJCNGF (in version 7.5.0.1 and 7.5.1.0).
  - APPLID
  - CONSOLE\_NAME
  - GEN\_CONSOLE\_NAME
- JES Job Monitor - A new command, Show JCL, is supported (since version 7.5.1.0) which might require updates to your security software.
- Lock daemon – The lock daemon (LOCKD) is a new started task (since version 7.5.0.1). This started task can be queried to identify which Developer for z client is holding a data set lock. (System commands stop at address space level, which is the RSE thread pool.)
- SCLMDT - the default location for the SCLMDT project configuration files has changed.

- /var/rdz/sclmdt
- RSE - New operator commands have been added.
  - MODIFY RSESTANDARDLOG
- RSE - New required directives have been added to rsed.envvars (in version 7.5.0.1 and 7.6.0.0).
  - \_RSE\_LOCKD\_PORT
  - (\_RSE\_JAVAOPTS) -Dlock.daemon.port
  - (\_RSE\_JAVAOPTS) -Dlock.daemon.cleanup.interval
  - \_RSE\_LOCKD\_CLASS
  - \_RSE\_HOST\_CODEPAGE
  - (\_RSE\_JAVAOPTS) -Dfile.encoding
  - (\_RSE\_JAVAOPTS) -Dconsole.encoding
- RSE - New optional directives have been added to rsed.envvars (since version 7.5.0.1, 7.5.1.0 and 7.6.0.0).
  - (\_RSE\_JAVAOPTS) -Duser.log
  - (\_RSE\_JAVAOPTS) -Dkeep.last.log
  - (\_RSE\_JAVAOPTS) -Denable.standard.log
  - (\_RSE\_JAVAOPTS) -DDSTORE\_LOG\_DIRECTORY
  - (\_RSE\_JAVAOPTS) -DHIDE\_ZOS\_UNIX
  - (\_RSE\_JAVAOPTS) -Denable.certificate.mapping
  - GSK\_CRL\_SECURITY\_LEVEL
  - GSK\_LDAP\_SERVER
  - GSK\_LDAP\_PORT
  - GSK\_LDAP\_USER
  - GSK\_LDAP\_PASSWORD
- RSE - Some optional directives have changed in rsed.envvars.
  - (\_RSE\_JAVAOPTS) -Ddaemon.log
  - (\_RSE\_JAVAOPTS) -Xmx
  - SCLMDT\_CONF\_HOME
- RSE - New optional directives have been added to ssl.properties (since version 7.5.1.0 and 7.6.0.0).
  - server\_keystore\_label
  - server\_keystore\_type
- RSE - RSE daemon supports X.509 client certificate authentication (since version 7.5.1.0), which requires updates to your current certificate and security setup when used.
- RSE - Security has been tightened, failing connection requests upon PassTicket and FEKAPPL errors.
- RSE - The default location for all log files (daemon and user logs) has changed.
  - /var/rdz/logs
  - /var/rdz/logs/\$LOGNAME
- RSE - A new sample JCL has been provided to gather Developer for System z logs and configuration information.
  - FEKLOGS

## Configurable files

Table 22 gives an overview of files that are customized in version 7.6. Note that the Developer for System z sample libraries, FEK.SFEKSAMP, FEK.SFEKSAMV and /usr/lpp/rdz/samples/, come with more customizable members than listed here, such as sample CARMA source code and jobs to compile them.

**Note:** Sample job FEKSETUP copies all listed members to different data sets and directories, default FEK.#CUST.\* and /etc/rdz/.\*.

Table 22. Version 7.6 customizations

| Member/File | Default location                             | Purpose                                                                            | Migration notes                             |
|-------------|----------------------------------------------|------------------------------------------------------------------------------------|---------------------------------------------|
| FEKSETUP    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL to create data sets and directories, and populate them with customizable files | Updated to include new customizable members |
| JMON        | FEK.SFEKSAMP(FEJJJCL)<br>[FEK.#CUST.PROCLIB] | JCL for JES Job Monitor                                                            | Added option to change LE options           |
| FEJJJCL     | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(JMON)]    | Shipping name for JMON member                                                      | See JMON member                             |
| RSED        | FEK.SFEKSAMP(FEKRSED)<br>[FEK.#CUST.PROCLIB] | JCL for RSE daemon                                                                 | none                                        |
| FEKRSED     | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(RSED)]    | Shipping name for RSED member                                                      | See RSED member                             |
| LOCKD       | FEK.SFEKSAMP(FEKLCKD)<br>[FEK.#CUST.PROCLIB] | JCL for lock daemon                                                                | NEW, customization is required              |
| FEKLCKD     | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB(LOCKD)]   | Shipping name for LOCKD member                                                     | See LOCKD member                            |
| ELAXF*      | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB]          | JCL for remote project builds, and so forth                                        | none                                        |
| FEKRACF     | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL for security definitions                                                       | Minor updates                               |
| FEJJCNFG    | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB]          | JES Job Monitor configuration file                                                 | New optional directives have been added     |
| FEJTSO      | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]             | JCL for TSO submits                                                                | none                                        |
| CRA\$VMSG   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL to create the CARMA message VSAM                                               | none                                        |
| CRA\$VDEF   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL to create the CARMA configuration VSAM                                         | none                                        |

Table 22. Version 7.6 customizations (continued)

| Member/File | Default location                    | Purpose                                                                  | Migration notes                |
|-------------|-------------------------------------|--------------------------------------------------------------------------|--------------------------------|
| CRA\$VSTR   | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA custom information VSAM                          | none                           |
| CRASUBMT    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]    | CARMA batch startup CLIST                                                | none                           |
| CRASUBCA    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]    | CARMA batch startup CLIST for CA Endeavor® SCM RAM                       | NEW, customization is optional |
| CRASHOW     | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB] | CARMA configuration for CA Endeavor® SCM RAM                             | NEW, customization is optional |
| CRATMAP     | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB] | CARMA configuration for CA Endeavor® SCM RAM                             | NEW, customization is optional |
| CRANDVRA    | FEK.SFEKPROC                        | CARMA allocation REXX for CA Endeavor® SCM RAM                           | NEW, customization is optional |
| CRAISPRX    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]    | Sample DD allocation exec for CARMA using TSO/ISPF Client Gateway        | none                           |
| CRA#VSLM    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the SCLM RAM's message VSAM                                | none                           |
| CRA#ASLM    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the SCLM RAM's data sets                                   | none                           |
| CRA#VPDS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the PDS RAM's message VSAM                                 | none                           |
| CRA#CRAM    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to compile the skeleton RAM                                          | none                           |
| CRA#VCAD    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA configuration VSAM for CA Endeavor® SCM RAM      | NEW, customization is optional |
| CRA#VCAS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CARMA custom information VSAM for CA Endeavor® SCM RAM | NEW, customization is optional |
| CRA#UADD    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to merge RAM definitions                                             | NEW, customization is optional |
| CRA#UQRY    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to extract RAM definitions                                           | NEW, customization is optional |
| CRAXJCL     | FEK.SFEKSAMP<br>[FEK.#CUST.ASM]     | Sample source code for IRXJCL replacement                                | none                           |

Table 22. Version 7.6 customizations (continued)

| Member/File | Default location                    | Purpose                                                                                | Migration notes                                                              |
|-------------|-------------------------------------|----------------------------------------------------------------------------------------|------------------------------------------------------------------------------|
| CRA#CIRX    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to compile CRAXJCL                                                                 | none                                                                         |
| ADNCSDRS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define the RESTful CRD server to primary CICS region                            | NEW, customization is optional                                               |
| ADNCSDTX    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define alternate transaction IDs to CICS region                                 | NEW, customization is optional                                               |
| ADNTXNC     | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create alternate transaction IDs                                                | NEW, customization is optional                                               |
| ADNMSGHC    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to compile ADNMSGHS                                                                | Renamed, was ADNCMSGH                                                        |
| ADNMSGHS    | FEK.SFEKSAMP<br>[FEK.#CUST.COBOL]   | Sample source code for the Pipeline Message Handler                                    | Renamed, was ADNSMSGH                                                        |
| ADNVCRD     | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create the CRD repository                                                       | Renamed, was ADNVSAM                                                         |
| ADNCSDWS    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define the Web Service CRD server to primary CICS region                        | Renamed, was ADNPCCSD                                                        |
| ADNCSDAR    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define the CRD server to non-primary CICS regions                               | Renamed, was ADNARCSD                                                        |
| ADNJSPAU    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to update the CRD defaults                                                         | Definitions for the RESTful service are added, customizations must be redone |
| ADNVMFST    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create and define the Manifest repository                                       | Renamed, was ADNMFEST                                                        |
| ELAXMSAM    | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB] | JCL procedure of the WLM address space for the PL/I and COBOL Stored Procedure Builder | none                                                                         |
| ELAXMJCL    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to define the PL/I and COBOL Stored Procedure Builder to DB2                       | none                                                                         |
| FEKAPPCC    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to create an APPC transaction                                                      | none                                                                         |
| FEKAPPCL    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]     | JCL to display an APPC transaction                                                     | none                                                                         |

Table 22. Version 7.6 customizations (continued)

| Member/File              | Default location                     | Purpose                                                             | Migration notes                                                            |
|--------------------------|--------------------------------------|---------------------------------------------------------------------|----------------------------------------------------------------------------|
| FEKAPPCX                 | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to delete an APPC transaction                                   | none                                                                       |
| FEKLOGS                  | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to collect log files                                            | NEW, customization is optional                                             |
| rsed.envvars             | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE environment variables                                           | Older copies must be replaced by this one (customizations must be redone). |
| ISPF.conf                | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | TSO/ISPF Client Gateway configuration file                          | ISP.SISPLIB added to SYSPROC for SCLMDT                                    |
| CRASRV.properties        | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file                                            | none                                                                       |
| crastart.conf            | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file for CRASTART usage                         | none                                                                       |
| crastart.endevor.conf    | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file for CRASTART usage for CA Endevor® SCM RAM | NEW, customization is optional                                             |
| ssl.properties           | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE SSL configuration file                                          | New optional directives have been added                                    |
| rsecomm.properties       | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE trace configuration file                                        | none                                                                       |
| propertiescfg.properties | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | Host-based property groups configuration file                       | none                                                                       |
| projectcfg.properties    | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | Host-based projects configuration file                              | none                                                                       |
| FMIEXT.properties        | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | File Manager Integration configuration file                         | Older copies must be replaced by this one (customizations must be redone). |
| uchars.settings          | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | Uneditable characters configuration file                            | none                                                                       |



---

## Migrate from version 7.1 to version 7.5

### IBM Rational Developer for System z, FMID HHOP750

- The default SMP/E install location for MVS components did not change and thus remains FEK.\*.
- The default SMP/E install location for z/OS UNIX components changed to /usr/lpp/rdz/.\*.
- Common Access Repository Manager (CARMA) has merged into Developer for System z Version 7.5, disabling the need to install it as a separate product.
- SCLM Developer Toolkit has merged into Developer for System z Version 7.5, disabling the need to install it as a separate product.
- In version 7.5 ISPF's TSO/ISPF Client Gateway service replaces the SCLM Developer Toolkit function used in version 7.1 to connect to the TSO Commands service. The APPC connection method is still supported.
- In version 7.5, RSE server is no longer an INETD managed process but a started task. RSE server now also uses a single server model whereas with previous versions, each client-host connection had a private RSE server.
- All modules requiring APF authorization (JES Job Monitor and SCLM Developer Toolkit) moved to FEK.SFEKAUTH in version 7.5, requiring an update to the existing APF definitions.
- JES Job Monitor load module moved to FEK.SFEKAUTH in version 7.5, requiring an update to the existing started task procedure.
- CARMA load modules moved to new libraries, requiring an update to the existing CRASUBMT server startup script.
- SCLM Developer Toolkit load modules moved to new libraries, requiring and update to the existing LINKLIST definitions.
- ELAXFTS0 is a new sample build procedure since version 7.1.1, ELAXFCP1 and ELAXFPP1 are new in version 7.5.
- uchars.settings is a new configuration file for uneditable characters.
- propertiescfg.properties is a new configuration file for default property groups.
- FEJJCNFG, CRASRV.properties and FMIEXT.properties have new optional directives.
- rsed.envvars has changed in version 7.5 and must be replaced.
- The sample ISPF.conf file shipped with version 7.5 is similar to the one used by SCLM Developer Toolkit in version 7.1.
- Some of the existing Application Deployment manager customizations must be redone.
- Application Deployment Manager has new functions which require customization.
- The security settings for RSE server changed drastically in version 7.5.
- The MVS.MCSOPER.JMON security profile is new for JES Job monitor in version 7.5.
- The CARMA startup script changed name and moved to a new location, requiring an update to the existing CRASRV.properties configuration file.
- The FMI startup script changed name and moved to a new location, requiring an update to the existing FMIEXT.properties configuration file.
- A new load module has been added for bidirectional support, requiring an update to the existing CICS DFHRPL concatenation if you are not using the FEK.SFEKLOAD library.

- Changes to the MAXPROCUSER parameter of SYS1.PARMLIB(BPXPRMxx) are now also documented.

## Configurable files

Table 23 gives an overview of files that are customized in version 7.5. Note that the Developer for System z sample libraries, FEK.SFEKSAMP, FEK.SFEKSAMV and /usr/lpp/rdz/samples/, come with more customizable members than listed here, such as sample CARMA source code and jobs to compile them.

**Note:** Sample job FEKSETUP copies all listed members to different data sets and directories, default FEK.#CUST.\* and /etc/rdz/\*.

Table 23. Version 7.5 customizations

| Member/File | Default location                             | Purpose                                                                            | Migration notes                                                                                                                        |
|-------------|----------------------------------------------|------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| FEKSETUP    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL to create data sets and directories, and populate them with customizable files | NEW, customization is required                                                                                                         |
| JMON        | FEK.SFEKSAMP(FEJJJCL)<br>[FEK.#CUST.PROCLIB] | JCL for JES Job Monitor                                                            | STEPLIB changed to SFEKAUTH                                                                                                            |
| RSED        | FEK.SFEKSAMP(FEKRSED)<br>[FEK.#CUST.PROCLIB] | JCL for RSE daemon                                                                 | NEW, customization is required                                                                                                         |
| ELAXF*      | FEK.SFEKSAMP<br>[FEK.#CUST.PROCLIB]          | JCL for remote project builds, and so on                                           | ELAXFTSO, ELAXFCP1 and ELAXFPP1 are new                                                                                                |
| FEKRACF     | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL for security definitions                                                       | NEW, required                                                                                                                          |
| FEJJCNGF    | FEK.SFEKSAMP<br>[FEK.#CUST.PARMLIB]          | JES Job Monitor configuration file                                                 | <ul style="list-style-type: none"> <li>• Some directives became optional</li> <li>• New optional directives have been added</li> </ul> |
| FEJTSO      | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]             | JCL for TSO submits                                                                | Job name can now be a variable                                                                                                         |
| CRAISPRX    | FEK.SFEKSAMP<br>[FEK.#CUST.CNTL]             | Sample DD allocation exec for CARMA using TSO/ISPF Client Gateway                  | NEW, customization is optional                                                                                                         |
| CRAXJCL     | FEK.SFEKSAMP<br>[FEK.#CUST.ASM]              | Sample source code for IRXJCL replacement                                          | NEW, customization is optional                                                                                                         |
| CRA#CIRX    | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]              | JCL to compile CRAXJCL                                                             | NEW, customization is optional                                                                                                         |
| ADNSMSGH    | FEK.SFEKSAMP<br>[FEK.#CUST.COBOL]            | Sample source code for the Pipeline Message Handler                                | Older copies must be replaced by this one (customizations must be redone)                                                              |

Table 23. Version 7.5 customizations (continued)

| Member/File       | Default location                     | Purpose                                             | Migration notes                                                                                                                             |
|-------------------|--------------------------------------|-----------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| ADNPCCSD          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to define the CRD server to primary CICS region | Older copies must be replaced by this one (customizations must be redone)                                                                   |
| ADNJSPAU          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to update the CRD defaults                      | NEW, customization is optional                                                                                                              |
| ADNMFEST          | FEK.SFEKSAMP<br>[FEK.#CUST.JCL]      | JCL to create and define the Manifest repository    | NEW, customization is optional                                                                                                              |
| rsed.envvars      | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | RSE environment variables                           | Older copies must be replaced by this one (customizations must be redone)                                                                   |
| ISPF.conf         | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | TSO/ISPF Client Gateway configuration file          | Identical to the ISPF.conf shipped with SCLMDT in v7.1                                                                                      |
| CRASRV.properties | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file                            | <ul style="list-style-type: none"> <li>Startup script changed location and name</li> <li>New optional directives have been added</li> </ul> |
| crastart.conf     | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | CARMA configuration file for CRASTART usage         | NEW, customization is optional                                                                                                              |
| FMEXT.properties  | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | File Manager Integration configuration file         | <ul style="list-style-type: none"> <li>Startup script changed location and name</li> <li>New optional directives have been added</li> </ul> |
| uchars.settings   | /usr/lpp/rdz/samples/<br>[/etc/rdz/] | Uneditable characters configuration file            | NEW, customization is optional                                                                                                              |



---

## Chapter 10. Operator commands

This appendix summarizes the operator (or console) commands information in *Rational Developer for System z Host Configuration Guide* (SC23-7658). Refer to that publication for more details.

---

### Start (S)

Use the **START** command to dynamically start a started task (STC). The abbreviated version of the command is the letter S.

#### JES Job Monitor

```
>> START procname ><
  S
    FEK
    , HLQ= install_hlq
    FEK.#CUST.PARMLIB (FEJJCNFG)
    , CFG= config_member
    , PRM=-TV
  <
```

Figure 35. START JMON operator command

##### procname

The name of the member in a procedure library that is used to start the server. The default name used during the host configuration is JMON.

##### HLQ=install\_hlq

High-level qualifier used to install Developer for System z. The default is FEK.

##### CFG=config\_member

Absolute data set and member name of the JES Job Monitor configuration file. The default is FEK.#CUST.PARMLIB (FEJJCNFG).

##### PRM=-TV

Enable verbose (trace) mode. Tracing will cause performance degradations and should only be done under the direction of the IBM support center.

#### RSE daemon

```
>> START procname ><
  S
    4035
    , PORT= port
    , HOME= '/usr/lpp/rdz'
    , CNFG= '/etc/rdz'
    , TMPDIR= '/tmp'
    , IVP= IVP
  <
```

Figure 36. START RSED operator command

The name of the member in a procedure library that is used to start the server. The default name used during the host configuration is RSED.

```
TMPDIR='temporary_file_path'
```

Absolute location for temporary z/OS UNIX files. If not specified, then /tmp is used. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes (') to preserve lower case characters.

## PORT=port

The port used by the RSE daemon for the clients to connect. If not specified, then the port defined in `/etc/rdz/rsed.envvars` is used (variable `_RSE_RSSED_PORT`). The default is 4035.

IVP=IVP

Do not start the server but run the RSE daemon installation verification program (IVP).

CNFG='config\_path'

Absolute location of the configuration files stored in z/OS UNIX. The default is '/etc/rdz'. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes ('') to preserve lower case characters.

## HOME='install\_path'

Path prefix and the mandatory /usr/lpp/rdz used to install Developer for System z. The default is '/usr/lpp/rdz'. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes (') to preserve lower case characters.

## Lock daemon




Figure 37. *START LOCKD* operator command

**procname**

The name of the member in a procedure library that is used to start the server. The default name used during the host configuration is LOCKD.

```
TMPDIR='temporary_file_path'
```

Absolute location for temporary z/OS UNIX files. If not specified, then /tmp is used. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes (') to preserve lower case characters.

## LOG=log\_level

The detail level of output in DD STDOUT.

- 0 : Log error messages only.
- 1 : Log error and warning messages (default).
- 2 : Log error, warning and informational messages.

**CNFG='config\_path'**

Absolute location of the configuration files stored in z/OS UNIX. The default is '/etc/rdz'. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes (') to preserve lower case characters.

**HOME='install\_path'**

Path prefix and the mandatory /usr/lpp/rdz used to install Developer for System z. The default is '/usr/lpp/rdz'. Note that the z/OS UNIX path is case sensitive and that it must be enclosed in single quotes (') to preserve lower case characters.

---

## Modify (F)

The **MODIFY** command allows you to dynamically query and change the characteristics of an active task. The abbreviated version of the command is the letter F.

## JES Job Monitor

```
>> [MODIFY] [F] [procname] [, APPL=-TV] [, APPL=-TN] <<
```

Figure 38. *MODIFY JMON operator command*

### procname

The name of the member in a procedure library that was used to start the server. The default name used during the host configuration is JMON.

- TV** Enable verbose (trace) mode. Tracing will cause performance degradations and should only be done under the direction of the IBM support center.
- TN** Disable verbose (trace) mode.

## RSE daemon




Figure 39. MODIFY RSED operator command

### procname

The name of the member in a procedure library that was used to start the server. The default name used during the host configuration is RSED.

### DISPLAY CLIENT [{LOGON | ,ID | ,USER}]

Display the active clients in a single BPXM023I message. The result layout depends on which command option was used. You can change the sorting order with the optional command arguments.

- No command option: Clients are grouped by the thread pool process that serves them.



```

| ProcessId(<processid>) ASId(<asid>) JobName(<jobname>)
| Clients(<local>/<total>) Order(<startup order>)
| <clientid><userid><connected since>
|
| • LOGON command option: Clients are ordered by logon time.
| LOGON TIME----- ID----- USERID--
| <connected since> <clientid> <userid>
|
| • ID command option: Clients are ordered by client ID.
| ID----- USERID-- LOGON TIME-----
| <clientid> <userid> <connected since>
|
| • USER command option: Clients are ordered by user ID.
| USERID-- ID----- LOGON TIME-----
| <userid> <clientid> <connected since>

```

## DISPLAY PROCESS[,{CLEANUP | ,DETAIL}]

Display the RSE thread pool processes in a single BPXM023I message. There can be multiple processes, which are used for load balancing the connected users.

```

ProcessId(<processid>) Memory Usage(<java heap usage>%)
Clients(<number of clients>) Order(<startup order>) <error status>

```

### Note:

- <processid> can be used in process specific z/OS UNIX operator commands.
- Each process has its own Java heap, whose size can be set in `rsed.envvars`.
- <startup order> is a sequential number that indicates the order that the thread pools were started. The number corresponds to the number used in the filename of the `stderr.*.log` and `stdout.*.log` files.

In normal situations, <error status> is blank. Table 24 documents the possible non-blank values for <error status>.

Table 24. Thread pool error status

| Status           | Description                                                                                                                                                                                                                                                                                                 |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| *severe error*   | The thread pool process encountered an unrecoverable error and halted operations. The other status fields show the last known values. Use the CLEANUP option of the <b>DISPLAY PROCESS</b> modify command to remove this entry from the table.                                                              |
| *killed process* | The thread pool process was killed by Java, z/OS UNIX or an operator command. The other status fields show the last known values. Use the CLEANUP option of the <b>DISPLAY PROCESS</b> modify command to remove this entry from the table.                                                                  |
| *timeout*        | The thread pool process did not respond in a timely manner to RSE daemon during a client connect request. The other status fields show the current values. The thread pool is excluded for future client connect requests. The *timeout* status is reset when a client served by this thread pool logs off. |

More information is provided when the DETAIL option of the **DISPLAY PROCESS** modify command is used:

```

ProcessId(33555087) ASId(002E) JobName(RSED8) Order(1)
PROCESS LIMITS:      CURRENT  HIGHWATER    LIMIT
JAVA HEAP USAGE(%)   10       56           100
CLIENTS              0        25           60
MAXFILEPROC          83       103          64000
MAXPROCUSER          97        99           200
MAXTHREADS           9        14          1500
MAXTHREADTASKS       9        14          1500

```

The ASId field is the address space ID, in hexadecimal notation. The process limits table shows the current resource usage, the high-water mark for the resource usage, and the resource limit. Note that due to other limiting factors, the defined limit might never be reached.

#### **CANCEL ID=clientid**

Cancel a client connection based upon the client ID, which is shown in the **DISPLAY CLIENT** modify command.

#### **CANCEL USER=userid**

Cancel a client connection based upon the client's user ID, which is shown in the **DISPLAY CLIENT** modify command.

#### **RSECOMMLOG {ON | OFF | I | W | E | 2 | 1 | 0}**

Control the trace detail level for RSE server (rsecomm.log) and the MVS data set services (lock.log and ffs\*.log). The startup default is defined in rsecomm.properties. There are three detail levels available:

|               |                                                                                |
|---------------|--------------------------------------------------------------------------------|
| E or 0 or OFF | Error messages only.                                                           |
| W or 1        | Error and Warning messages. This is the default setting in rsecomm.properties. |
| I or 2 or ON  | Error, Warning and Informational messages.                                     |

Detailed tracing will cause performance degradations and should only be done under the direction of the IBM support center.

#### **RSEDAEMONLOG {ON | OFF | I | E | 2 | 0}**

Control the trace detail level for RSE daemon (rsedaemon.log). The startup default is defined in rsecomm.properties. There are two detail levels available:

|               |                                             |
|---------------|---------------------------------------------|
| E or 0 or OFF | Error messages only.                        |
| I or 2 or ON  | Error, Warning, and Informational messages. |

Detailed tracing will cause performance degradations and should only be done under the direction of the IBM support center.

#### **RSESERVERLOG {ON | OFF | I | E | 2 | 0}**

Control the trace detail level for RSE thread pools (rserver.log). The startup default is defined in rsecomm.properties. There are two detail levels available:

|               |                                             |
|---------------|---------------------------------------------|
| E or 0 or OFF | Error messages only.                        |
| I or 2 or ON  | Error, Warning, and Informational messages. |

Detailed tracing will cause performance degradations and should only be done under the direction of the IBM support center.

## RSESTANDARDLOG {ON |, OFF}

Disable (OFF) or enable (ON) updating the log files holding the stdout and stderr streams of the thread pools (stdout.\*.log and stderr.\*.log). The startup default is defined by the enable.standard.log directive in rsed.envvars.

Detailed tracing will cause performance degradations and should only be done under the direction of the IBM support center.

## IVP DAEMON,userid

Log user ID userid on to RSE daemon to do a connection test. Results are shown with one ore more FEK900I console messages. The return code is shown with console message FEK901I.

```
+FEK900I DAEMON IVP: SSL is disabled
+FEK900I DAEMON IVP: connected
+FEK900I DAEMON IVP: 1977
+FEK900I DAEMON IVP: 6902918
+FEK900I DAEMON IVP: Success
+FEK901I DAEMON IVP Exit code = 0
```

### Note:

- The function is similar to what the fekfivpd IVP (Installation Verification Program) does.
- RSE daemon will generate a PassTicket which is used as password for the IVP, so there will be no WTOR (Write To Operator with Reply) requesting a password.

## IVP ISPF,userid

Invoke ISPF's Client Gateway as user ID userid. Results are shown with one ore more FEK900I console messages. The return code is shown with console message FEK901I.

```
+FEK900I ISPF IVP: executed on CDFMVS08 -- Tue Sep 13 22:29:28 EDT 2011
+FEK900I ISPF IVP: executed by uid=1(IBMUSER) gid=0(SYS1)
+FEK900I ISPF IVP: using /etc/rdz/rsed.envvars
+FEK900I ISPF IVP: current address space size limit is 2147483647
(2048.0 MB)
+FEK900I ISPF IVP: maximum address space size limit is 2147483647
(2048.0 MB)
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: /etc/rdz/ISPF.conf content:
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: ispllib=ISP.SISPLOAD
+FEK900I ISPF IVP: isplib=ISP.SISPMENU
+FEK900I ISPF IVP: isptlib=ISP.SISPTEU
+FEK900I ISPF IVP: ispplib=ISP.SISPPENU
+FEK900I ISPF IVP: ispslib=ISP.SISPSLIB
+FEK900I ISPF IVP: sysproc=ISP.SISPCLIB,FEK.SFEKPROC
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: Host install verification for RSE
+FEK900I ISPF IVP: Review IVP log messages from HOST below :
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: Service level 22Feb2011
+FEK900I ISPF IVP: RSE connection and base TS0/ISPF session initializati
on check only
+FEK900I ISPF IVP: *** CHECK : ENVIRONMENT VARIABLES - key variables
displayed below :
+FEK900I ISPF IVP: Server PATH          = ./usr/lpp/java/J5.0/bin:/usr/l
pp/rdz/bin:/usr/lpp/ispf/bin:/bin:/usr/sbin
+FEK900I ISPF IVP: STEPLIB              = NONE
```

```

+FEK900I ISPF IVP: Temporary directory = /tmp
+FEK900I ISPF IVP: _CMDSERV_BASE_HOME = /usr/lpp/ispf
+FEK900I ISPF IVP: _CMDSERV_CONF_HOME = /etc/rdz
+FEK900I ISPF IVP: _CMDSERV_WORK_HOME = /var/rdz
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: *** CHECK : USS MODULES
+FEK900I ISPF IVP: Checking ISPF Directory : /usr/lpp/ispf
+FEK900I ISPF IVP: Checking modules in /usr/lpp/ispf/bin directory
+FEK900I ISPF IVP: Checking for ISPF configuration file ISPF.conf
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: *** CHECK : TSO/ISPF INITIALIZATION
+FEK900I ISPF IVP: ( TSO/ISPF session will be initialized )
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: *** CHECK: Shutting down TSO/ISPF IVP session
+FEK900I ISPF IVP: RC=0
+FEK900I ISPF IVP: MSG: SUCCESSFUL
+FEK900I ISPF IVP: -----
-----
+FEK900I ISPF IVP: Host installation verification completed successfully
+FEK900I ISPF IVP: -----
-----
+FEK901I ISPF IVP Exit code = 0

```

**Note:**

- The function is similar to what the fekfivpi IVP (Installation Verification Program) does.
- RSE daemon will generate a PassTicket which is used as password for the IVP, so there will be no WTOR (Write To Operator with Reply) requesting a password.

**IVP PASSTICKET,userid**

Test the reusability of a PassTicket generated for user ID userid. Results are shown with one or more FEK900I console messages. The return code is shown with console message FEK901I.

```

+FEK900I PASSTICKET IVP: the default applid=FEKAPPL
+FEK900I PASSTICKET IVP: Success, PassTicket IVP finished normally
+FEK901I PASSTICKET IVP Exit code = 0

```

**Note:**

- When using RACF as security product, reusable PassTickets require the "NO REPLAY PROTECTION" keyword in the security definitions.
- There is no equivalent IVP (Installation Verification Program) for this test. Starting RSE daemon with the IVP=IVP argument will invoke a PassTicket IVP that tests PassTicket generation, but it cannot test PassTicket reusability.
- RSE daemon will generate a PassTicket which is used as password for the IVP, so there will be no WTOR (Write To Operator with Reply) requesting a password.

**SWITCH**

Switch to a new audit log file.

1



## 1

1

11

11

---

## Console messages

### JES Job Monitor

JES Job Monitor does not have product-specific console messages. The server relies on z/OS and JES to generate console messages for actions done by Developer for System z clients.

### RSE daemon, RSE thread pool server, and lock daemon

Table 25 lists the product-specific console messages generated by RSE daemon, RSE thread pool server, and the lock daemon.

*Table 25. RSE console messages*

| Message ID | Message text                                                    |
|------------|-----------------------------------------------------------------|
| FEK001I    | RseDaemon being initialized in {0} bit mode                     |
| FEK002I    | RseDaemon started. (port={0})                                   |
| FEK003I    | Stop command being processed                                    |
| FEK004I    | RseDaemon: Max Heap Size={0}MB and private AS Size={1}MB        |
| FEK005I    | Server process started. (processId={0})                         |
| FEK009I    | RseDaemon is waiting for the server process to start.           |
| FEK010I    | (rsed.envvars location = {0})                                   |
| FEK011I    | (log directory = {0})                                           |
| FEK012I    | (RSE home directory = {0})                                      |
| FEK100E    | Daemon port/timeout value must be digits                        |
| FEK101E    | JRE {0} or higher required                                      |
| FEK102E    | Invalid arguments received: {0}                                 |
| FEK103E    | Almost Disk-Full in {0}                                         |
| FEK104E    | Maximum number of processes has been reached                    |
| FEK105E    | Error in sending audit data (rc={0})                            |
| FEK110E    | socket() failed. reason=({0})                                   |
| FEK111E    | setsockopt() failed. reason=({0})                               |
| FEK112E    | bind() failed. reason=({0})                                     |
| FEK113E    | listen() failed. reason=({0})                                   |
| FEK114E    | accept() failed. reason=({0})                                   |
| FEK115E    | write() failed. reason=({0})                                    |
| FEK116E    | pipe() failed. reason=({0})                                     |
| FEK117E    | socketpair() failed. reason=({0})                               |
| FEK118E    | select() failed. reason=({0})                                   |
| FEK119E    | _console() failed. reason=({0})                                 |
| FEK130E    | gsk_environment_open() failed. reason=({0})                     |
| FEK131E    | gsk_attribute_set_enum(GSK_PROTOCOL_SSLV2) failed. reason=({0}) |
| FEK132E    | gsk_attribute_set_enum(GSK_PROTOCOL_SSLV3) failed. reason=({0}) |
| FEK133E    | gsk_attribute_set_enum(GSK_PROTOCOL_TLSV1) failed. reason=({0}) |
| FEK134E    | gsk_attribute_set_buffer(GSK_KEYRING_FILE) failed. reason=({0}) |
| FEK135E    | gsk_attribute_set_buffer(GSK_KEYRING_PW) failed. reason=({0})   |

Table 25. RSE console messages (continued)

| Message ID | Message text                                                         |
|------------|----------------------------------------------------------------------|
| FEK136E    | gsk_environment_init() failed. reason=({0})                          |
| FEK137E    | gsk_secure_socket_open() failed. reason=({0})                        |
| FEK138E    | gsk_attribute_set_numeric_value(GSK_FD) failed. reason=({0})         |
| FEK139E    | gsk_attribute_set_buffer(GSK_KEYRING_LABEL) failed. reason=({0})     |
| FEK140E    | gsk_attribute_set_enum(GSK_SESSION_TYPE) failed. reason=({0})        |
| FEK141E    | gsk_attribute_set_callback(GSK_IO_CALLBACK) failed. reason=({0})     |
| FEK142E    | gsk_secure_socket_init() failed. reason=({0})                        |
| FEK143E    | gsk_attribute_set_enum(GSK_CLIENT_AUTH_TYPE) failed.<br>reason=({0}) |
| FEK144E    | gsk_get_cert_info failed. reason=({0})                               |
| FEK145E    | gsk_secure_socket_read() failed. reason=({0})                        |
| FEK146E    | gsk_secure_socket_write() failed. reason=({0})                       |
| FEK150E    | RseDaemon abnormally terminated; {0}                                 |
| FEK201I    | {0} Command has been processed                                       |
| FEK202E    | Invalid Command Entered                                              |
| FEK203E    | Invalid Display Command: Display Process Client                      |
| FEK204E    | Invalid Cancel Command: Cancel ID= User=                             |
| FEK205E    | Command was not processed owing to consecutive SWITCHs               |
| FEK206E    | Audit Log facility is not active                                     |
| FEK207I    | No Client to be displayed                                            |
| FEK208I    | {0} canceled                                                         |
| FEK209I    | No Process to be displayed                                           |
| FEK210I    | {0} canceled owing to duplicate logon                                |
| FEK501I    | Lock daemon started, port={0}, cleanup interval={1}, log level={2}   |
| FEK502I    | Lock daemon terminating                                              |
| FEK510E    | Lock daemon, missing port                                            |
| FEK511E    | Lock daemon, wrong port, port={0}                                    |
| FEK512E    | Lock daemon, socket error, port={0}                                  |
| FEK513W    | Lock daemon, registration failed, ASID={0}, TCB={1}, USER={2}        |
| FEK514W    | Lock daemon, wrong log level, log level={0}                          |
| FEK900I    | {0} IVP: {1}                                                         |
| FEK901I    | {0} IVP Exit code = {1}                                              |
| FEK910I    | {0} EXIT : {1}                                                       |
| BPXM023I   | (stclock) dataset[(member)] NOT LOCKED                               |
| BPXM023I   | (stclock) dataset[(member)] LOCKED BY userid                         |
| BPXM023I   | (stclock) command, WRONG COMMAND                                     |
| BPXM023I   | (stclock) command, MISSING ARGUMENT                                  |
| BPXM023I   | (stclock) argument, WRONG ARGUMENT                                   |

---

## How to read a syntax diagram

The syntax diagram shows you how to specify a command so that the operating system can correctly interpret what you type. Read the syntax diagram from left to right and from top to bottom, following the horizontal line (the main path).




### Symbols

The following symbols are used in syntax diagrams:

| Symbol | Description                                                              |
|--------|--------------------------------------------------------------------------|
| >>     | Marks the beginning of the syntax diagram.                               |
| >      | Indicates that the syntax diagram is continued.                          |
|        | Marks the beginning and end of a fragment or part of the syntax diagram. |
| ><     | Marks the end of the syntax diagram.                                     |

### Operands

The following types of operands are used in syntax diagrams:

- Required operands are displayed on the main path line:  

- Optional operands are displayed below the main path line:  

- Default operands are displayed above the main path line:  


Operands are classified as keywords or variables:

- Keywords are constants that must be provided. If the keyword appears in the syntax diagram in both uppercase and lowercase, the uppercase portion is the abbreviation for the keyword (for example, KEYword). Keywords are not case-sensitive. You can code them in uppercase or lowercase.
- Variables are italicized, appear in lowercase letters, and represent names or values you supply. For example, a data set name is a variable. Variables can be case sensitive.

### Syntax example

In the following example, the USER command is a keyword. The required variable parameter is *user\_id*, and the optional variable parameter is *password*. Replace the variable parameters with your own values:

```
>>—USER—user_id—[password]—><
```

### Nonalphanumeric characters and blank spaces


If a diagram shows a character that is not alphanumeric (such as parentheses, periods, commas, equal signs, and blank spaces), you must code the character as part of the syntax. In this example, you must code OPERAND=(001 0.001):

```
>>—OPERAND=—(—001— 0.001—)—><
```




## Selecting more than one operand

An arrow returning to the left in a group of operands means that more than one can be selected, or that a single one can be repeated:



## Longer than one line

If a diagram is longer than one line, the first line ends with a single arrowhead and the second line begins with a single arrowhead:



## Syntax fragments

Some diagrams might contain syntax fragments, which serve to break up diagrams that are too long, too complex, or too repetitious. Syntax fragment names are in mixed case and are shown in the diagram and in the heading of the fragment. The fragment is placed below the main diagram:



Syntax fragment:





---

## Appendix. Host Configuration Reference

This section summarizes the information in *Rational Developer for System z Host Configuration Reference* (SC14-7290). Refer to that publication for more details.

---

### Understanding Developer for System z

The Developer for System z host consists of several components that interact to give the client access to the host services and data. Understanding the design of these components can help you make the correct configuration decisions.

---

### Security considerations

Developer for System z provides mainframe access to users on a non-mainframe workstation. Validating connection requests, providing secure communication between the host and the workstation, and authorizing and auditing activity are therefore important aspects of the product configuration.

---

### TCP/IP considerations

Developer for System z uses TCP/IP to provide mainframe access to users on a non-mainframe workstation. It also uses TCP/IP for communication between various components and other products.

---

### WLM considerations

Unlike traditional z/OS applications, Developer for System z is not a monolithic application that can be identified easily to Workload Manager (WLM). Developer for System z consists of several components that interact to give the client access to the host services and data. Some of these services are active in different address spaces, resulting in different WLM classifications.

---

### Tuning considerations

RSE (Remote Systems Explorer) is the core of Developer for System z. To manage the connections and workloads from the clients, RSE is composed of a daemon address space, which controls thread pooling address spaces. The daemon acts as a focal point for connection and management purposes, while the thread pools process the client workloads.

This makes RSE a prime target for tuning the Developer for System z setup. However, maintaining hundreds of users, each using 16 or more threads, a certain amount of storage, and possibly one or more address spaces requires proper configuration of both Developer for System z and z/OS.

---

### Performance considerations

z/OS is a highly customizable operating system, and (sometimes small) system changes can have a huge impact on the overall performance. This chapter highlights some of the changes that can be made to improve the performance of Developer for System z.

---

## Push-to-client considerations

Push-to-client, or host-based client control, supports central management of the following:

- Client configuration files
- Client product version
- Project definitions

---

## CICSTS considerations

This chapter contains information useful for a CICS Transaction Server administrator.

---

## Customizing the TSO environment

This chapter assists you with mimicking a TSO logon procedure by adding DD statements and data sets to the TSO environment in Developer for System z.

---

## Running multiple instances

There are times that you want multiple instances of Developer for System z active on the same system, for example, when testing an upgrade. However, some resources such as TCP/IP ports cannot be shared, so the defaults are not always applicable. Use the information in this chapter to plan the coexistence of the different instances of Developer for System z, after which you can use this configuration guide to customize them.

---

## Troubleshooting configuration problems

This chapter is provided to assist you with some common problems that you might encounter during your configuration of Developer for System z, and has the following sections:

- Log and setup analysis using FEKLOGS
- Log files
- Dump files
- Tracing
- z/OS UNIX permission bits
- Reserved TCP/IP ports
- Address Space size
- APPC transaction and TSO Commands service
- Miscellaneous information

---

## Setting up SSL and X.509 authentication

This appendix is provided to assist you with some common problems that you might encounter when setting up Secure Socket Layer (SSL), or during checking or modifying an existing setup. This appendix also provides a sample setup to support users authenticating themselves with an X.509 certificate.

---

## Setting up TCP/IP

This appendix is provided to assist you with some common problems that you might encounter when setting up TCP/IP, or during checking or modifying an existing setup.



---

# Bibliography

---

## Referenced publications

The following publications are referenced in this document:

*Table 26. Referenced publications*

| Publication title                                                                  | Order number | Reference              | Reference Web site                                                                                                                                                                  |
|------------------------------------------------------------------------------------|--------------|------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Program Directory for IBM Rational Developer for System z                          | GI11-8298    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Prerequisites                                      | SC23-7659    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Host Configuration Quick Start                     | GI11-9201    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Host Configuration Guide                           | SC23-7658    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Host Configuration Reference                       | SC14-7290    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Host Configuration Utility Guide                   | SC14-7282    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Messages and Codes                                 | SC14-7497    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Common Access Repository Manager Developer's Guide | SC23-7660    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Prerequisites                                      | SC23-7659    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Rational Developer for System z Host Configuration Quick Start                     | GI11-9201    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| SCLM Developer Toolkit Administrator's Guide                                       | SC23-9801    | Developer for System z | <a href="http://www.ibm.com/software/rational/products/developer/systemz/library/index.html">http://www.ibm.com/software/rational/products/developer/systemz/library/index.html</a> |
| Using APPC to provide TSO command services                                         | SC14-7291    | White paper            | <a href="http://www-306.ibm.com/software/awdtools/rdz/library/">http://www-306.ibm.com/software/awdtools/rdz/library/</a>                                                           |
| Using ISPF Client Gateway to provide CARMA services                                | SC14-7292    | White paper            | <a href="http://www-306.ibm.com/software/awdtools/rdz/library/">http://www-306.ibm.com/software/awdtools/rdz/library/</a>                                                           |
| Communications Server IP Configuration Guide                                       | SC31-8775    | z/OS 1.11              | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a>                                                   |
| Communications Server IP Configuration Reference                                   | SC31-8776    | z/OS 1.11              | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a>                                                   |
| Communications Server IP Diagnosis Guide                                           | GC31-8782    | z/OS 1.11              | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a>                                                   |

Table 26. Referenced publications (continued)

| Publication title                                        | Order number | Reference | Reference Web site                                                                                                                |
|----------------------------------------------------------|--------------|-----------|-----------------------------------------------------------------------------------------------------------------------------------|
| Communications Server IP System Administrator's Commands | SC31-8781    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Communications Server SNA Network Implementation Guide   | SC31-8777    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Communications Server SNA Operations                     | SC31-8779    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Cryptographic Services System SSL Programming            | SC24-5901    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| DFSMS Macro Instructions for Data Sets                   | SC26-7408    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| DFSMS Using data sets                                    | SC26-7410    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Language Environment Customization                       | SA22-7564    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Language Environment Debugging Guide                     | GA22-7560    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS Initialization and Tuning Guide                      | SA22-7591    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS Initialization and Tuning Reference                  | SA22-7592    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS JCL Reference                                        | SA22-7597    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS Planning APPC/MVS Management                         | SA22-7599    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS Planning Workload Management                         | SA22-7602    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| MVS System Commands                                      | SA22-7627    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Security Server RACF Command Language Reference          | SA22-7687    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| Security Server RACF Security Administrator's Guide      | SA22-7683    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| TSO/E Customization                                      | SA22-7783    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| TSO/E REXX Reference                                     | SA22-7790    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| UNIX System Services Command Reference                   | SA22-7802    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| UNIX System Services Planning                            | GA22-7800    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |
| UNIX System Services User's Guide                        | SA22-7801    | z/OS 1.11 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a> |



Table 26. Referenced publications (continued)

| Publication title                           | Order number | Reference                 | Reference Web site                                                                                                                                                                                                                                                |
|---------------------------------------------|--------------|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Using REXX and z/OS UNIX System Services    | SA22-7806    | z/OS 1.11                 | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a>                                                                                                                                 |
| Java™ Diagnostic Guide                      | SC34-6650    | Java 5.0                  | <a href="http://www.ibm.com/developerworks/java/jdk/diagnosis/">http://www.ibm.com/developerworks/java/jdk/diagnosis/</a>                                                                                                                                         |
| Java SDK and Runtime Environment User Guide | /            | Java 5.0                  | <a href="http://www-03.ibm.com/servers/eserver/zseries/software/java/">http://www-03.ibm.com/servers/eserver/zseries/software/java/</a>                                                                                                                           |
| Resource Definition Guide                   | SC34-6430    | CICSTS 3.1                | <a href="http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html">http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html</a>                                                                                                                       |
| Resource Definition Guide                   | SC34-6815    | CICSTS 3.2                | <a href="http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html">http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html</a>                                                                                                                       |
| Resource Definition Guide                   | SC34-7000    | CICSTS 4.1                | <a href="https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html">https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html</a> |
| Resource Definition Guide                   | SC34-7181    | CICSTS 4.2                | <a href="https://publib.boulder.ibm.com/infocenter/cicsts/v4r2/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html">https://publib.boulder.ibm.com/infocenter/cicsts/v4r2/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html</a> |
| RACF Security Guide                         | SC34-6454    | CICSTS 3.1                | <a href="http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html">http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html</a>                                                                                                                       |
| RACF Security Guide                         | SC34-6835    | CICSTS 3.2                | <a href="http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html">http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html</a>                                                                                                                       |
| RACF Security Guide                         | SC34-7003    | CICSTS 4.1                | <a href="https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html">https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html</a> |
| RACF Security Guide                         | SC34-7179    | CICSTS 4.2                | <a href="https://publib.boulder.ibm.com/infocenter/cicsts/v4r2/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html">https://publib.boulder.ibm.com/infocenter/cicsts/v4r2/index.jsp?topic=/com.ibm.cics.ts.home.doc/library/library_html.html</a> |
| Language Reference                          | SC27-1408    | Enterprise COBOL for z/OS | <a href="http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html">http://www-03.ibm.com/systems/z/os/zos/bkserv/zapplsbooks.html</a>                                                                                                                       |

The following Web sites are referenced in this document:

Table 27. Referenced Web sites

| Description                                | Reference Web site                                                                                                                                                                              |
|--------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Developer for System z Information Center  | <a href="http://publib.boulder.ibm.com/infocenter/ratdevz/v8r0/index.jsp">http://publib.boulder.ibm.com/infocenter/ratdevz/v8r0/index.jsp</a>                                                   |
| Developer for System z Support             | <a href="http://www-306.ibm.com/software/awdtools/rdz/support/">http://www-306.ibm.com/software/awdtools/rdz/support/</a>                                                                       |
| Developer for System z Library             | <a href="http://www-306.ibm.com/software/awdtools/rdz/library/">http://www-306.ibm.com/software/awdtools/rdz/library/</a>                                                                       |
| Developer for System z home page           | <a href="http://www-306.ibm.com/software/awdtools/rdz/">http://www-306.ibm.com/software/awdtools/rdz/</a>                                                                                       |
| Developer for System z Recommended service | <a href="http://www-01.ibm.com/support/docview.wss?rs=2294&amp;context=SS2QJ2&amp;uid=swg27006335">http://www-01.ibm.com/support/docview.wss?rs=2294&amp;context=SS2QJ2&amp;uid=swg27006335</a> |
| Developer for System z enhancement request | <a href="https://www.ibm.com/developerworks/support/rational/rfe/">https://www.ibm.com/developerworks/support/rational/rfe/</a>                                                                 |
| z/OS internet library                      | <a href="http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/">http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/</a>                                                               |
| CICSTS Information Center                  | <a href="https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp">https://publib.boulder.ibm.com/infocenter/cicsts/v4r1/index.jsp</a>                                                   |
| IBM Tivoli® Directory Server               | <a href="http://www-01.ibm.com/software/tivoli/products/directory-server/">http://www-01.ibm.com/software/tivoli/products/directory-server/</a>                                                 |

Table 27. Referenced Web sites (continued)

| Description                          | Reference Web site                                                                                                                                |
|--------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| Problem Determination Tools Plug-ins | <a href="http://www-01.ibm.com/software/awdtools/deployment/pdtplugins/">http://www-01.ibm.com/software/awdtools/deployment/pdtplugins/</a>       |
| Download Apache Ant                  | <a href="http://ant.apache.org/">http://ant.apache.org/</a>                                                                                       |
| Java keytool documentation           | <a href="http://java.sun.com/j2se/1.5.0/docs/tooldocs/solaris/keytool.html">http://java.sun.com/j2se/1.5.0/docs/tooldocs/solaris/keytool.html</a> |
| CA support home page                 | <a href="https://support.ca.com/">https://support.ca.com/</a>                                                                                     |

## Informational publications

The following publications can be helpful in understanding setup issues for requisite host components:

Table 28. Informational publications

| Publication title                                                              | Order number | Reference | Reference Web site                                                      |
|--------------------------------------------------------------------------------|--------------|-----------|-------------------------------------------------------------------------|
| ABCs of z/OS System Programming Volume 9 (z/OS UNIX)                           | SG24-6989    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |
| System Programmer's Guide to: Workload Manager                                 | SG24-6472    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |
| TCPIP Implementation Volume 1: Base Functions, Connectivity, and Routing       | SG24-7532    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |
| TCPIP Implementation Volume 3: High Availability, Scalability, and Performance | SG24-7534    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |
| TCP/IP Implementation Volume 4: Security and Policy-Based Networking           | SG24-7535    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |
| Tivoli Directory Server for z/OS                                               | SG24-7849    | Redbook   | <a href="http://www.redbooks.ibm.com/">http://www.redbooks.ibm.com/</a> |

---

## Glossary

### Action ID

A numeric identifier for an action between 0 and 999

### Application Server

1. A program that handles all application operations between browser-based computers and an organization's back-end business applications or databases. There is a special class of Java-based appservers that conform to the J2EE standard. J2EE code can be easily ported between these appservers. They can support JSPs and servlets for dynamic Web content and EJBs for transactions and database access.
2. The target of a request from a remote application. In the DB2 environment, the application server function is provided by the distributed data facility and is used to access DB2 data from remote applications.
3. A server program in a distributed network that provides the execution environment for an application program.
4. The target of a request from an application requester. The database management system (DBMS) at the application server site provides the requested data.
5. Software that handles communication with the client requesting an asset and queries of the Content Manager.

### Bidirectional (bi-di)

Pertaining to scripts such as Arabic and Hebrew that generally run from right to left, except for numbers, which run from left to right. This definition is from the Localization Industry Standards Association (LISA) Glossary.

### Bidirectional Attribute

Text type, text orientation, numeric swapping, and symmetric swapping.

### Build Request

A request from the client to perform a build transaction.

### Build Transaction

A job started on MVS to perform builds after a build request has been received from the client.

### Compile

1. In Integrated Language Environment (ILE) languages, to translate source statements into modules that then can be bound into programs or service programs.
2. To translate all or part of a program expressed in a high-level language into a computer program expressed in an intermediate language, an assembly language, or a machine language.

### Container

1. In CoOperative Development Environment/400, a system object that contains and organizes source files. An i5/OS<sup>®</sup> library or an MVS-partitioned data set are examples of a container.
2. In J2EE, an entity that provides life-cycle management, security, deployment, and runtime services to components. (Sun) Each type of container (EJB, Web, JSP, servlet, applet, and application client) also provides component-specific services
3. In Backup Recovery and Media Services, the physical object used to store and move media such as a box, a case, or a rack.
4. In a virtual tape server (VTS), a receptacle in which one or more exported logical volumes (LVOLs) can be stored. A stacked volume containing one or more LVOLs and residing outside a VTS library is considered to be the container for those volumes.
5. A physical storage location of the data. For example, a file, directory, or device.

6. A column or row that is used to arrange the layout of a portlet or other container on a page.
7. An element of the user interface that holds objects. In the folder manager, an object that can contain other folders or documents.

### **Database**

A collection of interrelated or independent data items that are stored together to serve one or more applications.

### **Data Definition View**

Contains a local representation of databases and their objects and provides features to manipulate these objects and export them to a remote database

### **Data Set**

The major unit of data storage and retrieval, consisting of a collection of data in one of several prescribed arrangements and described by control information to which the system has access.

### **Debug**

To detect, diagnose, and eliminate errors in programs.

### **Debugging Session**

The debugging activities that occur between the time that a developer starts a debugger and the time that the developer exits from it.

### **Error Buffer**

A portion of storage used to hold error output information temporarily.

### **Gateway**

1. A middleware component that bridges Internet and intranet environments during Web service invocations.
2. Software that provides services between the endpoints and the rest of the Tivoli environment.

3. A component of a Voice over Internet Protocol that provides a bridge between VoIP and circuit-switched environments.
4. A device or program used to connect networks or systems with different network architectures. The systems might have different characteristics, such as different communication protocols, different network architecture, or different security policies, in which case the gateway performs a translation role as well as a connection role.

### **Interactive System Productivity Facility (ISPF)**

An IBM licensed program that serves as a full-screen editor and dialog manager. Used for writing application programs, it provides a means of generating standard screen panels and interactive dialogs between the application programmer and terminal user. ISPF consists of four major components: DM, PDF, SCLM, and C/S. The DM component is the Dialog Manager, which provides services to dialogs and end-users. The PDF component is the Program Development Facility, which provides services to assist the dialog or application developer. The SCLM component is the Software Configuration Library Manager, which provides services to application developers to manage their application development libraries. The C/S component is the Client/Server, which allows you to run ISPF on programmable workstation, to display the panels using the display function of your workstation operating system, and to integrate workstation tools and data with host tools and data.

### **Interpreter**

A program that translates and runs each instruction of a high-level programming language before it translates and runs the next instruction.

### **Isomorphic**

Each composed element (in other words, an element containing other elements) of the XML instance document starting from

the root has one and only one corresponding COBOL group item whose nesting depth is identical to the nesting depth of its XML equivalent. Each non-composed element (in other words, an element that does not contain other elements) in the XML instance document starting from the top has one and only one corresponding COBOL elementary item whose nesting depth is identical to the nesting level of its XML equivalent and whose memory address at runtime can be uniquely identified.

**Linkage Section**

The section in the data division of an activated unit (a called program or an invoked method) that describes data items available from the activating unit (a program or a method). These data items can be referred to by both the activated unit and the activating unit.

**Load Library**

A library containing load modules.

**Lock Action**

Locks a member.

**Navigator View**

Provides a hierarchical view of the resources in the Workbench.

**Non-Isomorphic**

A simple mapping of COBOL items and XML elements belonging to XML documents and COBOL groups that are not identical in shape (non-isomorphic). Non-isomorphic mapping can also be created between non-isomorphic elements of isomorphic structures.

**Output Console View**

Displays the output of a process and allows you to provide keyboard input to a process.

**Output View**

Displays messages, parameters, and results that are related to the objects that you work with

**Perspective**

A group of views that show various aspects of the resources in the workbench. The workbench user can switch perspectives, depending on the task at hand, and customize the layout of views and editors within the perspective.

**RAM** Repository Access Manager

**Remote File System**

A file system residing on a separate server or operating system.

**Remote System**

Any other system in the network with which your system can communicate.

**Remote Systems Perspective**

Provides an interface for managing remote systems using conventions that are similar to ISPF.

**Repository**

1. A storage area for data. Every repository has a name and an associated business item type. By default, the name will be the same as the name of the business item. For example, a repository for invoices will be called Invoices. There are two types of information repositories: local (specific to the process) and global (reusable).
2. A VSAM data set on which the states of BTS processes are stored. When a process is not executing under the control of BTS, its state (and the states of its constituent activities) are preserved by being written to a repository data set. The states of all processes of a particular process-type (and of their activity instances) are

stored on the same repository data set. Records for multiple process-types can be written to the same repository.

3. A persistent storage area for source code and other application resources. In a team programming environment, a shared repository enables multiuser access to application resources.
4. A collection of information about the queue managers that are members of a cluster. This information includes queue manager names, their locations, their channels, what queues they host, and so on.

**Repository Instance**

A project or component that exists in an SCM.

**Repositories View**

Displays the CVS repository locations that have been added to your Workbench.

**Response File**

1. A file that contains a set of predefined answers to questions asked by a program and that is used instead of entering those values one at a time.
2. An ASCII file that can be customized with the setup and configuration data that automates an installation. The setup and configuration data would have to be entered during an interactive install, but with a response file, the installation can proceed without any intervention.

**Servers View**

Displays a list of all your servers and the configurations that are associated with them.

**Shell** A software interface between users and the operating system that interprets commands and user interactions and communicates them to the operating system. A computer might have several layers of shells for various levels of user interaction.

**Shell Name**

The name of the shell interface.

**Shell Script**

A file containing commands that can be interpreted by the shell. The user types the name of the script file at the shell

command prompt to make the shell execute the script commands.

**Siddeck**

A library that publishes the functions of a DLL program. The entry names and module names are stored in the library after the source code is compiled.

**Silent Installation**

An installation that does not send messages to the console but instead stores messages and errors in log files. Also, a silent installation can use response files for data input.

**Silent Uninstallation**

An uninstallation process that does not send messages to the console but instead stores messages and errors in log files after the uninstall command has been invoked.

**Task List**

A list of procedures that can be executed by a single flow of control.

**URL** Uniform Resource Locator

---

## Documentation notices for IBM Rational Developer for System Z

© Copyright IBM Corporation - 2000, 2011

U.S. Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan, Ltd.  
1623-14, Shimotsuruma, Yamato-shi  
Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.



Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Intellectual Property Dept. for Rational Software  
IBM Corporation  
3039 Cornwallis Road, PO Box 12195  
Research Triangle Park, NC 27709  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.



---

## Copyright license

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

---

## Trademark acknowledgments

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

CA Endeavor is a registered trademark of CA Technologies.

Rational are trademarks of International Business Machines Corporation and Rational Software Corporation, in the United States, other countries, or both.

Intel and Pentium are trademarks of Intel Corporation in the United States, or other countries, or both.

Microsoft, Windows, and the Windows logo are trademarks or registered trademarks of Microsoft Corporation in the United States, or other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.



---

# Index

## Special characters

\_RSE\_CMDSERV\_OPTS, Defining extra  
Java startup parameters with 41  
\_RSE\_JAVAOPTS, Defining extra Java  
startup parameters with 36  
/tmp, Remove old files from 80

## A

access requirements 6  
Activating Common Access Repository  
Manager 45  
active RAM, select 46  
ADM, customization 81  
admin, SCLMDT 79  
ADNCS DAR, RESTful non-primary and  
web service non-primary 83  
ADNCS DRS, RESTful primary 83  
ADNCS DTX, RESTful change ID 84  
ADNCS DWS, web service primary 85  
ADNJSPAU, CICS administrative  
utility 82  
ADNMSGHC, pipeline message  
handler 85  
ADNMSGHS, pipeline message  
handler 85  
ADNTXNC, RESTful change ID 84  
ADNVCRD, CRD repository 82  
ADNVMFST, manifest repository 86  
Ant, Install and customize 78  
APF authorization  
FEK.SFEKAUTH 122  
APPC usage considerations 89  
Application Deployment Manager,  
customization 81  
application protection for RSE,  
Define 130  
applications supported 1  
ASSIZEMAX 127  
availability, Port 111

## B

backing up configured files  
Version 7.1 135  
Version 7.5 135  
basic customization 11  
batch actions, SCM RAM 66  
batch submit with CA Endeavor® SCM  
RAM 51  
batch submit, sample RAMs 54  
Bidirectional language support 100  
blank spaces, syntax diagram 166  
BPXPRMxx  
MAXASSIZE 127  
BPXPRMxx, set limits in  
MAXASSIZE 12  
MAXPROCUSER 12  
MAXTHREADS 12  
MAXTHREADTASKS 12

## C

CA Endeavor® SCM RAM 47  
CA Endeavor® SCM RAM allocation  
exec 65  
CA Endeavor® SCM RAM configuration  
files  
CRASHOW 65  
CRATMAP 65  
CA Endeavor® SCM RAM customization,  
additional 49  
CA Endeavor® SCM RAM, batch  
submit 51  
CARMA VSAM data sets, creating 48,  
50, 52  
CARMA, activating 45  
CARMA, RSE interface to 56  
changes, DB2 98  
changes, PROCLIB 97  
changes, Workload Manager 97  
characters, Nonalphanumeric in syntax  
diagram 166  
checklist, client 9  
checklist, Client 9  
checklist, requirements 11  
checklist, SCLM administrator 79  
CICS administrative utility 82  
CICS Bidirectional language support 100  
CICS non-primary connection region 86  
CICS non-primary connection  
regions 83  
CICS primary connection region 83, 85  
Client checklist 9  
client control, host-based 89  
Client Gateway configuration file,  
TSO/ISPF 42  
command security, Define JES 127  
commands, JES Job Monitor Modify 157  
commands, JES Job Monitor Start 155  
commands, Lock daemon Modify 163  
commands, Lock daemon Start 156  
commands, RSE daemon Modify 158  
commands, RSE daemon Start 155  
commands, Start (S) 155  
commands, Stop (P) 163  
COMMNDxx, add started tasks 13  
Common Access Repository Manager,  
Activating 45  
components, Installing and  
configuring 1  
components, Optional 43  
configurable files 147  
configuration details, CARMA 55  
configuration file changes, other  
products 135  
configuration files, CA Endeavor® SCM  
RAM  
CRASHOW 65  
CRATMAP 65  
configuration of requisite products and  
software 6  
configuration.properties  
default.store 90  
enabled 90  
primary\_system 90  
project\_enabled 90  
pushtoclient.folder 90  
version 90  
configuring host components 1  
connection regions, CICS  
non-primary 83  
connection, JES Job Monitor 114  
connection, lock daemon 114  
connection, RSE daemon 113  
considerations, pre-configuration 6  
considerations, predeployment 8  
considerations, Preinstallation 2  
considerations, server 7  
considerations, User ID 6  
console messages 164  
JES Job Monitor 164  
Console messages  
lock daemon 164  
RSE daemon 164  
RSE thread pool server 164  
controlled libraries for RSE, Define  
MVS 129  
CRA#CIRX, IRXJCL versus CRAXJCL 71  
CRA0VCAD 69  
CRA0VCAS 69  
CRA0VDEF 69  
CRA0VSTR 69  
CRABATCA, SCM RAM batch action 68  
CRABCFG, SCM RAM batch action  
configuration 67  
CRADEF 69  
CRADEF, configuration data set  
CRA\$VCAD 62  
CRA\$VDEF 62  
CRAISPRX, ISPF configuration file 42  
CRAMSG, message data set 62  
CRANDVRA 65, 70  
CRASRV.properties 56  
clist.dsname 56  
crastart.configuration.file 56  
crastart.steplib 56  
crastart.stub 56  
crastart.syslog 56  
crastart.tasklib 56  
crastart.timeout 56  
port.range 56  
port.start 56  
startup.script.name 56  
CRASRV.properties, customizing 48, 50,  
52, 54  
CRASTART 47  
CRASTART with sample RAMs 50  
crastart.conf, customizing 51  
crastart.endeavor.conf, customizing 48  
crastart\*.conf, CRASTART server  
startup 58  
CRASTRS 69

- CRASTRS, custom string data set 62
- CRASUB\*, batch submit server
  - startup 60
- CRASUBCA, customizing 52
- CRASUBMT, customizing 55
- CRAXJCL, IRXJCL versus CRAXJCL 71
- CRD repository 82
- CRD server transaction IDs,
  - customizing 84
- CRD server using the RESTful
  - interface 83
- creating LSTRANS.FILE 76
- cron, WORKAREA directory
  - cleanup 102
- custom allocation exec 70
- customization setup 11
- customization tasks, optional 89
- customization, basic 11
- customization, SCLM Developer
  - Toolkit 73
- customizing CRD server transaction
  - IDs 84

## D

- daemon connection, RSE 109
- daemon, Lock 18
- daemon, RSE 18
- data set profiles, Define 122
- DB2 changes 98
- DB2 stored procedure 97
- Debug Tool, IBM, corequisite 16
- Define MVS program controlled libraries
  - for RSE 129
- Define PassTicket support for RSE 130
- Define RSE server as a secure z/OS
  - UNIX 129
- Define z/OS UNIX program controlled
  - files for RSE 132
- definitions, prerequisite LINKLIST and
  - LPA 16
- definitions, Security 22, 119
- Developer for System z started tasks,
  - Define 126
- Diagnostic IRZ error messages 101
- directory cleanup, WORKAREA
  - skulker 102

## E

- ELAXF\* high level qualifier checklist 21
- ELAXF\* procedures, Sample
  - ELAXFADT 20
  - ELAXFASM 20
  - ELAXFBMS 20
  - ELAXFCOC 20
  - ELAXFCOP 20
  - ELAXFCOT 20
  - ELAXFCP1 20
  - ELAXFCPC 20
  - ELAXFCPP 20
  - ELAXFDCL 20
  - ELAXFGO 20
  - ELAXFLNK 20
  - ELAXFMFS 20
  - ELAXFPL1 20

- ELAXF\* procedures, Sample (*continued*)
  - ELAXFPLP 20
  - ELAXFPLT 20
  - ELAXFPP1 20
  - ELAXFTSO 20
  - ELAXFUOP 20
- ELAXF\* remote build procedures 20
- ELAXMJCL, DB2 changes 98
- ELAXMSAM 98
- encryption, ssl.properties 93
- Enterprise Service Tools support 100
- error messages, IRZ Diagnostic 101

## F

- FEJJCNCFG, JES Job Monitor configuration
  - file 22
- FEJJJCL, PROCLIB changes, JES Job
  - monitor 17
- FEJTOS 22
- FEKLOCKD 18
- FEKRACE, security definitions 22, 119
- FEKRSED 18
- FEKSETUP 11, 74, 83
- File Manager integration 92
- FMID HHOP750 151
- FMID HHOP760 144
- FMIEXT.properties
  - enabled 93
  - fmlistenport 93
- fragments, Syntax 167

## G

- Gateway, ISPF Client 109

## H

- Handler, Pipeline message 85
- HHOP750 151
- HHOP760 144
- host components, Installing and
  - configuring 1
- host-based client control 89

## I

- IBM Debug Tool, corequisite 16
- ID considerations, User 6
- initialization, IVP 111
- installation verification 103
- installation verification programs 110
- Installing and configuring host
  - components 1
- integration, File Manager 92
- interface, RESTful versus Web
  - Service 83
- IRXJCL, IRXJCL versus CRAXJCL 71
- ISPSISPLD
  - ISPF TSO/ISPF Client Gateway 129
- ISPF Client Gateway 109
- ISPF commands 42
- ISPF TSO/ISPF Client Gateway
  - ISPSISPLD 129
- ISPF.conf 42

- ISPF.conf (*continued*)

- allocjob 42
- ISPF\_timeout 42
- ispllib 42
- ispmlib 42
- ispllib 42
- ispslib 42
- isptlib 42
- sysproc 42
- ISPF.conf, updates for SCLMDT 74
- ISPF's TSO/ISPF Client Gateway
  - connection, verifying 115

- IVP

- fekfivpd 113
- fekfivpi 115
- fekfivpj 114
- fekfivpl 114
- fekfivps 117
- IVP initialization
  - ivpinit 111
- IVP operator commands 108
- IVP, basic and optional services
  - fekfivpd 110
  - fekfivpi 110
  - fekfivpj 110
  - fekfivpl 110
  - fekfivps 110
  - fekfivpt 110
  - IVP scripts 110
- ivpinit shell script, setting RSE
  - environment variables with 111

## J

- J2EE 73, 78
- Java 73, 78
- Java startup parameters with
  - \_RSE\_CMDSERV\_OPTS, Defining 41
- Java startup parameters with
  - \_RSE\_JAVAOPTS, Defining 36
- JES command security, Define 127
- JES JMON, FEJJCNCFG
  - \_BPXK\_SETIBMOPT
  - \_TRANSPORT 23
- APPLID 23
- AUTHMETHOD 23
- CODEPAGE 23
- CONCHAR 23
- CONSOLE\_NAME 23
- GEN\_CONSOLE\_NAME 23
- HOST\_CODEPAGE 23
- LIMIT\_COMMANDS 23
- LIMIT\_VIEW 23
- LISTEN\_QUEUE\_LENGTH 23
- MAX\_DATASETS 23
- MAX\_THREADS 23
- SERV\_PORT 23
- SUBMITMETHOD 23
- TIMEOUT 23
- TIMEOUT\_INTERVAL 23
- TSO\_TEMPLATE 23
- TZ 23
- JES Job Monitor configuration file,
  - FEJJCNCFG, 22
- JES Job Monitor connection 114
- JES Job Monitor server 17
- JES Job Monitor started task, JMON 17

- JES Job Monitor, JMON 103
- JES Job Monitor, Modify command 157
- JES Job Monitor, Start command 155
- JMON 17, 128
  - fekfivpj 114
- JMON, JES Job Monitor 103
- Job Monitor server, JES 17

## L

- libraries for RSE , Define MVS 129
- limits, z/OS UNIX set in BPXPRMxx 12
- LINKLIST definitions, prerequisite 16
- LINKLIST, definitions for other products 17
- lock daemon
  - console messages 164
- Lock daemon 18
- lock daemon connection 114
- lock daemon, LOCKD 103
- Lock daemon, Modify command 163
- Lock daemon, Start command 156
- LOCKD 7
- LOCKD, lock daemon 103
- Logging configuration file, rsecomm.properties 96
- long/short name translation, rsed.envvars updates for 78
- Long/short name translation, SCLM 75
- LPA definitions, prerequisite 16
- LPALSTxx, LPA definitions in 14
- LSTRANS.FILE, creating 76

## M

- manifest repository 86
- Message handler, Pipeline 85
- messages, console 164
- migration 135
- migration 8.0.3 136
- migration considerations 135
- Migration considerations 1
- migration scenarios, sample 144
- migration, CARMA VSAM 62
- migration, version 7.5 to 7.6 144
- multiple RAMs, supporting 69
- MVS program controlled libraries for RSE , Define 129

## N

- name translation, SCLM 75
- netstat, TCP/IP setup 112
- non-primary connection regions, CICS 83
- Nonalphanumeric characters, syntax diagram 166

## O

- OMVS segment, Define 122
- operand, Selecting more than one in a syntax diagram 167
- Operands, syntax diagram 166
- operating systems supported 1

- operator commands, IVP 108
- Optional components 43
- optional customization tasks 89

## P

- PARM variable, JCL limitations 19
- PARMLIB, changes 12
- PassTicket support for RSE , Define 130
- PassTicket, reusability 108
- Pipeline message handler 85
- platforms supported 1
- Port availability 111
- PORTRANGE 36
- PORTRANGE available for RSE , Defining 35
- ports, REXEC 100
- pre-configuration considerations 6
- predeployment considerations 8
- Preinstallation considerations 2
- prerequisite products 2
- previously configured files, backing up
  - Version 7.1 135
  - Version 7.5 135
- primary connection region, CICS 83
- PROCLIB changes 97
- PROCLIB, changes 17
- products and software, configuration of requisite 6
- products, prerequisite 2
- profiles, Define data set 122
- PROGxx, APF authorizations 14
- PROGxx, LINKLIST definitions 15
- publications, Referenced 173
- pushtoclient.properties 89

## Q

- qualifier checklist, ELAXF\* 21

## R

- RACF
  - permits 123
- read a syntax diagram, How to 166
- Referenced publications 173
- remote build procedures, ELAXF\* 20
- Remote Execution, using 99
- Remote Systems Explorer 8
- Remove old files from /tmp 80
- Remove old files from WORKAREA 80
- Repository Access Managers, CARMA
  - CA Endeavor® SCM RAM 63
  - PDS RAM 63
  - SCLM RAM 63
  - Skeleton RAM 63
- repository, CRD 82
- repository, manifest 86
- required resources 3
- requirements checklist 11
- requisite products and software, configuration of 6
- resources, required 3
- RESTful interface
  - ADMI 84
  - ADMR 84
- RESTful interface (*continued*)
  - ADMS 84
- RESTful interface versus Web Service interface 83
- RESTful interface, CRD server using 83
- reusability, PassTicket 108
- REXEC set up 100
- REXEC, using 99
- RSE 8
- RSE , Define MVS program controlled libraries for 129
- RSE , Define PassTicket support for 130
- RSE , Defining the PORTRANGE 35
- RSE configuration file, rsed.envvars, 27
- RSE daemon 7, 18
  - console messages 164
- RSE daemon connection 109, 113
- RSE daemon, Modify command 158
- RSE daemon, RSED 103
- RSE daemon, Start command 155
- RSE interface to CARMA 56
- RSE SSL encryption, ssl.properties, daemon properties 93
  - server properties 93
- RSE started task, RSED 18
- RSE thread pool server
  - console messages 164
- RSE trace configuration, rsecomm.properties, 96
- RSE, define application protection for 130
- RSE, Define as a secure z/OS UNIX server 129
- RSE, Define z/OS UNIX program controlled files for 132
- rsecomm.properties
  - debug\_level 96
  - log\_location 96
  - server.version 96
- rsecomm.properties, 96
- RSED 18
- RSED, RSE daemon 103
- rsed.envvars 159
  - \_BPX\_SHAREAS 34
  - \_BPX\_SPAWN\_SCRIPT 34
  - \_BPXK\_SETIBMOPT
    - \_TRANSPORT 32
  - \_CEE\_DMPPTARG 30
  - \_CEE\_RUNOPTS 34
  - \_CMDSERV\_BASE\_HOME 31
  - \_CMDSERV\_CONF\_HOME 31
  - \_CMDSERV\_WORK\_HOME 31
  - \_FEKFSCMD\_PARTNER\_LU\_ 32
  - \_FEKFSCMD\_TP\_NAME\_ 32
  - \_RSE\_CMDSERV\_OPTS 34
  - \_RSE\_DAEMON\_CLASS 34
  - \_RSE\_HOST\_CODEPAGE 30
  - \_RSE\_JAVAOPTS 34
  - \_RSE\_LOCKD\_CLASS 34
  - \_RSE\_LOCKD\_PORT 30
  - \_RSE\_POOL\_SERVER\_CLASS 34
  - \_RSE\_PORTRANGE 32
  - \_RSE\_SERVER\_CLASS 34
  - \_RSE\_SERVER\_TIMEOUT 34
  - \_SCLMDT\_TRANTABLE 32
  - &ISPPROF=&SYSUID..ISPPROF 41
  - ANT\_HOME 32

rsed.envvars (*continued*)

- CGI\_DTWORk 34
- CLASSPATH 34
- DAPPLID 40
- Daudit.cycle 38
- Daudit.retention.period 38
- Ddaemon.log 37
- DDENY\_PASSWORD 40
- Ddeny.nonzero.port 39
- DDSTORE\_IDLE\_SHUTDOWN\_TIMEOUT 40
- DDSTORE\_LOG\_DIRECTORY 37
- DDSTORE\_MEMLOGGING\_ON 40
- DDSTORE\_TRACING\_ON 40
- Denable.audit.log 38
- Denable.automount 38
- Denable.certificate.mapping 38
- Denable.port.of.entry 38
- Denable.standard.log 38
- DHIDE\_ZOS\_UNIX 40
- Dipv6 38
- Dkeep.last.log 38
- Dmaximum.clients 37
- Dmaximum.threadpool.process 38
- Dmaximum.threads 37
- Dminimum.threadpool.process 37
- Dprocess.cleanup.interval 39
- Dsingle.logon 39
- DTSO\_SERVER 40
- Duser.log 37
- GSK\_CRL\_SECURITY\_LEVEL 32
- GSK\_LDAP\_PASSWORD 32
- GSK\_LDAP\_PORT 32
- GSK\_LDAP\_SERVER 32
- GSK\_LDAP\_USER 32
- JAVA\_HOME 30
- JAVA\_PROPAGATE 34
- LANG 30
- LIBPATH 34
- PATH 30, 34
- RSE\_HOME 30
- RSE\_JAVAOPTS 31
- RSE\_LIB 34
- RSE\_SAF\_CLASS 31
- SCLMDT\_BASE\_HOME 34
- SCLMDT\_CONF\_HOME 32
- SCLMDT\_WORK\_HOME 34
- STEPLIB 30, 31, 32
- TZ 30
- Xms 37
- Xmx 37

rsed.envvars, RSE configuration file 27

rsed.envvars, updates for long/short name translation 78

rsed.envvars, updates for SCLMDT 75

## S

sample RAMs, batch submit 54

SCLM 78

SCLM administrator checklist 79

SCLM Developer Toolkit 130

SCLM Developer Toolkit connection, verifying

- SCLMDT checks 117

SCLM Developer Toolkit service 15

SCLM Developer Toolkit, customization 73

SCLM updates for SCLMDT 79

SCLM, Long/short name translation 75

SCLMDT admin 79

SCLMDT connection, verifying 117

SCLMDT, ISPF.conf updates for 74

SCLMDT, rsed.envvars updates for 75

SCM packages RAM, CA Endeavor 64

SCM RAM batch action configuration, CRABCFG 67

SCM RAM batch action JCL, CRABATCA 68

SCM RAM batch actions 66

SDSF 74

Secure Shell, using 99

secure z/OS UNIX server, Define RSE as a 129

Security definitions 22, 119

security definitions, Checklist 119

security settings and classes, Activate 120

security settings, verify 132

security, Define JES command 127

segment, Define OMVS 122

server considerations 7

server startup method, select 46

settings and classes, Activate security 120

setup, customization 11

skulker, WORKAREA directory cleanup 102

software, configuration of requisite products and 6

spaces, syntax diagram 166

SSH set up 100

SSH, using 99

ssl.properties 93

- daemon\_key\_label 95
- daemon\_keydb\_file 95
- daemon\_keydb\_password 95
- enable\_ssl 95
- server\_keystore\_file 95
- server\_keystore\_label 95
- server\_keystore\_password 95
- server\_keystore\_type 95

Start (S) command 155

started tasks, Define for Developer for System z

- JMON started tasks 126
- LOCKD started tasks 126
- RSED started tasks 126

started tasks, verifying 103

started tasks, verifying services 110

startup parameters with

- \_RSE\_CMDSERV\_OPTS, Defining extra Java 41

startup parameters with

- \_RSE\_JAVAOPTS, Defining extra Java 36

STEPLIB use 16

Stop (P) command 163

stored procedure, DB2 97

subsystems supported 1

support for RSE, Define PassTicket 130

support, Enterprise Service Tools 100

Symbols, syntax diagram 166

syntax diagram, How to read 166

syntax diagram, Longer than one line 167

syntax diagram, Nonalphanumeric characters and blank spaces 166

syntax diagram, Operands 166

syntax diagram, Selecting more than one operand 167

syntax diagram, symbols 166

Syntax fragments 167

Syntax, example 166

SYS1.PARMLIB(BPXPRMxx) MAXASSIZE 127

SYSEXEC 42

SYSPROC 42

## T

tasks, optional customization 89

TCP/IP setup, netstat 112

trace configuration, rsecomm.properties 96

tracing, RSE 96

TSO/ISPF Client Gateway configuration file 42

TSO/ISPF Client Gateway, deprecated 46

## U

UNIX program controlled files for RSE, Define 132

UNIX server, Define RSE as 129

usage considerations, APPC 89

User ID considerations 6

## V

Verify security settings 132

verifying ISPF's TSO/ISPF Client Gateway connection 115

VSAM data sets, creating 54

## W

Web Service interface

- ADMI 85
- ADMR 85
- ADMS 85

Web Service interface versus RESTful interface 83

Web Service interface, CRD server using 84

WLM considerations 169

WORKAREA directory cleanup skulker 102

WORKAREA, Remove old files from 80

Workload Manager changes 97

## Z

z/OS UNIX limits set in BPXPRMxx 12

z/OS UNIX program controlled files for RSE, Define 132

z/OS UNIX server, Define RSE as 129



---

## Readers' Comments — We'd Like to Hear from You

IBM Rational Developer for System z  
Version 8.0.3  
Configuration Guide

Publication No. SC23-7658-06

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Send your comments to the address on the reverse side of this form.

If you would like a response from IBM, please fill in the following information:

\_\_\_\_\_  
Name

\_\_\_\_\_  
Address

\_\_\_\_\_  
Company or Organization

\_\_\_\_\_  
Phone No.

\_\_\_\_\_  
Email address



Cut or Fold  
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

**BUSINESS REPLY MAIL**

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM  
Corporation  
Building 501  
P.O Box 12195  
Research Triangle Park, NC  
USA 27709-2195



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold  
Along Line







Printed in USA

SC23-7658-06

