


---

# Platform LSF Configuration Reference

Platform LSF™  
Version 7.0 Update 5  
Release date: April 2009  
Last modified: April 25, 2009



Copyright

© 1994-2009 Platform Computing Inc.

Although the information in this document has been carefully reviewed, Platform Computing Corporation ("Platform") does not warrant it to be free of errors or omissions. Platform reserves the right to make corrections, updates, revisions or changes to the information in this document.

UNLESS OTHERWISE EXPRESSLY STATED BY PLATFORM, THE PROGRAM DESCRIBED IN THIS DOCUMENT IS PROVIDED "AS IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. IN NO EVENT WILL PLATFORM COMPUTING BE LIABLE TO ANYONE FOR SPECIAL, COLLATERAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING WITHOUT LIMITATION ANY LOST PROFITS, DATA, OR SAVINGS, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS PROGRAM.

We'd like to hear from you

You can help us make this document better by telling us what you think of the content, organization, and usefulness of the information. If you find an error, or just want to make a suggestion for improving this document, please address your comments to [doc@platform.com](mailto:doc@platform.com).

Your comments should pertain only to Platform documentation. For product support, contact [support@platform.com](mailto:support@platform.com).

Document redistribution and translation

This document is protected by copyright and you may not redistribute or translate it into another language, in part or in whole.

Internal redistribution

You may only redistribute this document internally within your organization (for example, on an intranet) provided that you continue to check the Platform Web site for updates and update your version of the documentation. You may not make it available to your organization over the Internet.

Trademarks

LSF is a registered trademark of Platform Computing Corporation in the United States and in other jurisdictions.

ACCELERATING INTELLIGENCE, PLATFORM COMPUTING, PLATFORM SYMPHONY, PLATFORM JOBSCHEDULER, PLATFORM ENTERPRISE GRID ORCHESTRATOR, PLATFORM EGO, and the PLATFORM and PLATFORM LSF logos are trademarks of Platform Computing Corporation in the United States and in other jurisdictions.

UNIX is a registered trademark of The Open Group in the United States and in other jurisdictions.

Linux is the registered trademark of Linus Torvalds in the U.S. and other countries.

Microsoft is either a registered trademark or a trademark of Microsoft Corporation in the United States and/or other countries.

Windows is a registered trademark of Microsoft Corporation in the United States and other countries.

Intel, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Other products or services mentioned in this document are identified by the trademarks or service marks of their respective owners.

Third-party license agreements

<http://www.platform.com/Company/third.part.license.htm>

---

# Contents

---

---

## Part I: Features ... 5

Feature: Between-host user account mapping .....	7
Feature: Cross-cluster user account mapping .....	12
Feature: SSH .....	17
Feature: External authentication .....	19
Feature: LSF daemon startup control .....	29
Feature: Pre-execution and post-execution processing .....	38
Feature: Preemptive scheduling .....	50
Feature: UNIX/Windows user account mapping .....	62
Feature: External job submission and execution controls .....	70
Feature: Job migration .....	91
Feature: Job checkpoint and restart .....	98
Feature: Resizable Jobs .....	111
Feature: External load indices .....	116
Feature: External host and user groups .....	128

---

## Part II: Configuration Files ... 133

bld.license.acct .....	135
cshrc.lsf and profile.lsf .....	137
hosts .....	146
install.config .....	149
lim.acct .....	161
lsb.acct .....	162
lsb.applications .....	171
lsb.events .....	205
lsb.hosts .....	241
lsb.modules .....	257
lsb.params .....	262
lsb.queues .....	311
lsb.resources .....	359
lsb.serviceclasses .....	387
lsb.users .....	395
lsf.acct .....	402
lsf.cluster .....	405
lsf.cluster_name.license.acct .....	426

lsf.conf .....	428
lsf.licensescheduler .....	544
lsf.shared .....	572
lsf.sudoers .....	578
lsf.task .....	584
setup.config .....	587
slave.config .....	590

---

**Part III: Environment Variables ... 597**

Environment variables .....	599
-----------------------------	-----

---

**Part IV: Troubleshooting ... 641**

Troubleshooting and error messages .....	643
Understanding Platform LSF job exit information .....	655

P A R T

---



## Features



# Feature: Between-host user account mapping

The between-host user account mapping feature enables job submission and execution within a cluster that has different user accounts assigned to different hosts. Using this feature, you can map a local user account to a different user account on a remote host.

## Contents

- About between-host user account mapping
- Scope
- Configuration to enable between-host user account mapping
- Between-host user account mapping behavior
- Configuration to modify between-host user account mapping behavior
- Between-host user account mapping commands

## About between-host user account mapping

For clusters with different user accounts assigned to different hosts., between-host user account mapping allows you to submit a job from a local host and run the job as a different user on a remote host. There are two types of between-host user account mapping:

- Local user account mapping—for UNIX or Windows hosts, a user can map the local user account to a different user on a remote host
- Windows workgroup account mapping—allows LSF administrators to map all Windows workgroup users to a single Windows system account, eliminating the need to create multiple users and passwords in LSF. Users can submit and run jobs using their local user names and passwords, and LSF runs the jobs using the mapped system account name and password. With Windows workgroup account mapping, all users have the same permissions because all users map to the same Windows system account.




Figure 1: Default behavior (feature not enabled)

Feature: Between-host user account mapping




Figure 2: With local user account mapping enabled




Figure 3: With Windows workgroup account mapping enabled

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX hosts</li> <li>• Windows hosts</li> <li>• A mix of UNIX and Windows hosts within a single clusters</li> </ul>
Not required for	<ul style="list-style-type: none"> <li>• A cluster with a uniform user name space</li> <li>• A mixed UNIX/Windows cluster in which user accounts have the same user name on both operating systems</li> </ul>

Applicability	Details
Dependencies	<ul style="list-style-type: none"> <li>UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> <li>For clusters that include both UNIX and Windows hosts, you must also enable the UNIX/Windows user account mapping feature.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>For a MultiCluster environment that has different user accounts assigned to different hosts, you must also enable the cross-cluster user account mapping feature. Do not configure between-host user account mapping if you want to use system-level mapping in a MultiCluster environment; LSF ignores system-level mapping if mapping local user mapping is also defined in <code>.lsfhost.s</code>.</li> <li>For Windows workgroup account mapping in a Windows workgroup environment, all jobs run using the permissions associated with the specified system account.</li> </ul>

## Configuration to enable between-host user account mapping

Between-host user account mapping can be configured in one of the following ways:

- Users can map their local accounts at the user level in the file `.lsfhost.s`. This file must reside in the user's home directory with owner read-write permissions for UNIX and owner read-write-execute permissions for Windows. It must not be readable and writable by any other user other than the owner. Save the `.lsfhost.s` file without a file extension. Both the remote and local hosts must have corresponding mappings in their respective `.lsfhost.s` files.
- LSF administrators can set up Windows workgroup account mapping at the system level in `lsb.params`.

## Local user account mapping configuration

Local user account mapping is enabled by adding lines to the file `.lsfhost.s`. Both the remote and local hosts must have corresponding mappings in their respective `.lsfhost.s` files.

Configuration file	Syntax	Behavior
<code>.lsfhost.s</code>	<code>host_name user_name send</code>	<ul style="list-style-type: none"> <li>Jobs sent from the local account run as <code>user_name</code> on <code>host_name</code></li> </ul>
	<code>host_name user_name recv</code>	<ul style="list-style-type: none"> <li>The local account can run jobs received from <code>user_name</code> submitted on <code>host_name</code></li> </ul>
	<code>host_name user_name</code>	<ul style="list-style-type: none"> <li>The local account can send jobs to and receive jobs from <code>user_name</code> on <code>host_name</code></li> </ul>
	<code>++</code>	<ul style="list-style-type: none"> <li>The local account can send jobs to and receive jobs from any user on any LSF host</li> </ul>

## Windows workgroup account mapping

Windows workgroup account mapping is enabled by defining the parameter `SYSTEM_MAPPING_ACCOUNT` in the file `lsb.params`.

Configuration file	Parameter and syntax	Default behavior
lsb.params	SYSTEM_MAPPING_ACCOUNT= <i>account</i>	<ul style="list-style-type: none"> <li>Enables Windows workgroup account mapping</li> <li>Windows local user accounts run LSF jobs using the system account name and permissions</li> </ul>

## Between-host user account mapping behavior

### Local user account mapping example

The following example describes how local user account mapping works when configured in the file `.lsfhosts` in the user's home directory. Only mappings configured in `.lsfhosts` on both the local and remote hosts work.

In the following example, the cluster contains `hostA`, `hostB`, and `hostC`. The account `user1` is valid on all hosts except `hostC`, which requires a user account name of `user99`.

To allow ...	On ...	In the home directory of ...	.lsfhosts must contain the line ...
The account <code>user1</code> to run jobs on all hosts within the cluster:			
<ul style="list-style-type: none"> <li><code>user1</code> to send jobs to <code>user99</code> on <code>hostC</code></li> </ul>	<code>hostA</code>	<code>user1</code>	<code>hostC user99 send</code>
	<code>hostB</code>	<code>user1</code>	<code>hostC user99 send</code>
<ul style="list-style-type: none"> <li><code>user99</code> to receive jobs from <code>user1</code> on either <code>hostA</code> or <code>hostB</code></li> </ul>	<code>hostC</code>	<code>user99</code>	<code>hostA user1 recv</code> <code>hostB user1 recv</code>

### Windows workgroup account mapping example

The following example describes how Windows workgroup account mapping works when configured in the file `lsb.params`. In this example, the cluster has a Windows workgroup environment, and only the user account `jobuser` is valid on all hosts.

To allow ...	In lsb.params, configure ...	Behavior
All hosts within the cluster to run jobs on any other host within the cluster:		
<ul style="list-style-type: none"> <li>Map all local users to user account <code>jobuser</code></li> </ul>	<code>SYSTEM_MAPPING_ACCOUNT=j obuser</code>	When any local user submits an LSF job, the job runs under the account <code>jobuser</code> , using the permissions associated with the <code>jobuser</code> account.

## Configuration to modify between-host user account mapping behavior

Not applicable: There are no parameters that modify the behavior of this feature.

## Between-host user account mapping commands

### Commands for submission

Command	Description
<code>bsub</code>	<ul style="list-style-type: none"> <li>Submits the job with the user name and password of the user who entered the command. The job runs on the execution host with the submission user name and password, unless you have configured between-host user account mapping.</li> <li>With between-host user account mapping enabled, jobs that execute on a remote host run using the account name configured at the system level for Windows workgroups, or at the user level for local user account mapping.</li> </ul>

### Commands to monitor

Command	Description
<code>bj obs -l</code>	<ul style="list-style-type: none"> <li>Displays detailed information about jobs, including the user name of the user who submitted the job and the user name with which the job executed.</li> </ul>
<code>bhi st -l</code>	<ul style="list-style-type: none"> <li>Displays detailed historical information about jobs, including the user name of the user who submitted the job and the user name with which the job executed.</li> </ul>

### Commands to control

Not applicable.

### Commands to display configuration

Command	Description
<code>bparams</code>	<ul style="list-style-type: none"> <li>Displays the value of <code>SYSTEM_MAPPING_ACCOUNT</code> defined in <code>l sb. params</code>.</li> </ul>
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>Displays all configured parameters and their values set in <code>l sf. conf</code> or <code>ego. conf</code> that affect <code>mbat chd</code> and <code>sbat chd</code>. Use a text editor to view other parameters in the <code>l sf. conf</code> or <code>ego. conf</code> configuration files.</li> <li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

Use a text editor to view the file `.l sfhost s`.

# Feature: Cross-cluster user account mapping

The cross-cluster user account mapping feature enables cross-cluster job submission and execution for a MultiCluster environment that has different user accounts assigned to different hosts. Using this feature, you can map user accounts in a local cluster to user accounts in one or more remote clusters.

## Contents

- About cross-cluster user account mapping
- Scope
- Configuration to enable cross-cluster user account mapping
- Cross-cluster user account mapping behavior
- Configuration to modify cross-cluster user account mapping behavior
- Cross-cluster user account mapping commands

## About cross-cluster user account mapping

For MultiCluster environments that have different user accounts assigned to different hosts, cross-cluster user account mapping allows you to submit a job from a local host and run the job as a different user on a remote host.




Figure 4: Default behavior (feature not enabled)




Figure 5: With cross-cluster user account mapping enabled

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX hosts</li> <li>• Windows hosts</li> <li>• A mix of UNIX and Windows hosts within one or more clusters</li> </ul>
Not required for	<ul style="list-style-type: none"> <li>• Multiple clusters with a uniform user name space</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> <li>• If users at your site have different user names on UNIX and Windows hosts within a single cluster, you must configure between-host user account mapping at the user level in <code>.lsfhosts</code>.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>• You cannot configure this feature at both the system-level and the user-level; LSF ignores system-level mapping if user-level mapping is also defined in <code>.lsfhosts</code>.</li> <li>• If one or more clusters include both UNIX and Windows hosts, you must also configure UNIX/Windows user account mapping.</li> <li>• If one or more clusters have different user accounts assigned to different hosts, you must also configure between-host user account mapping for those clusters, and then configure cross-cluster user account mapping at the system level only.</li> </ul>

## Configuration to enable cross-cluster user account mapping

- LSF administrators can map user accounts at the system level in the UserMap section of `lsb.users`. Both the remote and local clusters must have corresponding mappings in their respective `lsb.users` files.
- Users can map their local accounts at the user level in `.lsfhosts`. This file must reside in the user's home directory with owner read-write permissions for UNIX and owner read-write-execute permissions for Windows. Save the `.lsfhosts` file without a file extension. Both the remote and local hosts must have corresponding mappings in their respective `.lsfhosts` files.

### Restriction:

Define *either* system-level or user-level mapping, but not both. LSF ignores system-level mapping if user-level mapping is also defined in `.lsfhosts`.

Configuration file	Level	Syntax	Behavior
lsb.users	System	Required fields: LOCAL REMOTE DIRECTION	<ul style="list-style-type: none"> <li>Maps a user name on a local host to a different user name on a remote host</li> <li>Jobs that execute on a remote host run using a mapped user name rather than the job submission user name</li> </ul>
.lsfhosts	User	<i>host_name user_name send</i>	Jobs sent from the local account run as <i>user_name</i> on <i>host_name</i>
		<i>host_name user_name recv</i>	The local account can run jobs received from <i>user_name</i> submitted on <i>host_name</i>
		<i>host_name user_name</i>	The local account can send jobs to and receive jobs from <i>user_name</i> on <i>host_name</i>
		<i>cluster_name user_name</i>	The local account can send jobs to and receive jobs from <i>user_name</i> on any host in the cluster <i>cluster_name</i>
		++	The local account can send jobs to and receive jobs from any user on any LSF host

## Cross-cluster user account mapping behavior

### System-level configuration example

The following example illustrates LSF behavior when the LSF administrator sets up cross-cluster user account mapping at the system level. This example shows the UserMap section of the file `lsb.users` on both the local and remote clusters.

*On cluster1:*

```
Begin UserMap
LOCAL    REMOTE
user1    user2@cluster2
user3    user6@cluster2
End UserMap
DI RECTI ON
export
export
```

*On cluster2:*

```
Begin UserMap
LOCAL    REMOTE
user2    user1@cluster1
user6    user3@cluster1
End UserMap
DI RECTI ON
import
import
```

The mappings between users on different clusters are as follows:




Figure 6: System-level mappings for both clusters

Only mappings configured in `lsb.users` on both clusters work. In this example, the common user account mappings are:

- `user1@cluster1` to `user2@cluster2`
- `user3@cluster1` to `user6@cluster2`

## User-level configuration examples

The following examples describe how user account mapping works when configured at the user level in the file `.lsfhosts` in the user's home directory. Only mappings configured in `.lsfhosts` on hosts in both clusters work.

To allow ...	On ...	In the home directory of ...	.lsfhosts must contain the line ...
The accounts <code>user1</code> and <code>user2</code> to run jobs on all hosts in both clusters:			
• <code>user1</code> to send jobs to and receive jobs from <code>user2</code> on cluster2	All hosts in cluster1	<code>user1</code>	<code>cluster2 user2</code>
• <code>user2</code> to send jobs to and receive jobs from <code>user1</code> on cluster1	All hosts in cluster2	<code>user2</code>	<code>cluster1 user1</code>
The account <code>user1</code> to run jobs on cluster2 using the <code>lsfguest</code> account:			
• <code>user1</code> to send jobs as <code>lsfguest</code> to all hosts in cluster2	All hosts in cluster1	<code>user1</code>	<code>cluster2 lsfguest send</code>
• <code>lsfguest</code> to receive jobs from <code>user1</code> on cluster1	All hosts in cluster2	<code>lsfguest</code>	<code>cluster1 user1 rcv</code>

## Configuration to modify cross-cluster user account mapping behavior

Not applicable: There are no parameters that modify the behavior of this feature.

## Cross-cluster user account mapping commands

### Commands for submission

Command	Description
<code>bsub</code>	<ul style="list-style-type: none"><li>Submits the job with the user name and password of the user who entered the command. The job runs on the execution host with the submission user name and password, unless you have configured cross-cluster user account mapping.</li><li>With cross-cluster user account mapping enabled, jobs that execute on a remote host run using the account name configured at the system or user level.</li></ul>

### Commands to monitor

Command	Description
<code>bjobs -l</code>	<ul style="list-style-type: none"><li>Displays detailed information about jobs, including the user name of the user who submitted the job and the user name with which the job executed.</li></ul>
<code>bhist -l</code>	<ul style="list-style-type: none"><li>Displays detailed historical information about jobs, including the user name of the user who submitted the job and the user name with which the job executed.</li></ul>

### Commands to control

Not applicable. There are no commands to control the behavior of this feature.

### Commands to display configuration

Not applicable. Use a text editor to view `.lsfhost.s` or to view the UserMap section of `lsb.users`.

# Feature: SSH

Secure Shell or SSH is a network protocol that provides confidentiality and integrity of data using a secure channel between two networked devices. You can enable and use SSH to secure communication between hosts and during job submission.

## About SSH

SSH uses public-key cryptography to authenticate the remote computer and allow the remote computer to authenticate the user, if necessary.

SSH is typically used to log into a remote machine and execute commands, but it also supports tunneling, forwarding arbitrary TCP ports and X11 connections. SSH uses a client-server protocol.

SSH uses private/public key pairs to log into another host. Users no longer have to supply a password every time they log on to a remote host.

SSH is used when running any of the following:

- Remote log on to a lightly loaded host (`lsl ogi n`)
- An interactive job (`bsub -IS | -ISp | ISs`)
- An interactive X-window job (`bsub -IX`)
- An externally submitted job that is interactive or X-window (`esub`)

## Scope

Applicability	Details
Dependencies	<ul style="list-style-type: none"> <li>• OpenSSH is fully supported.</li> <li>• You must have SSH correctly installed on all machines requiring it.</li> <li>• You must generate public/private key pairs and add the content of the public key to the <code>authorized_keys</code> file on remote hosts. For more information, refer to your SSH documentation.</li> <li>• For X-window jobs, you must set the <code>DISPLAY</code> environment variable to <code>X-serverHost:0.0</code>, where <code>X-serverHost</code> is the name of the X-window server. Ensure the X-server can access itself. Run, for example, <code>xhost +l ocal host</code>.</li> </ul>
Operating system	Any that also support OpenSSH.
Limitations	Private user keys must have no password set.

## Configuration to enable SSH

Configuration file	Level	Syntax	Behavior
<code>lsf.conf</code>	System	<code>LSF_LSLOGIN_SSH=Y   y</code>	<p>A user with SSH configured can log on to a remote host without providing a password.</p> <p>All communication between local and remote hosts is encrypted.</p>

## Configuration to modify SSH

Not applicable.

## SSH commands

### Commands to monitor

Command	Behavior
<code>netstat -an</code>	Displays all active TCP connections and the TCP and UDP ports on which the computer is listening.

### Troubleshoot SSH

Use the SSH command on the job execution host to connect it securely with the job submission host.

If the host fails to connect, you can perform the following steps to troubleshoot.

1. Check the SSH version on both hosts.

If the hosts have different SSH versions, a message displays identifying a protocol version mismatch.

2. Check that public and private key pairs are correctly configured.

More information on configuring key pairs is here: <http://sial.org/howto/openssh/publickey-auth/>.

3. Check the domain name.

```
$ ssh -f -L 6000:localhost:6000 domain_name.example.com date
```

```
$ ssh -f -L 6000:localhost:6000 domain_name date
```

If these commands return errors, troubleshoot the domain name with the error information returned.

The execution host should connect without password and pass phrases.

```
$ ssh sahpi a03  
$ ssh sahpi a03. exampl e. com
```

# Feature: External authentication

The external authentication feature provides a framework that enables you to integrate LSF with any third-party authentication product—such as Kerberos or DCE Security Services—to authenticate users, hosts, and daemons. This feature provides a secure transfer of data within the authentication data stream between LSF clients and servers. Using external authentication, you can customize LSF to meet the security requirements of your site.

## Contents

- About external authentication (eauth)
- Scope
- Configuration to enable external authentication
- External authentication behavior
- Configuration to modify external authentication
- External authentication commands

## About external authentication (eauth)

The external authentication feature uses an executable file called `eauth`. You can write an `eauth` executable that authenticates users, hosts, and daemons using a site-specific authentication method such as Kerberos or DCE Security Services client authentication. You can also specify an external encryption key (recommended) and the user account under which `eauth` runs.

---

### Important:

LSF uses an internal encryption key by default. To increase security, configure an external encryption key by defining the parameter `LSF_EAUTH_KEY` in `lsf.sudoers`.

---

During LSF installation, a default `eauth` executable is installed in the directory specified by the parameter `LSF_SERVERDIR` in `lsf.conf`. The default executable provides an example of how the `eauth` protocol works. You should write your own `eauth` executable to meet the security requirements of your cluster.

Feature: External authentication




Figure 7: Default behavior (eauth executable provided with LSF)

The `eauth` executable uses corresponding processes `eauth -c host_name` (client) and `eauth -s` (server) to provide a secure data exchange between LSF daemons on client and server hosts. The variable `host_name` refers to the host on which `eauth -s` runs; that is, the host called by the command. For `bsub`, for example, the `host_name` is NULL, which means the authentication data works for any host in the cluster.




Figure 8: How eauth works

One eauth -s process can handle multiple authentication requests. If eauth -s terminates, the LSF daemon invokes another instance of eauth -s to handle new authentication requests.

The standard input stream to eauth -s is a text string with the following format:

```
uid gid user_name client_addr client_port user_auth_data_len eauth_client eauth_server
aux_data_file aux_data_status user_auth_data
```

where

The variable ...	Represents the ...
<i>uid</i>	User ID of the client user
<i>gid</i>	Group ID of the client user
<i>user_name</i>	User name of the client user
<i>client_addr</i>	IP address of the client host
<i>client_port</i>	Port number from which the client request originates
<i>user_auth_data_len</i>	Length of the external authentication data passed from the client host
<i>eauth_client</i>	Daemon or user that invokes eauth -c
<i>eauth_server</i>	Daemon that invokes eauth -s

The variable ...	Represents the ...
<i>aux_data_file</i>	Location of the temporary file that stores encrypted authentication data
<i>aux_data_status</i>	File in which <code>eauth -s</code> stores authentication status. When used with Kerberos authentication, <code>eauth -s</code> writes the source of authentication to this file if authentication fails. For example, if <code>mbatchd</code> to <code>mbatchd</code> authentication fails, <code>eauth -s</code> writes "mbatchd" to the file defined by <i>aux_data_status</i> . If <code>user</code> to <code>mbatchd</code> authentication fails, <code>eauth -s</code> writes "user" to the <i>aux_data_status</i> file.
<i>user_auth_data</i>	External authentication data passed from the client host

The variables required for the `eauth` executable depend on how you implement external authentication at your site. For `eauth` parsing, unused variables are marked by "".

## User credentials

When an LSF user submits a job or issues a command, the LSF daemon that receives the request verifies the identity of the user by checking the user credentials. External authentication provides the greatest security of all LSF authentication methods because the user credentials are obtained from an external source, such as a database, and then encrypted prior to transmission. For Windows hosts, external authentication is the only truly secure type of LSF authentication.

## Host credentials

LSF first authenticates users and then checks host credentials. LSF accepts requests sent from all hosts configured as part of the LSF cluster, including floating clients and any hosts that are dynamically added to the cluster. LSF rejects requests sent from a non-LSF host. If your cluster requires additional host authentication, you can write an `eauth` executable that verifies both user and host credentials.

## Daemon credentials

Daemon authentication provides a secure channel for passing credentials between hosts, mediated by the master host. The master host mediates authentication by means of the `eauth` executable, which ensures secure passing of credentials between submission hosts and execution hosts, even though the submission host does not know which execution host will be selected to run a job.

Daemon authentication applies to the following communications between LSF daemons:

- `mbatchd` requests to `sbatchd`
- `sbatchd` updates to `mbatchd`
- PAM interactions with `res`
- `mbatchd` to `mbatchd` (in a MultiCluster environment)

## Kerberos authentication

Kerberos authentication is an extension of external daemon authentication, providing authentication of LSF users and daemons during client-server interactions. The `eauth` executable provided with the Platform integration package uses Kerberos Version 5 APIs for interactions between `mbatchd` and `sbatchd`, and between `pam` and `res`. When you use Kerberos authentication for a cluster or MultiCluster, authentication data is encrypted along the entire path from job submission through to job completion.

You can also use Kerberos authentication for delegation of rights (forwarding credentials) when a job requires a Kerberos ticket during job execution. LSF ensures that a ticket-granting ticket (TGT) can be forwarded securely to the execution host. LSF also automatically renews Kerberos credentials by means of daemon wrapper scripts.

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX</li> <li>• Windows (except for Kerberos authentication)</li> </ul>
Allows for	<ul style="list-style-type: none"> <li>• Authentication of LSF users, hosts, and daemons</li> <li>• Authentication of any number of LSF users</li> </ul>
Not required for	<ul style="list-style-type: none"> <li>• Authorization of users based on account permissions</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster, or the correct type of account mapping must be enabled: <ul style="list-style-type: none"> <li>• For a mixed UNIX/Windows cluster, UNIX/Windows user account mapping must be enabled</li> <li>• For a cluster with a non-uniform user name space, between-host account mapping must be enabled</li> <li>• For a MultiCluster environment with a non-uniform user name space, cross-cluster user account mapping must be enabled</li> </ul> </li> <li>• User accounts must have the correct permissions to successfully run jobs.</li> <li>• The owner of <code>lsf.sudoers</code> on Windows must be Administrators.</li> </ul>

## Configuration to enable external authentication

During LSF installation:

- The parameter `LSF_AUTH` in `lsf.conf` is set to `eauth`, which enables external authentication
- A default `eauth` executable is installed in the directory specified by the parameter `LSF_SERVERDIR` in `lsf.conf`

The default executable provides an example of how the `eauth` protocol works. You should write your own `eauth` executable to meet the security requirements of your cluster.

Configuration file	Parameter and syntax	Default behavior
lsf.conf	LSF_AUTH=eauth	<ul style="list-style-type: none"> <li>Enables external authentication</li> </ul>
	LSF_AUTH_DAEMONS=y   Y	<ul style="list-style-type: none"> <li>Enables daemon authentication when external authentication is enabled</li> </ul> <p><b>Note:</b></p> <p>By default, daemon authentication is not enabled. If you enable daemon authentication and want to turn it off later, you must comment out or delete the parameter <code>LSF_AUTH_DAEMONS</code>.</p>

## External authentication behavior

The following example illustrates how a customized `eauth` executable can provide external authentication of users, hosts, and daemons. In this example, the `eauth` executable has been customized so that corresponding instances of `eauth -c` and `eauth -s` obtain user, host, and daemon credentials from a file that serves as the external security system. The `eauth` executable can also be customized to obtain credentials from an operating system or from an authentication protocol such as Kerberos.




Figure 9: Example of external authentication

## Authentication failure

When external authentication is enabled, the message

User permission denied

indicates that the eauth executable failed to authenticate the user’s credentials.

## Security

External authentication—and any other LSF authentication method—depends on the security of the root account on all hosts within the cluster. Limit access to the root account to prevent unauthorized use of your cluster.

## Configuration to modify external authentication

You can modify external authentication behavior by writing your own eauth executable. There are also configuration parameters that modify various aspects of external authentication behavior by:

- Increasing security through the use of an external encryption key (recommended)
- Specifying a trusted user account under which the eauth executable runs (UNIX and Linux only)

You can also choose Kerberos authentication to provide a secure data exchange during LSF user and daemon authentication and to forward credentials to a remote host for use during job execution.

## Configuration to modify security

File	Parameter and syntax	Descriptions
<code>lsf.sudoers</code>	<code>LSF_EAUTH_KEY=key</code>	<ul style="list-style-type: none"> <li>The <code>eauth</code> executable uses the external encryption key that you define to encrypt and decrypt the credentials.</li> <li>The key must contain at least six characters and must use only printable characters.</li> <li>For UNIX, you must edit the <code>lsf.sudoers</code> file on all hosts within the cluster and specify the same encryption key. You must also configure <code>eauth</code> as <code>setuid</code> to <code>root</code> so that <code>eauth</code> can read the <code>lsf.sudoers</code> file and obtain the value of <code>LSF_EAUTH_KEY</code>.</li> <li>For Windows, you must edit the shared <code>lsf.sudoers</code> file.</li> </ul>

## Configuration to specify the eauth user account

On UNIX hosts, the `eauth` executable runs under the account of the primary LSF administrator. You can modify this behavior by specifying a different trusted user account. For Windows hosts, you do not need to modify the default behavior because `eauth` runs under the service account, which is always a trusted, secure account.

File	Parameter and syntax	Description
<code>lsf.sudoers</code>	<code>LSF_EAUTH_USER=user_name</code>	<ul style="list-style-type: none"> <li>UNIX only</li> <li>The <code>eauth</code> executable runs under the account of the specified user rather than the account of the LSF primary administrator</li> <li>You must edit the <code>lsf.sudoers</code> file on all hosts within the cluster and specify the same user name</li> </ul>

## Configuration to enable Kerberos authentication

To install and configure Kerberos authentication, refer to the information included with your Kerberos integration package provided by Platform Computing Inc..

### Restriction:

Kerberos authentication is supported only for UNIX and Linux hosts, and only on the following operating systems:

- AIX 4
- Alpha 4.x
- IRIX 6.5
- Linux 2.x

- Solaris 2.x

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSF_AUTH=eauth	<ul style="list-style-type: none"> <li>• Enables external authentication</li> </ul>
	LSF_AUTH_DAEMONS=y   Y	<ul style="list-style-type: none"> <li>• Enables daemon authentication when external authentication is enabled</li> </ul>
	LSF_DAEMON_WRAP=y   Y	<ul style="list-style-type: none"> <li>• Required for Kerberos authentication</li> <li>• mbatchd, sbatchd, and RES run the executable LSF_SERVERDIR/daemons.wrap</li> </ul>
lsf.sudoers	LSF_EAUTH_USER=root	<ul style="list-style-type: none"> <li>• for Kerberos authentication, the eauth executable must run under the root account</li> <li>• You must edit the lsf.sudoers file on all hosts within the cluster and specify the same user name</li> </ul>
	LSF_LOAD_PLUGINS=y   Y	<ul style="list-style-type: none"> <li>• Required for Kerberos authentication when plug-ins are used instead of the daemon wrapper script</li> <li>• LSF loads plug-ins from the directory LSB_LIBDIR</li> </ul>
	LSF_EEXEC_USER=root	<ul style="list-style-type: none"> <li>• Required for Kerberos authentication. The parameter LSF_DAEMON_WRAP must also be set to y or Y.</li> <li>• The eexec executable provided with the Kerberos integration runs under the root account</li> </ul>

## External authentication commands

### Commands for submission

Command	Description
All LSF commands	<ul style="list-style-type: none"> <li>• If the parameter LSF_AUTH=eauth in the file lsf.conf, LSF daemons authenticate users and hosts—as configured in the eauth executable—before executing an LSF command</li> <li>• If external authentication is enabled and the parameter LSF_AUTH_DAEMONS=Y in the file lsf.conf, LSF daemons authenticate each other as configured in the eauth executable</li> </ul>

### Commands to monitor

Not applicable: There are no commands to monitor the behavior of this feature.

### Commands to control

Not applicable: There are no commands to control the behavior of this feature.

## Commands to display configuration

Command	Description
<code>badmi n showconf</code>	<ul style="list-style-type: none"><li>Displays all configured parameters and their values set in <code>l sf. conf</code> or <code>ego. conf</code> that affect <code>mbat chd</code> and <code>sbat chd</code>.  Use a text editor to view other parameters in the <code>l sf. conf</code> or <code>ego. conf</code> configuration files.</li><li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li></ul>

Use a text editor to view the `l sf. sudoers` configuration file.

# Feature: LSF daemon startup control

The LSF daemon startup control feature allows you to specify a list of user accounts other than root that can start LSF daemons on UNIX hosts. This feature also enables UNIX and Windows users to bypass the additional login required to start `res` and `sbatchd` when the EGO Service Controller (EGOSC) is configured to control LSF daemons; bypassing the EGO administrator login enables the use of scripts to automate system startup.

## Contents

- About LSF daemon startup control
- Scope
- Configuration to enable LSF daemon startup control
- LSF daemon startup control behavior
- Configuration to modify LSF daemon startup control
- LSF daemon startup control commands

## About LSF daemon startup control

### Startup by users other than root (UNIX only)

On UNIX hosts, by default only root can manually start LSF daemons. To manually start LSF daemons, a user runs the commands `lsadmin n` and `badmi n`, which have been installed as `setuid root`. The LSF daemon startup control feature allows you to specify a list of user accounts that are allowed to run the commands `lsadmin n` and `badmi n` to start LSF daemons. The list is defined in the file `lsf.sudoers`.

On Windows hosts, the Platform services admin group identifies the user accounts that can start and shut down LSF daemons.




Figure 10: Default behavior (feature not enabled)

## Feature: LSF daemon startup control




Figure 11: With LSF daemon startup control enabled

## EGO administrator login bypass

If the EGO Service Controller (EGOSC) is configured to control LSF daemons, EGO will automatically restart the `res` and `sbatchd` daemons unless a user has manually shut them down. When manually starting a `res` or `sbatchd` daemon that EGO has not yet started, the user who invokes `lsadmin` or `badm` is prompted to enter EGO administrator credentials. You can configure LSF to bypass this step by specifying the EGO administrator credentials in the file `lsf.sudoers`.

In the following illustrations, an authorized user is either a UNIX user listed in the `LSF_STARTUP_USERS` parameter or a Windows user with membership in the Platform services admin group.




Figure 12: EGO administrator login bypass not enabled




Figure 13: With EGO administrator login bypass enabled

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>UNIX hosts only within a UNIX-only or mixed UNIX/Windows cluster: Startup of LSF daemons by users other than root.</li> <li>UNIX and Windows: EGO administrator login bypass.</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>For startup of LSF daemons by users other than root: <ul style="list-style-type: none"> <li>You must define both a list of users <i>and</i> the absolute path of the directory that contains the LSF daemon binary files.</li> <li>The commands <code>lsadmi n</code> and <code>badmi n</code> must be installed as <code>setuid root</code>.</li> </ul> </li> <li>For EGO administrator login bypass, the default Admin EGO cluster administrator account must be defined.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>Startup of LSF daemons by users other than root applies only to the following <code>lsadmi n</code> and <code>badmi n</code> subcommands: <ul style="list-style-type: none"> <li><code>badmi n hstartup</code></li> <li><code>lsadmi n limstartup</code></li> <li><code>lsadmi n resstartup</code></li> </ul> </li> </ul>

## Configuration to enable LSF daemon startup control

### Startup by users other than root (UNIX-only)

The LSF daemon startup control feature is enabled for UNIX hosts by defining the `LSF_STARTUP_USERS` and `LSF_STARTUP_PATH` parameters in the `lsf.sudoers` file. Permissions for `lsf.sudoers` must be set to 600. For Windows hosts, this feature is already enabled at installation when the Platform services admin group is defined.

Configuration file	Parameter and syntax	Default behavior
<code>lsf.sudoers</code>	<code>LSF_STARTUP_USERS=all_admins</code>	<ul style="list-style-type: none"> <li>Enables LSF daemon startup by users other than root when <code>LSF_STARTUP_PATH</code> is also defined.</li> <li>Allows all UNIX users defined as LSF administrators in the file <code>lsf.cluster.cluster_name</code> to start LSF daemons as root by running the <code>lsadm</code> and <code>lsbadmin</code> commands.</li> <li>Not recommended due to the security risk of a non-root LSF administrator adding to the list of administrators in the <code>lsf.cluster.cluster_name</code> file.</li> <li>Not required for Windows hosts because all users with membership in the Platform services admin group can start LSF daemons.</li> </ul>
	<code>LSF_STARTUP_USERS="user_name1 user_name2 ..."</code> <code>LSF_STARTUP_USERS=user_name</code>	<ul style="list-style-type: none"> <li>Enables LSF daemon startup by users other than root when <code>LSF_STARTUP_PATH</code> is also defined.</li> <li>Allows the specified user accounts to start LSF daemons as root by running the <code>lsadm</code> and <code>lsbadmin</code> commands.</li> <li>Specify only cluster administrator accounts; if you add a non-administrative user, the user can start—but not shut down—LSF daemons.</li> <li>Separate multiple user names with a space.</li> <li>For a single user, do not use quotation marks.</li> </ul>

Configuration file	Parameter and syntax	Default behavior
	LSF_STARTUP_PATH= <i>path</i>	<ul style="list-style-type: none"> <li>Enables LSF daemon startup by users other than root when LSF_STARTUP_USERS is also defined.</li> <li>Specifies the directory that contains the LSF daemon binary files.</li> <li>LSF daemons are usually installed in the path specified by the LSF_SERVERDIR parameter defined in the <code>csfrc.lsf</code>, <code>profile.lsf</code>, or <code>lsf.conf</code> files.</li> </ul> <p><b>Important:</b></p> <p>For security reasons, you should move the LSF daemon binary files to a directory other than LSF_SERVERDIR or LSF_BINDIR. The user accounts specified by LSF_STARTUP_USERS can start any binary in the LSF_STARTUP_PATH.</p>

## EGO administrator login bypass

For both UNIX and Windows hosts, you can bypass the EGO administrator login for `res` and `sbatchd` by defining the parameters `LSF_EGO_ADMIN_USER` and `LSF_EGO_ADMIN_PASSWORD` in the `lsf.sudoers` file.

Configuration file	Parameter and syntax	Default behavior
lsf.sudoers	LSF_EGO_ADMIN_USER=Admin	<ul style="list-style-type: none"> <li>Enables a user or script to bypass the EGO administrator login prompt when LSF_EGO_ADMIN_PASSWD is also defined.</li> <li>Applies only to startup of res or sbatchd.</li> <li>Specify the Admin EGO cluster administrator account.</li> </ul>
	LSF_EGO_ADMIN_PASSWD=password	<ul style="list-style-type: none"> <li>Enables a user or script to bypass the EGO administrator login prompt when LSF_EGO_ADMIN_USER is also defined.</li> <li>Applies only to startup of res or sbatchd.</li> <li>Specify the password for the Admin EGO cluster administrator account.</li> </ul>

## LSF daemon startup control behavior

This example illustrates how LSF daemon startup control works when configured for UNIX hosts in a cluster with the following characteristics:

- The cluster contains both UNIX and Windows hosts
- The UNIX account user1 is mapped to the Windows account BUSINESS\user1 by enabling the UNIX/Windows user account mapping feature
- The account BUSINESS\user1 is a member of the Platform services admin group
- In the file `lsf.sudoers`:

```
LSF_STARTUP_USERS="user1 user2 user3"
LSF_STARTUP_PATH=LSF_TOP/7.0/linux2.4-glibc2.3-x86/etc
LSF_EGO_ADMIN_USER=Admin
LSF_EGO_ADMIN_PASSWD=Admin
```

### Note:

You should change the Admin user password immediately after installation using the command `egosh user modify`.




Figure 14: Example of LSF daemon startup control

## Configuration to modify LSF daemon startup control

Not applicable: There are no parameters that modify the behavior of this feature.

## LSF daemon startup control commands

### Commands for submission

Command	Description
N/A	<ul style="list-style-type: none"> <li>This feature does not directly relate to job submission.</li> </ul>

### Commands to monitor

Command	Description
bhost s	<ul style="list-style-type: none"> <li>Displays the host status of all hosts, specific hosts, or specific host groups.</li> </ul>
lsl oad	<ul style="list-style-type: none"> <li>Displays host status and load information.</li> </ul>

## Commands to control

Command	Description
<code>badmi n hstartup</code>	<ul style="list-style-type: none"> <li>Starts the <code>sbatchd</code> daemon on specific hosts or all hosts. Only root and users listed in the <code>LSF_STARTUP_USERS</code> parameter can successfully run this command.</li> </ul>
<code>lsadmi n limstartup</code>	<ul style="list-style-type: none"> <li>Starts the <code>lim</code> daemon on specific hosts or all hosts in the cluster. Only root and users listed in the <code>LSF_STARTUP_USERS</code> parameter can successfully run this command.</li> </ul>
<code>lsadmi n resstartup</code>	<ul style="list-style-type: none"> <li>Starts the <code>res</code> daemon on specific hosts or all hosts in the cluster. Only root and users listed in the <code>LSF_STARTUP_USERS</code> parameter can successfully run this command.</li> </ul>

## Commands to display configuration

Command	Description
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>Displays all configured parameters and their values set in <code>lsf.conf</code> or <code>ego.conf</code> that affect <code>mbatchd</code> and <code>sbatchd</code>. Use a text editor to view other parameters in the <code>lsf.conf</code> or <code>ego.conf</code> configuration files.</li> <li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

Use a text editor to view the `lsf.sudoers` configuration file.

# Feature: Pre-execution and post-execution processing

The pre- and post-execution processing feature provides a way to run commands on the execution host prior to and after completion of LSF jobs. Use pre-execution commands to set up an execution host with the required directories, files, software licenses, environment, and user permissions. Use post-execution commands to define post-job processing such as cleaning up job files or transferring job output.

## Contents

- About pre- and post-execution processing
- Scope
- Configuration to enable pre- and post-execution processing
- Pre- and post-execution processing behavior
- Configuration to modify pre- and post-execution processing
- Pre- and post-execution processing commands

## About pre- and post-execution processing

You can use the pre- and post-execution processing feature to run commands before a batch job starts or after it finishes. Typical uses of this feature include the following:


- Reserving resources such as tape drives and other devices not directly configurable in LSF
- Making job-starting decisions in addition to those directly supported by LSF
- Creating and deleting scratch directories for a job
- Customizing scheduling based on the exit code of a pre-execution command
- Checking availability of software licenses
- Assigning jobs to run on specific processors on SMP machines
- Transferring data files needed for job execution
- Modifying system configuration files before and after job execution
- Using a post-execution command to clean up a state left by the pre-execution command or the job

Pre-execution and post-execution commands can be defined at the queue, application, and job levels.

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for %J (*job\_ID*) and %I (*index\_ID*).


When `JOB_INCLUDE_POSTPROC` is defined in an application profile, a job is considered in RUN state while the job is in post exec stage (which is DONE state for regular jobs). When the job is also resizable, job grow requests are ignored. However job shrink requests can be processed. For either case, LSF does not invoke the job resized notification command.

## Default behavior (feature not enabled)



## With pre- and post-execution processing enabled at the queue or application level

The following example illustrates how pre- and post-execution processing works for setting the environment prior to job execution and for transferring resulting files after the job runs.



Any executable command line can serve as a pre-execution or post-execution command. By default, the commands run under the same user account, environment, home directory, and working directory as the job. For parallel jobs, the commands run on the first execution host.

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX</li> <li>• Windows</li> <li>• A mix of UNIX and Windows hosts</li> </ul>

Applicability	Details
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> <li>• On a Windows Server 2003, x64 Edition platform, users must have read and execute privileges for cmd. exe.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>• Applies to batch jobs only (jobs submitted using the bsub command)</li> </ul>

## Configuration to enable pre- and post-execution processing

The pre- and post-execution processing feature is enabled by defining at least one of the parameters PRE\_EXEC or POST\_EXEC at the application or queue level, or by using the -E option of the bsub command to specify a pre-execution command. In some situations, specifying a queue-level or application-level pre-execution command can have advantages over requiring users to use bsub -E. For example, license checking can be set up at the queue or application level so that users do not have to enter a pre-execution command every time they submit a job.

Configuration file	Parameter and syntax	Behavior
l sb. queues	PRE_EXEC= <i>command</i>	<ul style="list-style-type: none"> <li>• Enables pre-execution processing at the queue level.</li> <li>• The pre-execution command runs on the execution host before the job starts.</li> <li>• If the PRE_EXEC command exits with a non-zero exit code, LSF requeues the job to the front of the queue.</li> <li>• The PRE_EXEC command uses the same environment variable values as the job.</li> </ul>
	POST_EXEC= <i>command</i>	<ul style="list-style-type: none"> <li>• Enables post-execution processing at the queue level.</li> <li>• The POST_EXEC command uses the same environment variable values as the job.</li> <li>• The post-execution command for the queue remains associated with the job. The original post-execution command runs even if the job is requeued or if the post-execution command for the queue is changed after job submission.</li> <li>• Before the post-execution command runs, LSB_JOBEXIT_STAT is set to the exit status of the job. The success or failure of the post-execution command has no effect on LSB_JOBEXIT_STAT.</li> <li>• The post-execution command runs after the job finishes, even if the job fails.</li> <li>• Specify the environment variable \$USER_POSTEXEC to allow UNIX users to define their own post-execution commands.</li> </ul>

Configuration file	Parameter and syntax	Behavior
lsb. applications	PRE_EXEC= <i>command</i>	<ul style="list-style-type: none"> <li>Enables pre-execution processing at the application level.</li> <li>The pre-execution command runs on the execution host before the job starts.</li> <li>If the PRE_EXEC command exits with a non-zero exit code, LSF requeues the job to the front of the queue.</li> <li>The PRE_EXEC command uses the same environment variable values as the job.</li> </ul>
	POST_EXEC= <i>command</i>	<ul style="list-style-type: none"> <li>Enables post-execution processing at the application level.</li> <li>The POST_EXEC command uses the same environment variable values as the job.</li> <li>The post-execution command for the application profile remains associated with the job. The original post-execution command runs even if the job is moved to a different application profile or is requeued, or if the post-execution command for the original application profile is changed after job submission.</li> <li>Before the post-execution command runs, LSB_JOBEXIT_STAT is set to the exit status of the job. The success or failure of the post-execution command has no effect on LSB_JOBEXIT_STAT.</li> <li>The post-execution command runs after the job finishes, even if the job fails.</li> <li>Specify the environment variable \$USER_POSTEXEC to allow UNIX users to define their own post-execution commands.</li> </ul>

## Pre- and post-execution processing behavior

Pre- and post-execution processing applies to both UNIX and Windows hosts.

Host type	Environment
UNIX	<ul style="list-style-type: none"> <li>The pre- and post-execution commands run in the <code>/tmp</code> directory under <code>/bin/sh -c</code>, which allows the use of shell features in the commands. The following example shows valid configuration lines: <code>PRE_EXEC= /usr/share/l sf/mi sc/testq_pre &gt;&gt; /tmp/pre.out POST_EXEC= /usr/share/l sf/mi sc/testq_post   grep -v "Testing..."</code></li> <li>LSF sets the PATH environment variable to <code>PATH=' /bin /usr/bin /sbin /usr/sbin'</code></li> <li>The stdin, stdout, and stderr are set to <code>/dev/null</code></li> </ul>
Windows	<ul style="list-style-type: none"> <li>The pre- and post-execution commands run under <code>cmd. exe /c</code></li> <li>The standard input, standard output, and standard error are set to NULL</li> <li>The PATH is determined by the setup of the LSF Service</li> </ul>

### Note:

If the pre-execution or post-execution command is not in your usual execution path, you must specify the full path name of the command.

## Order of command execution

Pre-execution commands run in the following order:

1. The queue-level command
2. The application-level or job-level command. If you specify a command at both the application and job levels, the job-level command overrides the application-level command; the application-level command is ignored.

If a pre-execution command is specified at the ...	Then the commands execute in the order of ...
Queue, application, and job levels	<ol style="list-style-type: none"> <li>1. Queue level</li> <li>2. Job level</li> </ol>
Queue and application levels	<ol style="list-style-type: none"> <li>1. Queue level</li> <li>2. Application level</li> </ol>
Queue and job levels	<ol style="list-style-type: none"> <li>1. Queue level</li> <li>2. Job level</li> </ol>
Application and job levels	<ol style="list-style-type: none"> <li>1. Job level</li> </ol>

Post-execution commands run in the following order:

1. The application-level command
2. The queue-level command
3. The job-level command

If both application-level (POST\_EXEC in lsb. applications) and job-level post-execution commands are specified, job level post-execution overrides application-level post-execution commands.

If a post-execution command is specified at the ...	Then the commands execute in the order of ...
Queue, application, and job levels	<ol style="list-style-type: none"> <li>1. Job level</li> <li>2. Queue level</li> </ol>
Queue and application levels	<ol style="list-style-type: none"> <li>1. Application level</li> <li>2. Queue level</li> </ol>
Queue and job levels	<ol style="list-style-type: none"> <li>1. Job level</li> <li>2. Queue level</li> </ol>

## Pre-execution command behavior

A pre-execution command returns information to LSF by means of the exit status. LSF holds the job in the queue until the specified pre-execution command returns an exit code of zero (0). If the pre-execution command exits with a non-zero value, the job pends until LSF tries

again to dispatch it. While the job remains in the PENDING state, LSF dispatches other jobs to the execution host.

If the pre-execution command exits with a value of 99, the job exits without pending. This allows you to cancel the job if the pre-execution command fails.

You must ensure that the pre-execution command runs without side effects; that is, you should define a pre-execution command that does not interfere with the job itself. For example, if you use the pre-execution command to reserve a resource, you cannot also reserve the same resource as part of the job submission.

LSF users can specify a pre-execution command at job submission. LSF first finds a suitable host on which to run the job and then runs the pre-execution command on that host. If the pre-execution command runs successfully and returns an exit code of zero, LSF runs the job.

## Post-execution command behavior

A post-execution command runs after the job finishes, regardless of the exit state of the job. Once a post-execution command is associated with a job, that command runs even if the job fails. You cannot configure the post-execution command to run only under certain conditions.

The resource usage of post-execution processing is not included in the job resource usage calculation, and post-execution command exit codes are not reported to LSF.

If `POST_EXEC=$USER_POSTEXEC` in either `l sb. appl i cat i ons` or `l sb. queues`, UNIX users can define their own post-execution commands:

```
setenv USER_POSTEXEC /path_name
```

where the path name for the post-execution command is an absolute path.

If <code>POST_EXEC=\$USER_POSTEXEC</code> and ...	Then ...
The user defines the <code>USER_POSTEXEC</code> environment variable	<ul style="list-style-type: none"> <li>LSF runs the post-execution command defined by the environment variable <code>USER_POSTEXEC</code></li> <li>After the user-defined command runs, LSF reports successful completion of post-execution processing</li> <li>If the user-defined command fails, LSF reports a failure of post-execution processing</li> </ul>
The user does not define the <code>USER_POSTEXEC</code> environment variable	<ul style="list-style-type: none"> <li>LSF reports successful post-execution processing without actually running a post-execution command</li> </ul>

### Important:

Do not allow users to specify a post-execution command when the pre- and post-execution commands are set to run under the root account.

## Configuration to modify pre- and post-execution processing

Configuration parameters modify various aspects of pre- and post-execution processing behavior by:

- Preventing a new job from starting until post-execution processing has finished
- Controlling the length of time post-execution processing can run
- Specifying a user account under which the pre- and post-execution commands run

- Controlling how many times pre-execution retries

## Configuration to modify when new jobs can start

When a job finishes, sbatchd reports a job finish status of DONE or EXIT to mbatchd. This causes LSF to release resources associated with the job, allowing new jobs to start on the execution host before post-execution processing from a previous job has finished.

In some cases, you might want to prevent the overlap of a new job with post-execution processing. Preventing a new job from starting prior to completion of post-execution processing can be configured at the application level or at the job level.

At the job level, the bsub -w option allows you to specify job dependencies; the keywords post\_done and post\_err cause LSF to wait for completion of post-execution processing before starting another job.

At the application level:

File	Parameter and syntax	Description
l sb. applications l sb. params	JOB_INCLUDE_POSTPROC=Y	<ul style="list-style-type: none"> <li>• Enables completion of post-execution processing before LSF reports a job finish status of DONE or EXIT</li> <li>• Prevents a new job from starting on a host until post-execution processing is finished on that host</li> </ul>

- sbatchd sends both job finish status (DONE or EXIT) and post-execution processing status (POST\_DONE or POST\_ERR) to mbatchd at the same time
- The job remains in the RUN state and holds its job slot until post-execution processing has finished
- Job requeue happens (if required) after completion of post-execution processing, not when the job itself finishes
- For job history and job accounting, the job CPU and run times include the post-execution processing CPU and run times
- The job control commands bst op, bkill, and bresume have no effect during post-execution processing
- If a host becomes unavailable during post-execution processing for a rerunnable job, mbatchd sees the job as still in the RUN state and reruns the job
- LSF does not preempt jobs during post-execution processing

## Configuration to modify the post-execution processing time

Controlling the length of time post-execution processing can run is configured at the application level.

File	Parameter and syntax	Description
l sb. appl i cat i ons l sb. par ams	JOB_POSTPROC_TIMEOUT= <i>minutes</i>	<ul style="list-style-type: none"> <li>Specifies the length of time, in minutes, that post-execution processing can run.</li> <li>The specified value must be greater than zero.</li> <li>If post-execution processing takes longer than the specified value, sbatchd reports post-execution failure—a status of POST_ERR—and kills the process group of the job's post-execution processes. This kills the parent process only.</li> <li>If JOB_INCLUDE_POSTPROC=Y and sbatchd kills the post-execution process group, post-execution processing CPU time is set to zero, and the job's CPU time does not include post-execution CPU time.</li> </ul>

## Configuration to modify the pre- and post-execution processing user account

Specifying a user account under which the pre- and post-execution commands run is configured at the system level. By default, both the pre- and post-execution commands run under the account of the user who submits the job.

File	Parameter and syntax	Description
l sf. sudoers	LSB_PRE_POST_EXEC_USER= <i>user_name</i>	<ul style="list-style-type: none"> <li>Specifies the user account under which pre- and post-execution commands run (UNIX only)</li> <li>This parameter applies only to pre- and post-execution commands configured at the application and queue levels; pre-execution commands defined at the job level with bsub -E run under the account of the user who submits the job</li> <li>If the pre-execution or post-execution commands perform privileged operations that require root permissions on UNIX hosts, specify a value of root</li> <li>You must edit the l sf. sudoers file on all UNIX hosts within the cluster and specify the same user account</li> </ul>

## Configuration to control how many times pre-execution retries

By default, if job pre-execution fails, LSF retries the job automatically. The job remains in the queue and pre-execution is retried 5 times by default, to minimize any impact to performance and throughput.

Limiting the number of times LSF retries job pre-execution is configured cluster-wide (l sb. par ams), at the queue level (l sb. queues), and at the application level (l sb. appl i cat i ons). pre-execution retry in l sb. appl i cat i ons overrides l sb. queues, and l sb. queues overrides l sb. par ams configuration.

Configuration file	Parameter and syntax	Behavior
l sb. params	LOCAL_MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the local cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is unlimited.</p>
	MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>
	REMOTE_MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> </ul> <p>Equivalent to MAX_PREEEXEC_RETRY</p> <ul style="list-style-type: none"> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>
l sb. queues	LOCAL_MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the local cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is unlimited.</p>
	MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>
	REMOTE_MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> </ul> <p>Equivalent to MAX_PREEEXEC_RETRY</p> <ul style="list-style-type: none"> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>
l sb. applications	LOCAL_MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the local cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is unlimited.</p>

Configuration file	Parameter and syntax	Behavior
	MAX_PREEEXEC_RETRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>
	REMOTE_MAX_PREEEXEC_R ENTRY= <i>integer</i>	<ul style="list-style-type: none"> <li>Controls the maximum number of times to attempt the pre-execution command of a job on the remote cluster.</li> </ul> <p>Equivalent to MAX_PREEEXEC_RETRY</p> <ul style="list-style-type: none"> <li>Specify an integer greater than 0</li> </ul> <p>By default, the number of retries is 5.</p>

When pre-execution retry is configured, if a job pre-execution fails and exits with non-zero value, the number of pre-exec retries is set to 1. When the pre-exec retry limit is reached, the job is suspended with PSUSP status.

The number of times that pre-execution is retried includes queue-level, application-level, and job-level pre-execution command specifications. When pre-execution retry is configured, a job will be suspended when the sum of its queue-level pre-exec retry times + application-level pre-exec retry times is greater than the value of the pre-execution retry parameter or if the sum of its queue-level pre-exec retry times + job-level pre-exec retry times is greater than the value of the pre-execution retry parameter.

The pre-execution retry limit is recovered when LSF is restarted and reconfigured. LSF replays the pre-execution retry limit in the PRE\_EXEC\_START or JOB\_STATUS events in `lsb.events`.

## Pre- and post-execution processing commands

### Commands for submission

The `bsub -E` option specifies a pre-execution command. Post-execution commands cannot be specified using `bsub`; post-execution processing can only be defined at the queue and application levels.

The `bsub -w` option allows you to specify job dependencies that cause LSF to wait for completion of post-execution processing before starting another job.

Command	Description
<code>bsub -E <i>command</i></code>	<ul style="list-style-type: none"> <li>Defines the pre-execution command at the job level.</li> </ul>
<code>bsub -w 'post_done(job_id   "job_name")'</code>	<ul style="list-style-type: none"> <li>Specifies the job dependency condition required to prevent a new job from starting on a host until post-execution processing on that host has finished without errors.</li> </ul>
<code>bsub -w 'post_err(job_id   "job_name")'</code>	<ul style="list-style-type: none"> <li>Specifies the job dependency condition required to prevent a new job from starting on a host until post-execution processing on that host has exited with errors.</li> </ul>

## Commands to monitor

Command	Description
<code>bhist</code> <code>bhist -l</code>	<ul style="list-style-type: none"> <li>Displays the host status of all hosts, specific hosts, or specific host groups, including the POST_DONE and POST_ERR states, if the user submitted the job with the <code>-w</code> option of <code>bsub</code>.</li> <li>The CPU and run times shown do not include resource usage for post-execution processing unless the parameter <code>JOB_INCLUDE_POSTPROC</code> is defined in <code>lsb. applications</code> or <code>lsb. params</code>.</li> <li>Displays the job exit code and reason if the pre-exec retry limit is exceeded.</li> </ul>
<code>bjobs -l</code>	<ul style="list-style-type: none"> <li>Displays information about pending, running, and suspended jobs. During post-execution processing, the job status will be RUN if the parameter <code>JOB_INCLUDE_POSTPROC</code> is defined in <code>lsb. applications</code> or <code>lsb. params</code>.</li> <li>The resource usage shown does not include resource usage for post-execution processing.</li> <li>Displays the job exit code and reason if the pre-exec retry limit is exceeded.</li> </ul>
<code>bacct</code>	<ul style="list-style-type: none"> <li>Displays accounting statistics for finished jobs.</li> <li>The CPU and run times shown do not include resource usage for post-execution processing, unless the parameter <code>JOB_INCLUDE_POSTPROC</code> is defined in <code>lsb. applications</code> or <code>lsb. params</code>.</li> </ul>

## Commands to control

Command	Description
<code>bmod -E <i>command</i></code>	<ul style="list-style-type: none"> <li>Changes the pre-execution command at the job level.</li> </ul>
<code>bmod -w 'post_done(job_id   "job_name")'</code>	<ul style="list-style-type: none"> <li>Specifies the job dependency condition required to prevent a new job from starting on a host until post-execution processing on that host has finished without errors.</li> </ul>
<code>bmod -w 'post_err(job_id   "job_name")'</code>	<ul style="list-style-type: none"> <li>Specifies the job dependency condition required to prevent a new job from starting on a host until post-execution processing on that host has exited with errors.</li> </ul>

## Commands to display configuration

Command	Description
<code>bapp -l</code>	<ul style="list-style-type: none"> <li>Displays information about application profiles configured in <code>lsb. applications</code>, including the values defined for <code>PRE_EXEC</code>, <code>POST_EXEC</code>, <code>JOB_INCLUDE_POSTPROC</code>, <code>JOB_POSTPROC_TIMEOUT</code>, <code>LOCAL_MAX_PREEEXEC_RETRY</code>, <code>MAX_PREEEXEC_RETRY</code>, and <code>REMOTE_MAX_PREEEXEC_RETRY</code>.</li> </ul>
<code>bparams</code>	<ul style="list-style-type: none"> <li>Displays the value of parameters defined in <code>lsb. params</code>, including the values defined for <code>LOCAL_MAX_PREEEXEC_RETRY</code>, <code>MAX_PREEEXEC_RETRY</code>, and <code>REMOTE_MAX_PREEEXEC_RETRY</code>.</li> </ul>

---

Command	Description
bqueues -l	<ul style="list-style-type: none"><li>Displays information about queues configured in <code>lsf.queues</code>, including the values defined for <code>PRE_EXEC</code> and <code>POST_EXEC</code>, <code>LOCAL_MAX_PREEEXEC_RETRY</code>, <code>MAX_PREEEXEC_RETRY</code>, and <code>REMOTE_MAX_PREEEXEC_RETRY</code>.</li></ul>

---

Use a text editor to view the `lsf.sudoers` configuration file.

# Feature: Preemptive scheduling

The preemptive scheduling feature allows a pending high-priority job to preempt a running job of lower priority. The lower-priority job is suspended and is resumed as soon as possible. Use preemptive scheduling if you have long-running, low-priority jobs causing high-priority jobs to wait an unacceptably long time.

## Contents

- About preemptive scheduling
- Scope
- Configuration to enable preemptive scheduling
- Preemptive scheduling behavior
- Configuration to modify preemptive scheduling behavior
- Preemptive scheduling commands

## About preemptive scheduling

Preemptive scheduling takes effect when two jobs compete for the same job slots. If a high-priority job is pending, LSF can suspend a lower-priority job that is running, and then start the high-priority job instead. For this to happen, the high-priority job must be pending in a *preemptive queue* (a queue that can preempt other queues), or the low-priority job must belong to a *preemptable queue* (a queue that can be preempted by other queues).

If multiple slots are required, LSF can preempt multiple jobs until sufficient slots are available. For example, one or more jobs can be preempted for a job that needs multiple job slots.

A preempted job is resumed as soon as more job slots become available; it does not necessarily have to wait for the preempting job to finish.

Preemptive queue	Jobs in a preemptive queue can preempt jobs in any queue of lower priority, even if the lower-priority queues are not specified as preemptable.
------------------	---

Preemptive queues are more aggressive at scheduling jobs because a slot that is not available to a low-priority queue may be available by preemption to a high-priority queue.

Preemptable queue	Jobs in a preemptable queue can be preempted by jobs from any queue of a higher priority, even if the higher-priority queues are not specified as preemptive.
-------------------	---

When multiple preemptable jobs exist (low-priority jobs holding the required slots), and preemption occurs, LSF preempts a job from the least-loaded host.

## Resizable jobs

Resize allocation requests are not able take advantage of the queue-based preemption mechanism to preempt other jobs. However, regular pending jobs are still able to preempt running resizable jobs, even while they have a resize request pending. When a resizable job is preempted and goes to the SSUSP state, its resize request remains pending and LSF stops scheduling it until it returns back to RUN state.


- New pending allocation requests cannot make use of preemption policy to get slots from other running or suspended jobs.
- Once a resize decision has been made, LSF updates its job counters to be reflected in future preemption calculations. For instance, resizing a running preemptable job from 2 slots to 4 slots, makes 4 preemptable slots for high priority pending jobs.
- If a job is suspended, LSF stops allocating resources to a pending resize request.
- When a preemption decision is made, if job has pending resize request and scheduler already has made an allocation decision for this request, LSF cancels the allocation decision.
- If a preemption decision is made while a job resize notification command is running, LSF prevents the suspend signal from reaching the job.

## Scope


Preemptive scheduling does not apply to jobs that have been forced to run or backfill and exclusive jobs.

Limitations	Description
Exclusive compute units	Jobs requesting exclusive use of compute units in the resource requirements cannot preempt other jobs. Jobs using compute units exclusively cannot be preempted.


## Default behavior (preemptive scheduling not enabled)



## With preemptive scheduling enabled (preemptive queue)



## With preemptive scheduling enabled (preemptable queue)



## Configuration to enable preemptive scheduling

The preemptive scheduling feature is enabled by defining at least one queue as preemptive or preemptable, using the `PREEMPTION` parameter in the `lsb.queues` file. Preemption does not actually occur until at least one queue is assigned a higher relative priority than another queue, using the `PRIORITY` parameter, which is also set in the `lsb.queues` file.

Both `PREEMPTION` and `PRIORITY` are used to determine which queues can preempt other queues, either by establishing relative priority of queues or by specifically defining preemptive properties for a queue.

Configuration file	Parameter and syntax	Default behavior
l sb. queues	PREEMPTION=PREEMPTIVE	<ul style="list-style-type: none"> <li>Enables preemptive scheduling</li> <li>Jobs in this queue can preempt jobs in any queue of lower priority, even if the lower-priority queue is not specified as preemptable</li> </ul>
	PREEMPTION=PREEMPTABLE	<ul style="list-style-type: none"> <li>Enables preemptive scheduling</li> <li>Jobs in this queue can be preempted by jobs from any queue of higher priority, even if the higher-priority queue is not specified as preemptive</li> </ul>
	PRIORITY= <i>integer</i>	<ul style="list-style-type: none"> <li>Sets the priority for this queue relative to all other queues</li> <li>The larger the number, the higher the priority—a queue with PRIORITY=99 has a higher priority than a queue with PRIORITY=1</li> </ul>

## Preemptive scheduling behavior

Preemptive scheduling is based primarily on parameters specified at the queue level: some queues are eligible for preemption, others are not. Once a hierarchy of queues has been established, other factors determine which jobs from a queue should be preempted.

There are three ways to establish which queues should be preempted:

- Based on queue priority—the PREEMPTION parameter defines a queue as preemptive or preemptable and preemption is based on queue priority, where jobs from higher-priority queues can preempt jobs from lower-priority queues
- Based on a preferred order—the PREEMPTION parameter defines queues that can preempt other queues, in a preferred order
- Explicitly, by specific queues—the PREEMPTION parameter defines queues that can be preempted, and by which queues

When ...	The behavior is ...
Preemption is not enabled—no queue is defined as preemptable, and no queue is defined as preemptive	<ul style="list-style-type: none"> <li>High-priority jobs do not preempt jobs that are already running</li> </ul>
A queue is defined as preemptable, but no specific queues are listed that can preempt it	<ul style="list-style-type: none"> <li>Jobs from this queue can be preempted by jobs from any queue with a higher value for priority</li> </ul>
A queue is defined as preemptable, and one or more queues are specified that can preempt it	<ul style="list-style-type: none"> <li>Jobs from this queue can be preempted only by jobs from the specified queues</li> </ul>
A queue is defined as preemptive, but no specific queues are listed that it can preempt	<ul style="list-style-type: none"> <li>Jobs from this queue preempt jobs from all queues with a lower value for priority</li> <li>Jobs are preempted from the least-loaded host</li> </ul>

When ...	The behavior is ...
A queue is defined as preemptive, and one or more specific queues are listed that it can preempt, but no queue preference is specified	<ul style="list-style-type: none"> <li>Jobs from this queue preempt jobs from any queue in the specified list</li> <li>Jobs are preempted on the least-loaded host first</li> </ul>
A queue is defined as preemptive, and one or more queues have a preference number specified, indicating a preferred order of preemption	<ul style="list-style-type: none"> <li>Queues with a preference number are preferred for preemption over queues without a preference number</li> <li>Queues with a higher preference number are preferred for preemption over queues with a lower preference number</li> <li>For queues that have the same preference number, the queue with lowest priority is preferred for preemption over queues with higher priority</li> <li>For queues without a preference number, the queue with lower priority is preferred for preemption over the queue with higher priority</li> </ul>
A queue is defined as preemptive, or a queue is defined as preemptable, and preemption of jobs with the shortest run time is configured	<ul style="list-style-type: none"> <li>A queue from which to preempt a job is determined based on other parameters as shown above</li> <li>The job that has been running for the shortest period of time is preempted</li> </ul>
A queue is defined as preemptive, or a queue is defined as preemptable, and preemption of jobs that will finish within a certain time period is prevented	<ul style="list-style-type: none"> <li>A queue from which to preempt a job is determined based on other parameters as shown above</li> <li>A job that has a run limit or a run time specified and that will not finish within the specified time period is preempted</li> </ul>
A queue is defined as preemptive, or a queue is defined as preemptable, and preemption of jobs with the specified run time is prevented	<ul style="list-style-type: none"> <li>A queue from which to preempt a job is determined based on other parameters as shown above</li> <li>The job that has been running for less than the specified period of time is preempted</li> </ul>

## Case study: Three queues with varying priority

Consider the case where three queues are defined as follows:

Queue A has the highest relative priority, with a value of 99

Queue B is both preemptive and preemptable, and has a relative priority of 10

Queue C has the lowest relative priority, with the default value of 1

The queues can preempt as follows:

- A can preempt B because B is preemptable and B has a lower priority than A
- B can preempt C because B is preemptive and C has a lower priority than B
- A cannot preempt C, even though A has a higher priority than C, because A is not preemptive, nor is C preemptable

## Calculation of job slots in use

The number of job slots in use determines whether preemptive jobs can start. The method in which the number of job slots in use is calculated can be configured to ensure that a preemptive job can start. When a job is preempted, it is suspended. If the suspended job still counts towards the total number of jobs allowed in the system, based on the limits imposed in the

In `lsb. resources` file, suspending the job may not be enough to allow the preemptive job to run.

The `PREEMPT_FOR` parameter is used to change the calculation of job slot usage, ignoring suspended jobs in the calculation. This ensures that if a limit is met, the preempting job can actually run.

When ...	The effect on the calculation of job slots used is ...
Preemption is not enabled	<ul style="list-style-type: none"> <li>Job slot limits are enforced based on the number of job slots taken by both running and suspended jobs.</li> <li>Job slot limits specified at the queue level are enforced for both running and suspended jobs.</li> </ul>
Preemption is enabled	<ul style="list-style-type: none"> <li>The total number of jobs at both the host and individual user level is not limited by the number of suspended jobs—only running jobs are considered.</li> <li>The number of running jobs never exceeds the job slot limits. If starting a preemptive job violates a job slot limit, a lower-priority job is suspended to run the preemptive job. If, however, a job slot limit is still violated (i.e. the suspended job still counts in the calculation of job slots in use), the preemptive job still cannot start.</li> <li>Job slot limits specified at the queue level are always enforced for both running and suspended jobs.</li> <li>When preemptive scheduling is enabled, suspended jobs never count against the total job slot limit for individual users.</li> </ul>
Preemption is enabled, and <code>PREEMPT_FOR=GROUP_JLP</code>	<ul style="list-style-type: none"> <li>Only running jobs are counted when calculating the per-processor job slots in use for a user group, and comparing the result with the limit specified at the user level.</li> </ul>
Preemption is enabled, and <code>PREEMPT_FOR=GROUP_MAX</code>	<ul style="list-style-type: none"> <li>Only running jobs are counted when calculating the job slots in use for this user group, and comparing the result with the limit specified at the user level.</li> </ul>
Preemption is enabled, and <code>PREEMPT_FOR=HOST_JLU</code>	<ul style="list-style-type: none"> <li>Only running jobs are counted when calculating the total job slots in use for a user group, and comparing the result with the limit specified at the host level. Suspended jobs do not count against the limit for individual users.</li> </ul>
Preemption is enabled, and <code>PREEMPT_FOR=USER_JLP</code>	<ul style="list-style-type: none"> <li>Only running jobs are counted when calculating the per-processor job slots in use for an individual user, and comparing the result with the limit specified at the user level.</li> </ul>

## Preemption of backfill jobs

With preemption of backfill jobs enabled (`PREEMPT_JOBTYPE=BACKFILL` in `lsb.params`), LSF maintains the priority of jobs with resource or slot reservations by preventing lower-priority jobs that preempt backfill jobs from "stealing" resources from jobs with reservations. Only jobs from queues with a higher priority than queues that define resource or slot reservations can preempt backfill jobs. For example,

If ...	Is configured ...	And a priority of ...	The behavior is ...
queueR	With a resource or slot reservation	80	Jobs in this queue reserve resources. If backfill scheduling is enabled, backfill jobs with a defined run limit can use the resources.
queueB	As a preemptable backfill queue	50	Jobs in queueB with a defined run limit use job slots reserved by jobs in queueR.
queueP	As a preemptive queue	75	Jobs in this queue do not necessarily have a run limit. LSF prevents jobs from this queue from preempting backfill jobs because queueP has a lower priority than queue R.

To guarantee a minimum run time for interruptible backfill jobs, LSF suspends them upon preemption. To change this behavior so that LSF terminates interruptible backfill jobs upon preemption, you must define the parameter `TERMINATE_WHEN=PREEMPT` in `l sb. queues`.

## Configuration to modify preemptive scheduling behavior

There are configuration parameters that modify various aspects of preemptive scheduling behavior, by

- Modifying the selection of the queue to preempt jobs from
- Modifying the selection of the job to preempt
- Modifying preemption of backfill and exclusive jobs
- Modifying the way job slot limits are calculated
- Modifying the number of jobs to preempt for a parallel job
- Modifying the control action applied to preempted jobs
- Control how many times a job can be preempted

## Configuration to modify selection of queue to preempt

File	Parameter	Syntax and description
l sb. queues	PREEMPTION	PREEMPTION=PREEMPTIVE[ <i>low_queue+pref ...</i> ]
		<ul style="list-style-type: none"> <li>• Jobs in this queue can preempt running jobs from the specified queues, starting with jobs in the queue with the highest value set for preference</li> </ul>
	PREEMPTION=PREEMPTABLE[ <i>hi_queue ...</i> ]	
		<ul style="list-style-type: none"> <li>• Jobs in this queue can be preempted by jobs from the specified queues</li> </ul>
	PRIORITY= <i>integer</i>	<ul style="list-style-type: none"> <li>• Sets the priority for this queue relative to all other queues</li> <li>• The higher the priority value, the more likely it is that jobs from this queue may preempt jobs from other queues, and the less likely it is for jobs from this queue to be preempted by jobs from other queues</li> </ul>

## Configuration to modify selection of job to preempt

Files	Parameter	Syntax and description
l sb. params	PREEMPT_FOR	PREEMPT_FOR=LEAST_RUN_TIME
l sb. appl i cat i on s		<ul style="list-style-type: none"> <li>Preempts the job that has been running for the shortest time</li> </ul>
	NO_PREEMPT_RUN_TIME	NO_PREEMPT_RUN_TIME=% <ul style="list-style-type: none"> <li>Prevents preemption of jobs that have been running for the specified percentage of minutes, or longer</li> <li>If NO_PREEMPT_RUN_TIME is specified as a percentage, the job cannot be preempted after running the percentage of the job duration. For example, if the job run limit is 60 minutes and NO_PREEMPT_RUN_TIME=50%, the job cannot be preempted after it running 30 minutes or longer.</li> <li>If you specify percentage for NO_PREEMPT_RUN_TIME, requires a run time (bsub - We or RUNTIME in l sb. appl i cat i ons), or run limit to be specified for the job (bsub - W, or RUNLIMIT in l sb. queues, or RUNLIMIT in l sb. appl i cat i ons)</li> </ul>
	NO_PREEMPT_FINISH_T IME	NO_PREEMPT_FINISH_TIME=% <ul style="list-style-type: none"> <li>Prevents preemption of jobs that will finish within the specified percentage of minutes</li> <li>If NO_PREEMPT_FINISH_TIME is specified as a percentage, the job cannot be preempted if the job finishes within the percentage of the job duration. For example, if the job run limit is 60 minutes and NO_PREEMPT_FINISH_TIME=10%, the job cannot be preempted after it running 54 minutes or longer.</li> <li>If you specify percentage for NO_PREEMPT_FINISH_TIME, requires a run time (bsub - We or RUNTIME in l sb. appl i cat i ons), or run limit to be specified for the job (bsub - W, or RUNLIMIT in l sb. queues, or RUNLIMIT in l sb. appl i cat i ons)</li> </ul>

## Configuration to modify preemption of backfill and exclusive jobs

File	Parameter	Syntax and description
lsf.param s	PREEMPT_JOBTYPE	PREEMPT_JOBTYPE=BACKFILL <ul style="list-style-type: none"> <li>Enables preemption of backfill jobs.</li> <li>Requires the line PREEMPTION=PREEMPTABLE in the queue definition.</li> <li>Only jobs from queues with a higher priority than queues that define resource or slot reservations can preempt jobs from backfill queues.</li> </ul>
		PREEMPT_JOBTYPE=EXCLUSIVE <ul style="list-style-type: none"> <li>Enables preemption of and preemption by exclusive jobs.</li> <li>Requires the line PREEMPTION=PREEMPTABLE or PREEMPTION=PREEMPTIVE in the queue definition.</li> <li>Requires the definition of LSB_DISABLE_LIMLOCK_EXCL in lsf.conf.</li> </ul>
		PREEMPT_JOBTYPE=EXCLUSIVE BACKFILL <ul style="list-style-type: none"> <li>Enables preemption of exclusive jobs, backfill jobs, or both.</li> </ul>
lsf.conf	LSB_DISABLE_LIMLOCK_EXCL	LSB_DISABLE_LIMLOCK_EXCL=y <ul style="list-style-type: none"> <li>Enables preemption of exclusive jobs.</li> <li>For a host running an exclusive job:               <ul style="list-style-type: none"> <li>lsl oad displays the host status ok.</li> <li>bhost s displays the host status closed.</li> <li>Users can run tasks on the host using lsr un or l sgr un. To prevent users from running tasks during execution of an exclusive job, the parameter LSF_DISABLE_LSRUN=y must be defined in l sf . conf .</li> </ul> </li> <li>Changing this parameter requires a restart of all sbatchds in the cluster (badmi n hrest art). Do not change this parameter while exclusive jobs are running.</li> </ul>

## Configuration to modify how job slot usage is calculated

File	Parameter	Syntax and description
l sb. params	PREEMPT_FOR	PREEMPT_FOR=GROUP_JLP
	R	<ul style="list-style-type: none"> <li>Counts only running jobs when evaluating if a user group is approaching its per-processor job slot limit (SLOTS_PER_PROCESSOR, USERS, and PER_HOST=all in the l sb. resources file), ignoring suspended jobs</li> </ul>
		PREEMPT_FOR=GROUP_MAX
		<ul style="list-style-type: none"> <li>Counts only running jobs when evaluating if a user group is approaching its total job slot limit (SLOTS, PER_USER=all, and HOSTS in the l sb. resources file), ignoring suspended jobs</li> </ul>
		PREEMPT_FOR=HOST_JLU
		<ul style="list-style-type: none"> <li>Counts only running jobs when evaluating if a user or user group is approaching its per-host job slot limit (SLOTS, PER_USER=all, and HOSTS in the l sb. resources file), ignoring suspended jobs</li> </ul>
		PREEMPT_FOR=USER_JLP
		<ul style="list-style-type: none"> <li>Counts only running jobs when evaluating if a user is approaching their per-processor job slot limit (SLOTS_PER_PROCESSOR, USERS, and PER_HOST=all in the l sb. resources file)</li> <li>Ignores suspended jobs when calculating the per-processor job slot limit for individual users</li> </ul>

## Configuration to modify preemption of parallel jobs

File	Parameter	Syntax and description
l sb. params	PREEMPT_FOR	PREEMPT_FOR=MINI_JOB
		<ul style="list-style-type: none"> <li>Optimizes preemption of parallel jobs by preempting only enough low-priority parallel jobs to start the high-priority parallel job</li> </ul>
		PREEMPT_FOR=OPTIMAL_MINI_JOB
		<ul style="list-style-type: none"> <li>Optimizes preemption of parallel jobs by preempting only low-priority parallel jobs using the least number of slots to allow the high-priority parallel job to start</li> </ul>

## Configuration to modify the control action applied to preempted jobs

File	Parameter	Syntax and description
l sb. queues	TERMINATE_WHE N	TERMINATE_WHEN=PREEMPT <ul style="list-style-type: none"> <li>Changes the default control action of SUSPEND to TERMINATE so that LSF terminates preempted jobs</li> </ul>

## Configuration to control how many times a job can be preempted

By default, if preemption is enabled, there is actually no guarantee that a job will ever actually complete. A lower priority job could be preempted again and again, and ultimately end up being killed due to a run limit.

Limiting the number of times a job can be preempted is configured cluster-wide (l sb. params), at the queue level (l sb. queues), and at the application level (l sb. appl i cat i ons). MAX\_JOB\_PREEMPT in l sb. appl i cat i ons overrides l sb. queues, and l sb. queues overrides l sb. params configuration.

Files	Parameter	Syntax and description
l sb. params	MAX_JOB_PREEMPT	MAX_JOB_PREEMPT= <i>integer</i>
l sb. queues		<ul style="list-style-type: none"> <li>Specifies the maximum number of times a job can be preempted.</li> <li>Specify a value within the following ranges: 0 &lt; MAX_JOB_PREEMPT &lt; INFINIT_INT INFINIT_INT is defined in l sf . h</li> <li>By default, the number of preemption times is unlimited.</li> </ul>
l sb. appl i cat i ons		

When MAX\_JOB\_PREEMPT is set, and a job is preempted by higher priority job, the number of job preemption times is set to 1. When the number of preemption times exceeds MAX\_JOB\_PREEMPT, the job will run to completion and cannot be preempted again.

The job preemption limit times is recovered when LSF is restarted or reconfigured.

## Preemptive scheduling commands

### Commands for submission

Command	Description
bsub -q <i>queue_name</i>	<ul style="list-style-type: none"> <li>Submits the job to the specified queue, which may have a run limit associated with it</li> </ul>
bsub -W <i>minutes</i>	<ul style="list-style-type: none"> <li>Submits the job with the specified run limit, in minutes</li> </ul>
bsub -app <i>application_profile_name</i>	<ul style="list-style-type: none"> <li>Submits the job to the specified application profile, which may have a run limit associated with it</li> </ul>

## Commands to monitor

Command	Description
<code>bjobs -s</code>	<ul style="list-style-type: none"> <li>Displays suspended jobs, together with the reason the job was suspended</li> </ul>

## Commands to control

Command	Description
<code>brun</code>	<ul style="list-style-type: none"> <li>Forces a pending job to run immediately on specified hosts. For an exclusive job, when <code>LSB_DISABLE_LIMLOCK_EXCL=y</code>, LSF allows other jobs already running on the host to finish but does not dispatch any additional jobs to that host until the exclusive job finishes.</li> </ul>

## Commands to display configuration

Command	Description
<code>bqueues</code>	<ul style="list-style-type: none"> <li>Displays the priority (PRIO) and run limit (RUNLIMIT) for the queue, and whether the queue is configured to be preemptive, preemptable, or both</li> </ul>
<code>bhosts</code>	<ul style="list-style-type: none"> <li>Displays the number of job slots per user for a host</li> <li>Displays the number of job slots available</li> </ul>
<code>bparams</code>	<ul style="list-style-type: none"> <li>Displays the value of parameters defined in <code>lsb.params</code>.</li> </ul>
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>Displays all configured parameters and their values set in <code>lsf.conf</code> or <code>ego.conf</code> that affect <code>mbatchd</code> and <code>sbatchd</code>. Use a text editor to view other parameters in the <code>lsf.conf</code> or <code>ego.conf</code> configuration files.</li> <li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

# Feature: UNIX/Windows user account mapping

The UNIX/Windows user account mapping feature enables cross-platform job submission and execution in a mixed UNIX/Windows environment. Using this feature, you can map Windows user accounts, which include a domain name, to UNIX user accounts, which do not include a domain name, for user accounts with the same user name on both operating systems.

## Contents

- About UNIX/Windows user account mapping
- Scope
- Configuration to enable UNIX/Windows user account mapping
- UNIX/Windows user account mapping behavior
- Configuration to modify UNIX/Windows user account mapping behavior
- UNIX/Windows user account mapping commands

## About UNIX/Windows user account mapping

In a mixed UNIX/Windows cluster, LSF treats Windows user names (with domain) and UNIX user names (no domain) as different users. The UNIX/Windows user account mapping feature makes job submission and execution transparent across operating systems by mapping Windows accounts to UNIX accounts. With this feature enabled, LSF sends the user account name in the format required by the operating system on the execution host.




Figure 15: Default behavior (feature not enabled)

## Feature: UNIX/Windows user account mapping




Figure 16: With UNIX/Windows user account mapping enabled

For mixed UNIX/Windows clusters, UNIX/Windows user account mapping allows you to do the following:

- Submit a job from a Windows host and run the job on a UNIX host
- Submit a job from a UNIX host and run the job on a Windows host
- Specify the domain\user combination used to run a job on a Windows host
- Schedule and track jobs submitted with either a Windows or UNIX account as though the jobs belong to a single user

LSF supports the use of both single and multiple Windows domains. In a multiple domain environment, you can choose one domain as the preferred execution domain for a particular job.

Existing Windows domain trust relationships apply in LSF. If the execution domain trusts the submission domain, the submission account is valid on the execution host.

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>UNIX and Windows hosts within a single cluster</li> </ul>
Not required for	<ul style="list-style-type: none"> <li>Windows-only clusters</li> <li>UNIX-only clusters</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>This feature works with a uniform user name space. If users at your site have different user names on UNIX and Windows hosts, you must enable between-host user account mapping.</li> <li>This feature does not affect Windows workgroup installations. If you want to map all Windows workgroup users to a single Windows system account, you must configure between-host user account mapping.</li> <li>This feature applies only to job execution. If you issue an LSF command or define an LSF parameter and specify a Windows user, you must use the long form of the user name, including the domain name typed in uppercase letters.</li> </ul>

## Configuration to enable UNIX/Windows user account mapping

Enable the UNIX/Windows user account mapping feature by defining one or more LSF user domains using the `LSF_USER_DOMAIN` parameter in `lsf.conf`.

### Important:

Configure `LSF_USER_DOMAIN` immediately after you install LSF—changing this parameter in an existing cluster requires that you verify and possibly reconfigure service accounts, user group memberships, and user passwords.

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSF_USER_DOMAIN= <i>domain_name</i>	<ul style="list-style-type: none"> <li>Enables Windows domain account mapping in a single-domain environment</li> <li>To run jobs on a UNIX host, LSF strips the specified domain name from the user name</li> <li>To run jobs on a Windows host, LSF appends the domain name to the user name</li> </ul>
	LSF_USER_DOMAIN= <i>domain_name:domain_name</i> ...	<ul style="list-style-type: none"> <li>Enables Windows domain account mapping in a multi-domain environment</li> <li>To run jobs on a UNIX host, LSF strips the specified domain names from the user name</li> <li>To run jobs on a Windows host, LSF appends the first domain name to the user name. If the first domain\user combination does not have permissions to run the job, LSF tries the next domain in the LSF_USER_DOMAIN list.</li> </ul>
	LSF_USER_DOMAIN=.	<ul style="list-style-type: none"> <li>Enables Windows domain account mapping</li> <li>To run jobs on a UNIX host, LSF strips the local machine name from the user name</li> <li>To run jobs on a Windows host, LSF appends the local machine name to the user name</li> </ul>

## UNIX/Windows user account mapping behavior

The following examples describe how UNIX/Windows user account mapping enables job submission and execution across a mixed UNIX/Windows cluster.

When ...	In the file ...	And the job is submitted by ...	The job ...
UNIX/Windows user account mapping is not enabled	—	<ul style="list-style-type: none"> <li>BUSINESS\user1 on a Windows host</li> </ul>	<ul style="list-style-type: none"> <li>Runs on a Windows host as BUSINESS\user1</li> <li>Fails on a UNIX host: BUSINESS\user1 is not a valid UNIX user name</li> </ul>
UNIX/Windows user account mapping is not enabled	—	<ul style="list-style-type: none"> <li>user1 on a UNIX host</li> </ul>	<ul style="list-style-type: none"> <li>Fails on a Windows host: Windows requires a domain\user combination</li> <li>Runs on a UNIX host as user1</li> </ul>

When ...	In the file ...	And the job is submitted by ...	The job ...
LSF_USER_DOMAIN=BUSINESS	lsf.conf	BUSINESS\user1 on a Windows host	<ul style="list-style-type: none"> <li>Runs on a Windows host as BUSINESS\user1</li> <li>Runs on a UNIX host as user1</li> </ul>
LSF_USER_DOMAIN=BUSINESS	lsf.conf	user1 on a UNIX host	<ul style="list-style-type: none"> <li>Runs on a Windows host as BUSINESS\user1</li> <li>Runs on a UNIX host as user1</li> </ul>
LSF_USER_DOMAIN=SUPPORT:ENGINEERING	lsf.conf	SUPPORT\user1 on a Windows host	<ul style="list-style-type: none"> <li>Runs on a Windows host as SUPPORT\user1</li> <li>Runs on a UNIX host as user1</li> </ul>
LSF_USER_DOMAIN=SUPPORT:ENGINEERING	lsf.conf	BUSINESS\user1 on a Windows host	<ul style="list-style-type: none"> <li>Runs on a Windows host as BUSINESS\user1</li> <li>Fails on a UNIX host: LSF cannot strip the domain name, and BUSINESS\user1 is not a valid UNIX user name</li> </ul>
LSF_USER_DOMAIN=SUPPORT:ENGINEERING	lsf.conf	user1 on a UNIX host	<ul style="list-style-type: none"> <li>Runs on a Windows host as SUPPORT\user1; if the job cannot run with those credentials, the job runs as ENGINEERING\user1</li> <li>Runs on a UNIX host as user1</li> </ul>

## Configuration to modify UNIX/Windows user account mapping behavior

You can select a preferred execution domain for a particular job. The execution domain must be included in the LSF\_USER\_DOMAIN list. When you specify an execution domain, LSF ignores the order of the domains listed in LSF\_USER\_DOMAIN and runs the job using the specified domain. The environment variable LSF\_EXECUTE\_DOMAIN, defined in the user environment or from the command line, defines the preferred execution domain. Once you submit a job with an execution domain defined, you cannot change the execution domain for that particular job.

Configuration file	Parameter and syntax	Behavior
.cshrc	LSF_EXECUTE_DOMAIN= <i>domain_name</i>	<ul style="list-style-type: none"> <li>Specifies the domain that LSF uses to run jobs on a Windows host</li> </ul>
.profile		<ul style="list-style-type: none"> <li>If LSF_USER_DOMAIN contains a list of multiple domains, LSF tries the LSF_EXECUTE_DOMAIN first</li> </ul>

The following example shows the changed behavior when you define the LSF\_EXECUTE\_DOMAIN.

When ...	In the file ...	And the job is submitted by ...	The job ...
LSF_USER_DOMAIN=SUPPORT:ENGINEERING and LSF_EXECUTE_DOMAIN=ENGINEERING	lsf.conf . profile cshrc	• user1 on a UNIX host	• Runs on a Windows host as ENGINEERING\user1; if the job cannot run with those credentials, runs as SUPPORT\user1 • Runs on a UNIX host as user1

These additional examples are based on the following conditions:

- In lsf.conf, LSF\_USER\_DOMAIN=SALES:ENGINEERING:BUSINESS
- The user has sufficient permissions to run the job in any of the LSF user domains

UNIX user1 enters ...	And LSF_EXECUTE_DOMAIN is ...	Then LSF runs the job as ...
<b>bsub -m "hostb" myjob</b>	Not defined in the user environment file	SALES\user1
<b>bsub -m "hostb" myjob</b>	Defined as BUSINESS in the user environment file	BUSINESS\user1
<b>setenv LSF_EXECUTE_DOMAIN BUSINESS</b> <b>bsub -m "hostb" myjob</b>	Either defined or not defined in the user environment file	BUSINESS\user1 The command line overrides the user environment file.

## UNIX/Windows user account mapping commands

### Commands for submission

Command	Description
bsub	<ul style="list-style-type: none"> <li>• Submits the job with the user name and password of the user who entered the command. The job runs on the execution host with the same user name and password, unless you have configured UNIX/Windows user account mapping.</li> <li>• With UNIX/Windows user account mapping enabled, jobs that execute on a remote host run with the user account name in the format required by the operating system on the execution host.</li> </ul>

### Commands to monitor

Command	Description
bj obs -w	<ul style="list-style-type: none"> <li>• Displays detailed information about jobs.</li> <li>• Displays the long form of the Windows user name including the domain name.</li> </ul>

## Commands to control

Command	Description
<code>lspasswd</code>	<ul style="list-style-type: none"> <li>Registers a password for a Windows user account. Windows users must register a password for each <code>domain\user</code> account using this command.</li> </ul>

## Commands to display configuration

Command	Description
<code>bugroup -w</code>	<ul style="list-style-type: none"> <li>Displays information about user groups.</li> <li>If UNIX/Windows user account mapping is enabled, the command <code>bugroup</code> displays user names without domains.</li> <li>If UNIX/Windows user account mapping is not enabled, the command <code>bugroup</code> displays user names with domains.</li> </ul>
<code>busers</code>	<ul style="list-style-type: none"> <li>Displays information about specific users and user groups.</li> <li>If UNIX/Windows user account mapping is enabled, the command <code>busers</code> displays user names without domains.</li> <li>If UNIX/Windows user account mapping is not enabled, the command <code>busers</code> displays user names with domains.</li> </ul>
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>Displays all configured parameters and their values set in <code>lsf.conf</code> or <code>ego.conf</code> that affect <code>mbatchd</code> and <code>sbatchd</code>. Use a text editor to view other parameters in the <code>lsf.conf</code> or <code>ego.conf</code> configuration files.</li> <li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

# Feature: External job submission and execution controls

The job submission and execution controls feature enables you to use external, site-specific executables to validate, modify, and reject jobs, transfer data, and modify the job execution environment. By writing external submission (`esub`) and external execution (`eexec`) binaries or scripts, you can, for example, prevent the overuse of resources, specify execution hosts, or set required environment variables based on the job submission options.

## Contents

- About job submission and execution controls
- Scope
- Configuration to enable job submission and execution controls
- Job submission and execution controls behavior
- Configuration to modify job submission and execution controls
- Job submission and execution controls commands

## About job submission and execution controls

The job submission and execution controls feature uses the executables `esub` and `eexec` to control job options and the job execution environment.

### External submission (`esub`)

An `esub` is an executable that you write to meet the job requirements at your site. The following are some of the things that you can use an `esub` to do:

- Validate job options
- Change the job options specified by a user
- Change user environment variables on the submission host (at job submission only)
- Reject jobs (at job submission only)
- Pass data to `stdin` of `eexec`

When a user submits a job using `bsub` or modifies a job using `bmod`, LSF runs the `esub` executable(s) on the submission host before accepting the job. If the user submitted the job with options such as `-R` to specify required resources or `-q` to specify a queue, an `esub` can change the values of those options to conform to resource usage policies at your site.

---


#### Note:

When compound resource requirements are used at any level, an `esub` can create job-level resource requirements which overwrite most application-level and queue-level resource requirements. `-R merge` rules are explained in detail in *Administering Platform LSF*.


---

An `esub` can also change the user environment on the submission host prior to job submission so that when LSF copies the submission host environment to the execution host, the job runs on the execution host with the values specified by the `esub`. For example, an `esub` can add user environment variables to those already associated with the job.

## Use of esub not enabled



## With esub enabled



An esub executable is typically used to enforce site-specific job submission policies and command-line syntax by validating or pre-parsing the command line. The file indicated by the environment variable `LSB_SUB_PARAM_FILE` stores the values submitted by the user. An esub reads the `LSB_SUB_PARAM_FILE` and then accepts or changes the

option values or rejects the job. Because an `esub` runs before job submission, using an `esub` to reject incorrect job submissions improves overall system performance by reducing the load on the master batch daemon (`mbatchd`).

An `esub` can be used to:

- Reject any job that requests more than a specified number of CPUs
- Change the submission queue for specific user accounts to a higher priority queue
- Check whether the job specifies an application and, if so, submit the job to the correct application profile

---

**Note:**

If an `esub` executable fails, the job will still be submitted to LSF.

---

## Multiple `esub` executables

LSF provides a master external submission executable (`LSF_SERVERDIR/mesub`) that supports the use of application-specific `esub` executables. Users can specify one or more `esub` executables using the `-a` option of `bsub` or `bmod`. When a user submits or modifies a job or when a user restarts a job that was submitted or modified with the `-a` option included, `mesub` runs the specified `esub` executables.

An LSF administrator can specify one or more mandatory `esub` executables by defining the parameter `LSB_ESUB_METHOD` in `lsf.conf`. If a mandatory `esub` is defined, `mesub` runs the mandatory `esub` for all jobs submitted to LSF in addition to any `esub` executables specified with the `-a` option.

The naming convention is `esub. application`. LSF always runs the executable named "`esub`" (without `.application`) if it exists in `LSF_SERVERDIR`.

---

**Note:**

All `esub` executables must be stored in the `LSF_SERVERDIR` directory defined in `lsf.conf`.


---

The `mesub` runs multiple `esub` executables in the following order:

1. The mandatory `esub` or `esubs` specified by `LSB_ESUB_METHOD` in `lsf.conf`
2. Any executable with the name "`esub`" in `LSF_SERVERDIR`
3. One or more `esubs` in the order specified by `bsub -a`

## Example of multiple `esub` execution


An `esub` runs only once, even if it is specified by both the `bsub -a` option and the parameter `LSB_ESUB_METHOD`.




## External execution (eexec)

An `eexec` is an executable that you write to control the job environment on the execution host.

### Use of `eexec` not enabled



## With eexec enabled



The following are some of the things that you can use an eexec to do:

- Set up the user environment variables on the execution host
- Monitor job state or resource usage
- Receive data from stdout of esub
- Run a shell script to create and populate environment variables needed by jobs
- Monitor the number of tasks running on a host and raise a flag when this number exceeds a pre-determined limit
- Pass DCE credentials and AFS tokens using a combination of esub and eexec executables; LSF functions as a pipe for passing data from the stdout of esub to the stdin of eexec

An eexec can change the user environment variable values transferred from the submission host so that the job runs on the execution host with a different environment.

For example, if you have a mixed UNIX and Windows cluster, the submission and execution hosts might use different operating systems. In this case, the submission host environment might not meet the job requirements when the job runs on the execution host. You can use an eexec to set the correct user environment between the two operating systems.

Typically, an eexec executable is a shell script that creates and populates the environment variables required by the job. An eexec can also monitor job execution and enforce site-specific resource usage policies.

The following are some of the things that you can use an eexec to do:

- Set up the user environment variables on the execution host
- Monitor job state or resource usage
- Receive data from stdout of esub
- Run a shell script to create and populate environment variables needed by jobs
- Monitor the number of tasks running on a host and raise a flag when this number exceeds a pre-determined limit
- Pass DCE credentials and AFS tokens using a combination of esub and eexec executables; LSF functions as a pipe for passing data from the stdout of esub to the stdin of eexec

If an eexec executable exists in the directory specified by LSF\_SERVERDIR, LSF invokes that eexec for all jobs submitted to the cluster. By default, LSF runs eexec on the execution host before the job starts. The job process that invokes eexec waits for eexec to finish before continuing with job execution.

Unlike a pre-execution command defined at the job, queue, or application levels, an eexec:

- Runs at job start, finish, or checkpoint
- Allows the job to run without pending if eexec fails; eexec has no effect on the job state
- Runs for all jobs, regardless of queue or application profile

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX and Linux</li> <li>• Windows</li> </ul>
Security	<ul style="list-style-type: none"> <li>• Data passing between <code>esub</code> on the submission host and <code>eexec</code> on the execution host is not encrypted.</li> </ul>
Job types	<ul style="list-style-type: none"> <li>• Batch jobs submitted with <code>bsub</code> or modified by <code>bmod</code>.</li> <li>• Batch jobs restarted with <code>brstart</code>.</li> <li>• Interactive tasks submitted with <code>l srun</code> and <code>l sgrun</code> (<code>eexec</code> only).</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster, or the correct type of account mapping must be enabled. <ul style="list-style-type: none"> <li>• For a mixed UNIX/Windows cluster, UNIX/Windows user account mapping must be enabled.</li> <li>• For a cluster with a non-uniform user name space, between-host account mapping must be enabled.</li> <li>• For a MultiCluster environment with a non-uniform user name space, cross-cluster user account mapping must be enabled.</li> </ul> </li> <li>• User accounts must have the correct permissions to successfully run jobs.</li> <li>• An <code>eexec</code> that requires root privileges to run on UNIX or Linux, must be configured to run as the root user.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>• Only an <code>esub</code> invoked by <code>bsub</code> can change the job environment on the submission host. An <code>esub</code> invoked by <code>bmod</code> or <code>brstart</code> cannot change the environment.</li> <li>• Any <code>esub</code> messages provided to the user must be directed to standard error, not to standard output. Standard output from any <code>esub</code> is automatically passed to <code>eexec</code>.</li> <li>• An <code>eexec</code> can handle only one standard output stream from an <code>esub</code> as standard input to <code>eexec</code>. You must make sure that your <code>eexec</code> handles standard output from correctly if any <code>esub</code> writes to standard output.</li> <li>• The <code>esub/eexec</code> combination cannot handle daemon authentication. To configure daemon authentication, you must enable external authentication, which uses the <code>eauth</code> executable.</li> </ul>

## Configuration to enable job submission and execution controls

This feature is enabled by the presence of at least one `esub` or one `eexec` executable in the directory specified by the parameter `LSF_SERVERDIR` in `lsf.conf`. LSF does not include a default `esub` or `eexec`; you should write your own executables to meet the job requirements of your site.

Executable file	UNIX naming convention	Windows naming convention
esub	LSF_SERVERDIR/ esub. <i>application</i>	LSF_SERVERDIR \esub. <i>application.exe</i>
		LSF_SERVERDIR \esub. <i>application.bat</i>
eexec	LSF_SERVERDIR/eexec	LSF_SERVERDIR\eexec.exe
		LSF_SERVERDIR\eexec.bat

The name of your esub should indicate the application with which it runs. For example: esub. fluent.

**Restriction:**

The name esub. user is reserved. Do not use the name esub. user for an application-specific esub.

Valid file names contain only alphanumeric characters, underscores (\_), and hyphens (-).

Once the LSF\_SERVERDIR contains one or more esub executables, users can specify the esub executables associated with each job they submit. If an eexec exists in LSF\_SERVERDIR, LSF invokes that eexec for all jobs submitted to the cluster.

The following esub executables are provided as separate packages, available from Platform Computing Inc. upon request:

- esub. openmpi : OpenMPI job submission
- esub. pvm: PVM job submission
- esub. poe : POE job submission
- esub. ls\_dyna : LS-Dyna job submission
- esub. fluent : FLUENT job submission
- esub. afs or esub. dce: AFS or DCE security
- esub. lammpi LAM/MPI job submission
- esub. mpi ch\_gm : MPICH-GM job submission
- esub. intel mpi : Intel®MPI job submission
- esub. bproc: Beowulf Distributed Process Space (BProc) job submission
- esub. mpi ch2: MPICH2 job submission
- esub. mpi chp4: MPICH-P4 job submission
- esub. mvapi ch: MVAPICH job submission
- esub. tv, esub. tvlammpi , esub. tvmpi ch\_gm, esub. tvpoe: TotalView® debugging for various MPI applications.

## Environment variables used by esub

When you write an esub, you can use the following environment variables provided by LSF for the esub execution environment:

**LSB\_SUB\_PARM\_FILE**

Points to a temporary file that LSF uses to store the bsub options entered in the command line. An esub reads this file at job submission and either accepts the values,

changes the values, or rejects the job. Job submission options are stored as name-value pairs on separate lines with the format `option_name=value`.

For example, if a user submits the following job,

```
bsub -q normal -x -P myproject -R "rlm rusage[mem=100]" -n 90 myjob
```

The `LSB_SUB_PARM_FILE` contains the following lines:

```
LSB_SUB_QUEUE="normal "
LSB_SUB_EXCLUSIVE=Y
LSB_SUB_RES_REQ="rlm rusage[mem=100]"
LSB_SUB_PROJECT_NAME="myproject"
LSB_SUB_COMMAND_LINE="myjob"
LSB_SUB_NUM_PROCESSORS=90
LSB_SUB_MAX_NUM_PROCESSORS=90
```

An `esub` can change any or all of the job options by writing to the file specified by the environment variable `LSB_SUB_MODIFY_FILE`.

The temporary file pointed to by `LSB_SUB_PARM_FILE` stores the following information:

Option	bsub or bmod option	data type	Description
<code>LSB_SUB_ADDITIONAL</code>	<code>-a</code>	string	String that contains the application name or names of the <code>esub</code> executables requested by the user.  <b>Restriction:</b> This is the only option that an <code>esub</code> cannot change or add at job submission.
<code>LSB_SUB_BEGIN_TIME</code>	<code>-b</code>	integer	Begin time, in seconds since 00:00:00 GMT, Jan. 1, 1970
<code>LSB_SUB_CHKPNT_DIR</code>	<code>-k</code>	string	Checkpoint directory The file path of the checkpoint directory can contain up to 4000 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.
<code>LSB_SUB_COMMAND_LINE</code>	bsub job command argument	string	<code>LSB_SUB_COMMANDNAME</code> must be set in <code>lsf.conf</code> to enable <code>esub</code> to use this variable.

Feature: External job submission and execution controls

Option	bsub or bmod option	data type	Description
LSB_SUB_CHKPNT_PERIOD	-k	integer	Checkpoint period
LSB_SUB_DEPEND_COND	-w	string	Dependency condition
LSB_SUB_ERR_FILE	-e, -eo	string	Standard error file name
LSB_SUB_EXCLUSIVE	-x	boolean	Exclusive execution, specified by "Y"
LSB_SUB_EXTSCHED_PARAM	-ext	string	External scheduler options
LSB_SUB_HOLD	-H	boolean	Hold job
LSB_SUB_HOST_SPEC	-c or -w	string	Host specifier, limits the CPU time or RUN time.
LSB_SUB_HOSTS	-m	string	List of requested execution host names
LSB_SUB_IN_FILE	-i, -io	string	Standard input file name
LSB_SUB_INTERACTIVE	-I	boolean	Interactive job, specified by "Y"
LSB_SUB_LOGIN_SHELL	-L	string	Login shell
LSB_SUB_JOB_NAME	-J	string	Job name

Option	bsub or bmod option	data type	Description
LSB_SUB_JOB_WARNING_ACTION	-wa	string	Job warning action
LSB_SUB_JOB_ACTION_WARNING_TIME	-wt	integer	Job warning time period
LSB_SUB_MAIL_USER	-u	string	Email address to which LSF sends job-related messages
LSB_SUB_MAX_NUM_PROCESSORS	-n	integer	Maximum number of processors requested
LSB_SUB_MODIFY	bmod	boolean	Indicates that bmod invoked esub, specified by "Y".
LSB_SUB_MODIFY_ONCE	bmod	boolean	Indicates that the job options specified at job submission have already been modified by bmod, and that bmod is invoking esub again, specified by "Y".
LSB_SUB_NOTIFY_BEGIN	-B	boolean	LSF sends an email notification when the job begins, specified by "Y".
LSB_SUB_NOTIFY_END	-N	boolean	LSF sends an email notification when the job ends, specified by "Y".
LSB_SUB_NUM_PROCESSORS	-n	integer	Minimum number of processors requested.
LSB_SUB_OTHER_FILES	bmod -f	integer	Indicates the number of files to be transferred. The value is SUB_RESET if bmod is being used to reset the number of files to be transferred.  The file path of the directory can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the director and file name.

Option	bsub or bmod option	data type	Description
LSB_SUB_OTHER_FILES_ <i>number</i>	bsub -f	integer	<p>The <i>number</i> indicates the particular file transfer value in the specified file transfer expression.</p> <p>For example, for bsub -f "a &gt; b" -f "c &lt; d", the following would be defined:</p> <pre>LSB_SUB_OTHER_FILES=2 LSB_SUB_OTHER_FILES_0="a &gt; b" LSB_SUB_OTHER_FILES_1="c &lt; d"</pre>
LSB_SUB_OUT_FILE	-o, -oo	string	Standard output file name.
LSB_SUB_PRE_EXEC	-E	string	<p>Pre-execution command.</p> <p>The file path of the directory can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.</p>
LSB_SUB_PROJECT_NAME	-P	string	Project name.
LSB_SUB_PTY	-lp	boolean	An interactive job with PTY support, specified by "Y"
LSB_SUB_PTY_SHELL	-ls	boolean	An interactive job with PTY shell support, specified by "Y"
LSB_SUB_QUEUE	-q	string	Submission queue name

Option	bsub or bmod option	data type	Description
LSB_SUB_RERUNNABLE	-r	boolean	"Y" specifies a rerunnable job "N" specifies a nonrerunnable job (specified with bsub -rn). The job is not rerunnable even it was submitted to a rerunnable queue or application profile For bmod -rn, the value is SUB_RESET.
LSB_SUB_RES_REQ	-R	string	Resource requirement string— <i>does not</i> support multiple resource requirement strings
LSB_SUB_RESTART	brestart	boolean	"Y" indicates to esub that the job options are associated with a restarted job.
LSB_SUB_RESTART_FORCE	brestart -f	boolean	"Y" indicates to esub that the job options are associated with a forced restarted job.
LSB_SUB_RLIMIT_CORE	-C	integer	Core file size limit
LSB_SUB_RLIMIT_CPU	-c	integer	CPU limit
LSB_SUB_RLIMIT_DATA	-D	integer	Data size limit For AIX, if the XPG_SUS_ENV=ON environment variable is set in the user's environment before the process is executed and a process attempts to set the limit lower than current usage, the operation fails with errno set to EINVAL. If the XPG_SUS_ENV environment variable is not set, the operation fails with errno set to EFAULT.
LSB_SUB_RLIMIT_FSIZE	-F	integer	File size limit
LSB_SUB_RLIMIT_PROCESS	-p	integer	Process limit

Feature: External job submission and execution controls

Option	bsub or bmod option	data type	Description
LSB_SUB_RLIMIT_RSS	-M	integer	Resident size limit
LSB_SUB_RLIMIT_RUN	-W	integer	Wall-clock run limit
LSB_SUB_RLIMIT_STACK	-S	integer	Stack size limit
LSB_SUB_RLIMIT_THREAD	-T	integer	Thread limit
LSB_SUB_TERM_TIME	-t	integer	Termination time, in seconds, since 00:00:00 GMT, Jan. 1, 1970
LSB_SUB_TIME_EVENT	-wt	string	Time event expression
LSB_SUB_USER_GROUP	-G	string	User group name
LSB_SUB_WINDOW_SIG	-s	boolean	Window signal number
LSB_SUB2_JOB_GROUP	-g	string	Submits a job to a job group
LSB_SUB2_LICENSE_PROJECT	-Lp	string	LSF License Scheduler project name
LSB_SUB2_IN_FILE_SPOOL	-is	string	Spooled input file name
LSB_SUB2_JOB_CMD_SPOOL	-Zs	string	Spooled job command file name
LSB_SUB2_JOB_PRIORITY	-sp	integer	Job priority For bmod -spn, the value is SUB_RESET.

Option	bsub or bmod option	data type	Description
LSB_SUB2_SLA	-sla	string	SLA scheduling options
LSB_SUB2_USE_RSV	-U	string	Advance reservation ID
LSB_SUB3_ABSOLUTE_PRIORITY	bmod -aps  bmod -apsn	string	For bmod -aps, the value equal to the APS string given. For bmod -apsn, the value is SUB_RESET.
LSB_SUB3_AUTO_RESIZABLE	-ar	boolean	Job autoresizable attribute. LSB_SUB3_AUTO_RESIZABLE=Y if bsub -ar or bmod -ar is specified.  LSB_SUB3_AUTO_RESIZABLE=SUB_RESET if bmod -arn is used.
LSB_SUB3_APP	-app	string	Application profile name  For bmod -appn, the value is SUB_RESET.
LSB_SUB3_CWD	-cwd	string	Current working directory
LSB_SUB3_INIT_CHKPNT_PERIOD	-k init	integer	Initial checkpoint period
LSB_SUB_INTERACTIVE LSB_SUB3_INTERACTIVE_SSH	bsub -IS	boolean	The session of the interactive job is encrypted with SSH.
LSB_SUB_INTERACTIVE LSB_SUB_PTY LSB_SUB3_INTERACTIVE_SSH	bsub -ISp	boolean	If LSB_SUB_INTERACTIVE is specified by "Y", LSB_SUB_PTY is specified by "Y", and LSB_SUB3_INTERACTIVE_SSH is specified by "Y", the session of interactive job with PTY support is encrypted by SSH.

Option	bsub or bmod option	data type	Description
LSB_SUB_INTERACTIVE LSB_SUB_PTY LSB_SUB_PTY_SHELL LSB_SUB3_INTERACTIVE_SSH	bsub -ISs	boolean	If LSB_SUB_INTERACTIVE is specified by "Y", LSB_SUB_PTY is specified by "Y", LSB_SUB_PTY_SHELL is specified by "Y", and LSB_SUB3_INTERACTIVE_SSH is specified by "Y", the session of interactive job with PTY shell support is encrypted by SSH.
LSB_SUB3_JOB_REQUEUE	-Q	string	String format parameter containing the job requeue exit values For bmod -Qn, the value is SUB_RESET.
LSB_SUB3_MIG	-mig -mign	integer	Migration threshold
LSB_SUB3_POST_EXEC	-Ep	string	Run the specified post-execution command on the execution host after the job finishes.  The file path of the directory can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.
LSB_SUB3_RESIZE_NOTIFY_CMD	-rnc	string	Job resize notification command. LSB_SUB3_RESIZE_NOTIFY_CMD=<cmd> if bsub -rnc or bmod -rnc is specified.  LSB_SUB3_RESIZE_NOTIFY_CMD=SUB_RESET if bmod -rnc is used.
LSB_SUB3_RUNTIME_ESTIMATION	-We	integer	Runtime estimate
LSB_SUB3_RUNTIME_ESTIMATION_ACC	-We+	integer	Runtime estimate that is the accumulated run time plus the runtime estimate
LSB_SUB3_RUNTIME_ESTIMATION_PERC	-Wep	integer	Runtime estimate in percentage of completion

Option	bsub or bmod option	data type	Description
LSB_SUB3_USER_SHELL_LIMITS	-ul	boolean	Pass user shell limits to execution host
LSB_SUB_INTERACTIVE LSB_SUB3_XJOB_SSH	bsub -IX	boolean	If both are set to "Y", the session between the X-client and X-server as well as the session between the execution host and submission host are encrypted with SSH.

### LSB\_SUB\_MODIFY\_FILE

Points to the file that `esub` uses to modify the `bsub` job option values stored in the `LSB_SUB_PARM_FILE`. You can change the job options by having your `esub` write the new values to the `LSB_SUB_MODIFY_FILE` in any order, using the same format shown for the `LSB_SUB_PARM_FILE`. The value `SUB_RESET`, integers, and boolean values do not require quotes. String parameters must be entered with quotes around each string, or space-separated series of strings.

When your `esub` runs at job submission, LSF checks the `LSB_SUB_MODIFY_FILE` and applies changes so that the job runs with the revised option values.

#### Restriction:

`LSB_SUB_ADDITIONAL` is the only option that an `esub` cannot change or add at job submission.

### LSB\_SUB\_MODIFY\_ENVFILE

Points to the file that `esub` uses to modify the user environment variables with which the job is submitted (not specified by `bsub` options). You can change these environment variables by having your `esub` write the values to the `LSB_SUB_MODIFY_ENVFILE` in any order, using the format `variable_name=value`, or `variable_name="string"`.

LSF uses the `LSB_SUB_MODIFY_ENVFILE` to change the environment variables on the submission host. When your `esub` runs at job submission, LSF checks the `LSB_SUB_MODIFY_ENVFILE` and applies changes so that the job is submitted with the new environment variable values. LSF associates the new user environment with the job so that the job runs on the execution host with the new user environment.

### LSB\_SUB\_ABORT\_VALUE

Indicates to LSF that a job should be rejected. For example, if you want LSF to reject a job, your `esub` should contain the line

```
exit $LSB_SUB_ABORT_VALUE
```

#### Restriction:

When an `esub` exits with the `LSB_SUB_ABORT_VALUE`, `esub` must not write to `LSB_SUB_MODIFY_FILE` or to `LSB_SUB_MODIFY_ENVFILE`.

If multiple `esubs` are specified and one of the `esubs` exits with a value of `LSB_SUB_ABORT_VALUE`, LSF rejects the job without running the remaining `esubs` and returns a value of `LSB_SUB_ABORT_VALUE`.

### LSB\_INVOKE\_CMD

Specifies the name of the LSF command that most recently invoked an external executable.

## Environment variables used by eexec

When you write an `eexec`, you can use the following environment variables in addition to all user-environment or application-specific variables.

### LS\_EXEC\_T

Indicates the stage or type of job execution. LSF sets `LS_EXEC_T` to:

- `START` at the beginning of job execution
- `END` at job completion
- `CHKPNT` at job checkpoint start

### LS\_JOBPID

Stores the process ID of the LSF process that invoked `eexec`. If `eexec` is intended to monitor job execution, `eexec` must spawn a child and then have the parent `eexec` process exit. The `eexec` child should periodically test that the job process is still alive using the `LS_JOBPID` variable.

## Job submission and execution controls behavior

The following examples illustrate how customized `esub` and `eexec` executables can control job submission and execution.

## Validating job submission parameters using esub

When a user submits a job using `bsub-P`, LSF accepts any project name entered by the user and associates that project name with the job. This example shows an `esub` that supports project-based accounting by enforcing the use of valid project names for jobs submitted by users who are eligible to charge to those projects. If a user submits a job to any project other than `proj1` or `proj2`, or if the user name is not `user1` or `user2`, LSF rejects the job based on the exit value of `LSB_SUB_ABORT_VALUE`.

```
#!/bin/sh
. $LSB_SUB_PARM_FILE
# Redirect stderr to stdout so echo can be used for error messages exec 1>&2
# Check valid projects
if [ $LSB_SUB_PROJECT_NAME != "proj1" -o $LSB_SUB_PROJECT_NAME != "proj2" ];
then
    echo "Incorrect project name specified"
    exit $LSB_SUB_ABORT_VALUE
fi
USER=`whoami`
if [ $LSB_SUB_PROJECT_NAME="proj1" ]; then
# Only user1 and user2 can charge to proj1
if [ $USER != "user1" -a $USER != "user2" ]; then
```

```

        echo "You are not allowed to charge to this project"
        exit $LSB_SUB_ABORT_VALUE
    fi
fi

```

## Changing job submission parameters using esub

The following example shows an esub that modifies job submission options and environment variables based on the user name that submits a job. This esub writes the changes to LSB\_SUB\_MODIFY\_FILE for userA and to LSB\_SUB\_MODIFY\_ENVFILE for userB. LSF rejects all jobs submitted by userC without writing to either file:

```

#!/bin/sh
. $LSB_SUB_PARM_FILE
# Redirect stderr to stdout so echo can be used for error messages exec 1>&2
USER=`whoami`
# Make sure userA is using the right queue queueA
if [ $USER="userA" -a $LSB_SUB_QUEUE != "queueA" ]; then
    echo "userA has submitted a job to an incorrect queue"
    echo "...submitting to queueA"
    echo 'LSB_SUB_QUEUE="queueA"' > $LSB_SUB_MODIFY_FILE
fi
# Make sure userB is using the right shell (/bin/sh)
if [ $USER="userB" -a $SHELL != "/bin/sh" ]; then
    echo "userB has submitted a job using $SHELL"
    echo "...using /bin/sh instead"
    echo 'SHELL="/bin/sh"' > $LSB_SUB_MODIFY_ENVFILE
fi
# Deny userC the ability to submit a job
if [ $USER="userC" ]; then
    echo "You are not permitted to submit a job."
    exit $LSB_SUB_ABORT_VALUE
fi

```

## Monitoring the execution environment using eexec

This example shows how you can use an eexec to monitor job execution:

```

#!/bin/sh
# eexec
# Example script to monitor the number of jobs executing through RES.
# This script works in cooperation with an elim that counts the
# number of files in the TASKDIR directory. Each RES process on a host
# will have a file in the TASKDIR directory.
# Don't want to monitor lsbatch jobs.
if [ "$LSB_JOBID" != "" ]; then
    exit 0
fi
TASKDIR="/tmp/RES_dir"
# directory containing all the task files
# for the host.
# you can change this to whatever
# directory you wish, just make sure anyone
# has read/write permissions.
# if TASKDIR does not exist create it
if [ "test -d $TASKDIR" != "0" ]; then
    mkdir $TASKDIR > /dev/null 2>&1
fi
# Need to make sure LS_JOBPID, and USER are defined
# exit normally
if [ "test -z $LS_JOBPID" = "0" ]; then
    exit 0
elif [ "test -z $USER" = "0" ]; then
    exit 0
fi
taskFile="$TASKDIR/$LS_JOBPID.$USER"
# Fork grandchild to stay around for the duration of the task
touch $taskFile > /dev/null 2>&1
(
    (while : ;
        do

```

```

        kill -0 $LS_JOBPID >/dev/null 2>&1
        if [ $? -eq 0 ]; then
            sleep 10 # this is the poll interval
                    # increase it if you want but
                    # see the elim for its
                    # corresponding update interval
        else
            rm $taskFile >/dev/null 2>&1
            exit 0
        fi
    done) &
wait

```

## Passing data between esub and eexec

A combination of esub and eexec executables can be used to pass AFS/DCE tokens from the submission host to the execution host. LSF passes data from the standard output of esub to the standard input of eexec. A daemon wrapper script can be used to renew the tokens.

## Configuration to modify job submission and execution controls

There are configuration parameters that modify various aspects of job submission and execution controls behavior by:

- Defining a mandatory esub that applies to all jobs in the cluster
- Specifying the eexec user account (UNIX only)

## Configuration to define a mandatory esub

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSB_ESUB_METHOD=" <i>esub_appl i cat i on [esub_appl i cat i on] ...</i> "	<ul style="list-style-type: none"> <li>• The specified esub or esubs run for all jobs submitted to the cluster, in addition to any esub specified by the user in the command line</li> <li>• For example, to specify a mandatory esub named esub.fluent, define LSB_ESUB_METHOD=fluent</li> </ul>

## Configuration to specify the eexec user account

The eexec executable runs under the submission user account. You can modify this behavior for UNIX hosts by specifying a different user account.

Configuration file	Parameter and syntax	Behavior
lsf.sudoers	LSF_EEXEC_USER= <i>user_name</i>	<ul style="list-style-type: none"> <li>• Changes the user account under which eexec runs</li> </ul>

## Job submission and execution controls commands

### Commands for submission

Command	Description
<code>bsub -a esub_application [esub_application] ...</code>	<ul style="list-style-type: none"> <li>Specifies one or more esub executables to run at job submission</li> <li>For example, to specify the esub named <code>esub.fluent</code>, use <b><code>bsub -a fluent</code></b></li> <li>LSF runs any esub executables defined by <code>LSB_ESUB_METHOD</code>, followed by the executable named "esub" if it exists in <code>LSF_SERVERDIR</code>, followed by the esub executables specified by the <code>-a</code> option</li> <li>LSF runs <code>eexec</code> if an executable file with that name exists in <code>LSF_SERVERDIR</code></li> </ul>
<code>brestart</code>	<ul style="list-style-type: none"> <li>Restarts a checkpointed job and runs the esub executables specified when the job was submitted</li> <li>LSF runs any esub executables defined by <code>LSB_ESUB_METHOD</code>, followed by the executable named "esub" if it exists in <code>LSF_SERVERDIR</code>, followed by the esub executables specified by the <code>-a</code> option</li> <li>LSF runs <code>eexec</code> if an executable file with that name exists in <code>LSF_SERVERDIR</code></li> </ul>
<code>l srun</code>	<ul style="list-style-type: none"> <li>Submits an interactive task; LSF runs <code>eexec</code> if an <code>eexec</code> executable exists in <code>LSF_SERVERDIR</code></li> <li>LSF runs <code>eexec</code> only at task startup (<code>LS_EXEC_T=START</code>)</li> </ul>
<code>l sgrun</code>	<ul style="list-style-type: none"> <li>Submits an interactive task to run on a set of hosts; LSF runs <code>eexec</code> if an <code>eexec</code> executable exists in <code>LSF_SERVERDIR</code></li> <li>LSF runs <code>eexec</code> only at task startup (<code>LS_EXEC_T=START</code>)</li> </ul>

### Commands to monitor

Not applicable: There are no commands to monitor the behavior of this feature.

### Commands to control

Command	Description
<code>bmod -a esub_application [esub_application] ...</code>	<ul style="list-style-type: none"> <li>Resubmits a job and changes the esubs previously associated with the job</li> <li>LSF runs any esub executables defined by <code>LSB_ESUB_METHOD</code>, followed by the executable named "esub" if it exists in <code>LSF_SERVERDIR</code>, followed by the esub executables specified by the <code>-a</code> option of <code>bmod</code></li> <li>LSF runs <code>eexec</code> if an executable file with that name exists in <code>LSF_SERVERDIR</code></li> </ul>

---

Command	Description
<code>bmod -an</code>	<ul style="list-style-type: none"><li>• Dissociates from a job all esub executables that were previously associated with the job</li><li>• LSF runs any esub executables defined by <code>LSB_ESUB_METHOD</code>, followed by the executable named "esub" if it exists in <code>LSF_SERVERDIR</code></li><li>• LSF runs <code>eexec</code> if an executable file with that name exists in <code>LSF_SERVERDIR</code></li></ul>

---

## Commands to display configuration

---

Command	Description
<code>badmi n showconf</code>	<ul style="list-style-type: none"><li>• Displays all configured parameters and their values set in <code>lsf.conf</code> or <code>ego.conf</code> that affect <code>mbatchd</code> and <code>sbatchd</code>.  Use a text editor to view other parameters in the <code>lsf.conf</code> or <code>ego.conf</code> configuration files.</li><li>• In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li></ul>

---

Use a text editor to view the `lsf.sudoers` configuration file.

# Feature: Job migration

The job migration feature enables you to move checkpointable and rerunnable jobs from one host to another. Job migration makes use of job checkpoint and restart so that a migrated checkpointable job restarts on the new host from the point at which the job stopped on the original host.

## Contents


- About job migration
- Scope
- Configuration to enable job migration
- Job migration behavior
- Configuration to modify job migration
- Job migration commands

## About job migration


Job migration refers to the process of moving a checkpointable or rerunnable job from one host to another. This facilitates load balancing by moving jobs from a heavily-loaded host to a lightly-loaded host.

You can initiate job migration on demand (bmi g) or automatically. To initiate job migration automatically, you configure a migration threshold at the host or queue level.

## Default behavior (job migration not enabled)



## With automatic job migration enabled



## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX</li> <li>• Linux</li> <li>• Windows</li> </ul>
Job types	<ul style="list-style-type: none"> <li>• Non-interactive batch jobs submitted with <code>bsub</code> or <code>bmod</code>, including chunk jobs</li> </ul>

Applicability	Details
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster, or the correct type of account mapping must be enabled:               <ul style="list-style-type: none"> <li>• For a mixed UNIX/Windows cluster, UNIX/Windows user account mapping must be enabled</li> <li>• For a cluster with a non-uniform user name space, between-host account mapping must be enabled</li> <li>• For a MultiCluster environment with a non-uniform user name space, cross-cluster user account mapping must be enabled</li> </ul> </li> <li>• Both the original and the new hosts must:               <ul style="list-style-type: none"> <li>• Be binary compatible</li> <li>• Run the same dot version of the operating system for predictable results</li> <li>• Have network connectivity and read/execute permissions to the checkpoint and restart executables (in LSF_SERVERDIR by default)</li> <li>• Have network connectivity and read/write permissions to the checkpoint directory and the checkpoint file</li> <li>• Have access to all files open during job execution so that LSF can locate them using an absolute path name</li> </ul> </li> </ul>

## Configuration to enable job migration

The job migration feature requires that a job be made checkpointable or rerunnable at the job, application, or queue level. An LSF user can make a job

- Checkpointable, using `bsub -k` and specifying a checkpoint directory and checkpoint period, and an optional initial checkpoint period
- Rerunnable, using `bsub -r`

Configuration file	Parameter and syntax	Behavior
l sb. queues	CHKPNT= <i>chkpnt_dir</i> [ <i>chkpnt_period</i> ]	<ul style="list-style-type: none"> <li>All jobs submitted to the queue are checkpointable.</li> <li>The specified checkpoint directory must already exist. LSF will not create the checkpoint directory.</li> <li>The user account that submits the job must have read and write permissions for the checkpoint directory.</li> <li>For the job to restart on another execution host, both the original and new hosts must have network connectivity to the checkpoint directory.</li> <li>If the queue administrator specifies a checkpoint period, in minutes, LSF creates a checkpoint file every <i>chkpnt_period</i> during job execution.</li> <li>If a user specifies a checkpoint directory and checkpoint period at the job level with <code>bsub -k</code>, the job-level values override the queue-level values.</li> </ul>
	RERUNNABLE=Y	<ul style="list-style-type: none"> <li>If the execution host becomes unavailable, LSF reruns the job from the beginning on a different host.</li> </ul>
l sb. applications	CHKPNT_DIR= <i>chkpnt_dir</i>	<ul style="list-style-type: none"> <li>Specifies the checkpoint directory for automatic checkpointing for the application. To enable automatic checkpoint for the application profile, administrators must specify a checkpoint directory in the configuration of the application profile.</li> <li>If CHKPNT_PERIOD, CHKPNT_INITPERIOD or CHKPNT_METHOD was set in an application profile but CHKPNT_DIR was not set, a warning message is issued and those settings are ignored.</li> <li>The checkpoint directory is the directory where the checkpoint files are created. Specify an absolute path or a path relative to the current working directory for the job. Do not use environment variables in the directory path.</li> <li>If checkpoint-related configuration is specified in both the queue and an application profile, the application profile setting overrides queue level configuration.</li> </ul>
	CHKPNT_INITPERIOD= <i>init_chkpnt_period</i>	

Configuration file	Parameter and syntax	Behavior
	CHKPNT_PERIOD= <i>chkpnt_period</i>	
	CHKPNT_METHOD= <i>chkpnt_method</i>	

## Configuration to enable automatic job migration

Automatic job migration assumes that if a job is system-suspended (SSUSP) for an extended period of time, the execution host is probably heavily loaded. Configuring a queue-level or host-level migration threshold lets the job to resume on another less loaded host, and reduces the load on the original host. You can use `bmi g` at any time to override a configured migration threshold.

Configuration file	Parameter and syntax	Behavior
l sb. queues	MIG= <i>minutes</i>	
l sb. appli cations		<ul style="list-style-type: none"> <li>LSF automatically migrates jobs that have been in the SSUSP state for more than the specified number of minutes</li> <li>Specify a value of 0 to migrate jobs immediately upon suspension</li> <li>Applies to all jobs submitted to the queue</li> <li>Job-level command line migration threshold (<code>bsub -mi g</code>) overrides threshold configuration in application profile and queue. Application profile configuration overrides queue level configuration.</li> </ul>
l sb. hosts	HOST_NAME      MIG <i>host_name</i> <i>mi nut es</i>	<ul style="list-style-type: none"> <li>LSF automatically migrates jobs that have been in the SSUSP state for more than the specified number of minutes</li> <li>Specify a value of 0 to migrate jobs immediately upon suspension</li> <li>Applies to all jobs running on the host</li> </ul>

### Note:

When a host migration threshold is specified, and is lower than the value for the job, the queue, or the application, the host value is used.

## Job migration behavior

LSF migrates a job by performing the following actions:

1. Stops the job if it is running
2. Checkpoints the job if the job is checkpointable
3. Kills the job on the current host
4. Restarts or reruns the job on the first available host, bypassing all pending jobs

## Configuration to modify job migration

You can configure LSF to requeue a migrating job rather than restart or rerun the job.

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSB_MIG2PEND=1	<ul style="list-style-type: none"> <li>LSF requeues a migrating job rather than restarting or rerunning the job</li> <li>LSF requeues the job as pending in order of the original submission time and priority</li> <li>In a MultiCluster environment, LSF ignores this parameter</li> </ul>
	LSB_REQUEUE_TO_BOTTOM=1	<ul style="list-style-type: none"> <li>When LSB_MIG2PEND=1, LSF requeues a migrating job to the bottom of the queue, regardless of the original submission time and priority</li> <li>If the queue defines APS scheduling, migrated jobs keep their APS information and compete with other pending jobs based on the APS value</li> </ul>

## Job migration commands

### Commands for submission

Job migration applies to checkpointable or rerunnable jobs submitted with a migration threshold, or that have already started and are either running or suspended.

Command	Description
<code>bsub -mi g migration_threshold</code>	<ul style="list-style-type: none"> <li>Submits the job with the specified migration threshold for checkpointable or rerunnable jobs. Enables automatic job migration and specifies the migration threshold, in minutes. A value of 0 (zero) specifies that a suspended job should be migrated immediately.</li> <li>Command-level job migration threshold overrides application profile and queue-level settings.</li> <li>Where a host migration threshold is also specified, and is lower than the job value, the host value is used.</li> </ul>

### Commands to monitor

Command	Description
<code>bhist -l</code>	<ul style="list-style-type: none"> <li>Displays the actions that LSF took on a completed job, including migration to another host</li> </ul>
<code>bjobs -l</code>	<ul style="list-style-type: none"> <li>Displays information about pending, running, and suspended jobs</li> </ul>

## Commands to control

Command	Description
<code>bmi g</code>	<ul style="list-style-type: none"> <li>Migrates one or more running jobs from one host to another. The jobs must be checkpointable or rerunnable</li> <li>Checkpoints, kills, and restarts one or more checkpointable jobs—<code>bmi g</code> combines the functionality of the <code>bchkpnt</code> and <code>brstart</code> commands into a single command</li> <li>Migrates the job on demand even if you have configured queue-level or host-level migration thresholds</li> <li>When absolute job priority scheduling (APS) is configured in the queue, LSF schedules migrated jobs before pending jobs—for migrated jobs, LSF maintains the existing job priority</li> </ul>
<code>bmod -mi g migration_threshold   -mi gn</code>	<ul style="list-style-type: none"> <li>Modifies or cancels the migration threshold specified at job submission for checkpointable or rerunnable jobs. Enables or disables automatic job migration and specifies the migration threshold, in minutes. A value of 0 (zero) specifies that a suspended job should be migrated immediately.</li> <li>Command-level job migration threshold overrides application profile and queue-level settings.</li> <li>Where a host migration threshold is also specified, and is lower than the job value, the host value is used.</li> </ul>

## Commands to display configuration

Command	Description
<code>bhost s -l</code>	<ul style="list-style-type: none"> <li>Displays information about hosts configured in <code>l sb. host s</code>, including the values defined for migration thresholds in minutes</li> </ul>
<code>bqueues -l</code>	<ul style="list-style-type: none"> <li>Displays information about queues configured in <code>l sb. queues</code>, including the values defined for migration thresholds</li> </ul> <p><b>Note:</b></p> <p>The <code>bqueues</code> command displays the migration threshold in seconds—the <code>l sb. queues MIG</code> parameter defines the migration threshold in minutes.</p>
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>Displays all configured parameters and their values set in <code>l sf. conf</code> or <code>ego. conf</code> that affect <code>mbat chd</code> and <code>sbat chd</code>.</li> </ul> <p>Use a text editor to view other parameters in the <code>l sf. conf</code> or <code>ego. conf</code> configuration files.</p> <ul style="list-style-type: none"> <li>In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

# Feature: Job checkpoint and restart

The job checkpoint and restart feature enables you to stop jobs and then restart them from the point at which they stopped, which optimizes resource usage. LSF can periodically capture the state of a running job and the data required to restart it. This feature provides fault tolerance and allows LSF administrators and users to migrate jobs from one host to another to achieve load balancing.

## Contents

- About job checkpoint and restart
- Scope
- Configuration to enable job checkpoint and restart
- Job checkpoint and restart behavior
- Configuration to modify job checkpoint and restart
- Job checkpoint and restart commands

## About job checkpoint and restart


Checkpointing enables LSF users to restart a job on the same execution host or to migrate a job to a different execution host. LSF controls checkpointing and restart by means of interfaces named `echkpt` and `erestart`. By default, when a user specifies a checkpoint directory using `bsub -k` or `bmod -k` or submits a job to a queue that has a checkpoint directory specified, `echkpt` sends checkpoint instructions to an executable named `echkpt.default`.

When LSF checkpoints a job, the `echkpt` interface creates a checkpoint file in the directory `checkpoint_dir/job_ID`, and then checkpoints and resumes the job. The job continues to run, even if checkpointing fails.


When LSF restarts a stopped job, the `erestart` interface recovers job state information from the checkpoint file, including information about the execution environment, and restarts the job from the point at which the job stopped. At job restart, LSF

1. Resubmits the job to its original queue and assigns a new job ID
2. Dispatches the job when a suitable host becomes available (not necessarily the original execution host)
3. Re-creates the execution environment based on information from the checkpoint file
4. Restarts the job from its most recent checkpoint

## Default behavior (job checkpoint and restart not enabled)



## With job checkpoint and restart enabled



## Kernel-level checkpoint and restart

The operating system provides checkpoint and restart functionality that is transparent to your applications and enabled by default. To implement job checkpoint and restart at the kernel level, the LSF `echkpt` and `erestart` executables invoke operating system-specific calls.

LSF uses the default executables `echkpt.default` and `erestart.default` for kernel-level checkpoint and restart.

## User-level checkpoint and restart

For systems that do not support kernel-level checkpoint and restart, LSF provides a job checkpoint and restart implementation that is transparent to your applications and does not require you to rewrite code. User-level job checkpoint and restart is enabled by linking your application files to the LSF checkpoint libraries in `LSF_LIBDIR`. LSF uses the default executables `echkpt.default` and `erestart.default` for user-level checkpoint and restart.

## Application-level checkpoint and restart

Different applications have different checkpointing implementations that require the use of customized external executables (`echkpt.application` and `erestart.application`). Application-level checkpoint and restart enables you to configure LSF to use specific `echkpt.application` and `erestart.application` executables for a job, queue, or cluster. You can write customized checkpoint and restart executables for each application that you use.

LSF uses a combination of corresponding checkpoint and restart executables. For example, if you use `echkpt.fluent` to checkpoint a particular job, LSF will use `erestart.fluent` to restart the checkpointed job. You cannot override this behavior or configure LSF to use a specific restart executable.

## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"><li>Kernel-level checkpoint and restart using the LSF checkpoint libraries works only with supported operating system versions and architecture for:<ul style="list-style-type: none"><li>SGI IRIX 6.4 and later</li><li>SGI Altix ProPack 3 and later</li></ul></li></ul>
Job types	<ul style="list-style-type: none"><li>Non-interactive batch jobs submitted with <code>bsub</code> or <code>bmod</code></li><li>Non-interactive batch jobs, including chunk jobs, checkpointed with <code>bchkpnt</code></li><li>Non-interactive batch jobs migrated with <code>bmi g</code></li><li>Non-interactive batch jobs restarted with <code>brstart</code></li></ul>

Applicability	Details
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster, or the correct type of account mapping must be enabled. <ul style="list-style-type: none"> <li>• For a mixed UNIX/Windows cluster, UNIX/Windows user account mapping must be enabled.</li> <li>• For a cluster with a non-uniform user name space, between-host account mapping must be enabled.</li> <li>• For a MultiCluster environment with a non-uniform user name space, cross-cluster user account mapping must be enabled.</li> </ul> </li> <li>• The checkpoint and restart executables run under the user account of the user who submits the job. User accounts must have the correct permissions to <ul style="list-style-type: none"> <li>• Successfully run executables located in LSF_SERVERDIR or LSB_ECHKPNT_METHOD_DIR</li> <li>• Write to the checkpoint directory</li> </ul> </li> <li>• The <code>erestart.application</code> executable must have access to the original command line used to submit the job.</li> <li>• For user-level checkpoint and restart, you must have access to your application object (.o) files.</li> <li>• To allow restart of a checkpointed job on a different host than the host on which the job originally ran, both the original and the new hosts must: <ul style="list-style-type: none"> <li>• Be binary compatible</li> <li>• Run the same dot version of the operating system for predictable results</li> <li>• Have network connectivity and read/execute permissions to the checkpoint and restart executables (in LSF_SERVERDIR by default)</li> <li>• Have network connectivity and read/write permissions to the checkpoint directory and the checkpoint file</li> <li>• Have access to all files open during job execution so that LSF can locate them using an absolute path name</li> </ul> </li> </ul>
Limitations	<ul style="list-style-type: none"> <li>• <code>bmod</code> cannot change the <code>echkpnt</code> and <code>erestart</code> executables associated with a job.</li> <li>• Linux 32, AIX, and HP platforms with NFS (network file systems), checkpoint directories (including path and file name) must be shorter than 1000 characters.</li> <li>• Linux 64 with NFS (network file systems), checkpoint directories (including path and file name) must be shorter than 2000 characters.</li> </ul>

## Configuration to enable job checkpoint and restart

The job checkpoint and restart feature requires that a job be made checkpointable at the job or queue level. LSF users can make jobs checkpointable by submitting jobs using `bsub -k` and specifying a checkpoint directory. Queue administrators can make all jobs in a queue checkpointable by specifying a checkpoint directory for the queue.

Configuration file	Parameter and syntax	Behavior
l sb. queues	CHKPNT= <i>chkpnt_dir</i> [ <i>chkpnt_period</i> ]	<ul style="list-style-type: none"> <li>All jobs submitted to the queue are checkpointable. LSF writes the checkpoint files, which contain job state information, to the checkpoint directory. The checkpoint directory can contain checkpoint files for multiple jobs.</li> <li>The specified checkpoint directory must already exist. LSF will not create the checkpoint directory.</li> <li>The user account that submits the job must have read and write permissions for the checkpoint directory.</li> <li>For the job to restart on another execution host, both the original and new hosts must have network connectivity to the checkpoint directory.</li> <li>If the queue administrator specifies a checkpoint period, in minutes, LSF creates a checkpoint file every <i>chkpnt_period</i> during job execution.</li> </ul> <p><b>Note:</b></p> <p>There is no default value for checkpoint period. You must specify a checkpoint period if you want to enable periodic checkpointing.</p> <ul style="list-style-type: none"> <li>If a user specifies a checkpoint directory and checkpoint period at the job level with <code>bsub -k</code>, the job-level values override the queue-level values.</li> <li>The file path of the checkpoint directory can contain up to 4000 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.</li> </ul>

l sb. appli cation  
s

## Configuration to enable kernel-level checkpoint and restart

Kernel-level checkpoint and restart is enabled by default. LSF users make a job checkpointable by either submitting a job using `bsub -k` and specifying a checkpoint directory or by submitting a job to a queue that defines a checkpoint directory for the CHKPNT parameter.

## Configuration to enable user-level checkpoint and restart

To enable user-level checkpoint and restart, you must link your application object files to the LSF checkpoint libraries provided in `LSF_LIBDIR`. You do not have to change any code within your application. For instructions on how to link application files, see the *Platform LSF Programmer's Guide*.

## Configuration to enable application-level checkpoint and restart

Application-level checkpointing requires the presence of at least one `echkptn`. *application* executable in the directory specified by the parameter `LSF_SERVERDIR` in `lsf.conf`. Each `echkptn`. *application* must have a corresponding `erestart`. *application*.

---

### Important:

The `erestart`.*application* executable must:

- Have access to the command line used to submit or modify the job
  - Exit with a return value without running an application; the `erestart` interface runs the application to restart the job
- 

Executable file	UNIX naming convention	Windows naming convention
<code>echkptn</code>	<code>LSF_SERVERDIR/echkptn. application</code>	<code>LSF_SERVERDIR\echkptn. application.exe</code> <code>LSF_SERVERDIR\echkptn. application.bat</code>
<code>erestart</code>	<code>LSF_SERVERDIR/erestart. application</code>	<code>LSF_SERVERDIR</code> <code>\erestart. application.exe</code> <code>LSF_SERVERDIR</code> <code>\erestart. application.bat</code>

---



---

### Restriction:

The names `echkptn.default` and `erestart.default` are reserved. Do not use these names for application-level checkpoint and restart executables.

Valid file names contain only alphanumeric characters, underscores (`_`), and hyphens (`-`).

---

For application-level checkpoint and restart, once the `LSF_SERVERDIR` contains one or more checkpoint and restart executables, users can specify the external checkpoint executable associated with each checkpointable job they submit. At restart, LSF invokes the corresponding external restart executable.

## Requirements for application-level checkpoint and restart executables

- The executables must be written in C or Fortran.
- The directory/name combinations must be unique within the cluster. For example, you can write two different checkpoint executables with the name `echkptn.fluent` and save them as `LSF_SERVERDIR/echkptn.fluent` and `my_execs/echkptn.fluent`. To run checkpoint and restart executables from a directory other than `LSF_SERVERDIR`, you must configure the parameter `LSB_ECHKPNT_METHOD_DIR` in `lsf.conf`.
- Your executables must return the following values.

- An `echkpt.application` must return a value of 0 when checkpointing succeeds and a non-zero value when checkpointing fails.
  - The `erestart` interface provided with LSF restarts the job using a restart command that `erestart.application` writes to a file. The return value indicates whether `erestart.application` successfully writes the parameter definition `LSB_RESTART_CMD=restart_command` to the file `checkpoint_dir/job_ID/.restart_cmd`.
    - A non-zero value indicates that `erestart.application` failed to write to the `.restart_cmd` file.
    - A return value of 0 indicates that `erestart.application` successfully wrote to the `.restart_cmd` file, or that the executable intentionally did not write to the file.
  - Your executables must recognize the syntax used by the `echkpt` and `erestart` interfaces, which communicate with your executables by means of a common syntax.
    - `echkpt.application` syntax:  
`echkpt [-c] [-f] [-k | -s] [-d checkpoint_dir] [-x] process_group_ID`
- Restriction:**
- The `-k` and `-s` options are mutually exclusive.
- `erestart.application` syntax:  
`erestart [-c] [-f] checkpoint_dir`

Option or variable	Description	Operating systems
-c	Copies all files in use by the checkpointed process to the checkpoint directory.	Some, such as SGI systems running IRIX and Altix
-f	Forces a job to be checkpointed even under non-checkpointable conditions, which are specific to the checkpoint implementation used. This option could create checkpoint files that do not provide for successful restart.	Some, such as SGI systems running IRIX and Altix
-k	Kills a job after successful checkpointing. If checkpoint fails, the job continues to run.	All operating systems that LSF supports
-s	Stops a job after successful checkpointing. If checkpoint fails, the job continues to run.	Some, such as SGI systems running IRIX and Altix
-d <i>checkpoint_dir</i>	Specifies the checkpoint directory as a relative or absolute path.	All operating systems that LSF supports
-x	Identifies the <code>cpr</code> (checkpoint and restart) process as type <code>HID</code> . This identifies the set of processes to checkpoint as a process hierarchy (tree) rooted at the current <code>PID</code> .	Some, such as SGI systems running IRIX and Altix
<i>process_group_ID</i>	ID of the process or process group to checkpoint.	All operating systems that LSF supports

## Job checkpoint and restart behavior

LSF invokes the `echkpt` interface when a job is

- Automatically checkpointed based on a configured checkpoint period
- Manually checkpointed with `bchkpnt`
- Migrated to a new host with `bmi g`

After checkpointing, LSF invokes the `erestart` interface to restart the job. LSF also invokes the `erestart` interface when a user

- Manually restarts a job using `brstart`
- Migrates the job to a new host using `bmi g`

All checkpoint and restart executables run under the user account of the user who submits the job.

---

### Note:

By default, LSF redirects standard error and standard output to `/dev/null` and discards the data.

---

## Checkpoint directory and files

LSF identifies checkpoint files by the checkpoint directory and job ID. For example:

```
bsub -k my_dir
Job <123> is submitted to default queue <default>
```

LSF writes the checkpoint file to `my_dir/123`.

LSF maintains all of the checkpoint files for a single job in one location. When a job restarts, LSF creates both a new subdirectory based on the new job ID and a symbolic link from the old to the new directory. For example, when job 123 restarts on a new host as job 456, LSF creates `my_dir/456` and a symbolic link from `my_dir/123` to `my_dir/456`.

The file path of the checkpoint directory can contain up to 4000 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.

## Precedence of job, queue, application, and cluster-level checkpoint values

LSF handles checkpoint and restart values as follows:

1. *Checkpoint directory and checkpoint period*—values specified at the job level override values for the queue. Values specified in an application profile setting overrides queue level configuration.

If checkpoint-related configuration is specified in the queue, application profile, and at job level:

- Application-level and job-level parameters are merged. If the same parameter is defined at both job-level and in the application profile, the job-level value overrides the application profile value.
  - The merged result of job-level and application profile settings override queue-level configuration.
2. *Checkpoint and restart executables*—the value for `checkpoint_method` specified at the job level overrides the application-level `CHKPNT_METHOD`, and the cluster-level value for `LSB_ECHKPNT_METHOD` specified in `lsf.conf` or as an environment variable.
  3. *Configuration parameters and environment variables*—values specified as environment variables override the values specified in `lsf.conf`

If the command line is...	And...	Then...
<code>bsub -k "my_dir 240"</code>	In <code>lsb.queues</code> , <code>CHKPNT=other_dir 360</code>	<ul style="list-style-type: none"> <li>LSF saves the checkpoint file to <code>my_dir/job_ID</code> every 240 minutes</li> </ul>
<code>bsub -k "my_dir fluent"</code>	In <code>lsf.conf</code> , <code>LSB_ECHKPNT_METHOD=myapp</code>	<ul style="list-style-type: none"> <li>LSF invokes <code>echkpnt.fluent</code> at job checkpoint and <code>erestart.fluent</code> at job restart</li> </ul>
<code>bsub -k "my_dir"</code>	In <code>lsb.applications</code> , <code>CHKPNT_PERIOD=360</code>	<ul style="list-style-type: none"> <li>LSF saves the checkpoint file to <code>my_dir/job_ID</code> every 360 minutes</li> </ul>
<code>bsub -k "240"</code>	In <code>lsb.applications</code> , <code>CHKPNT_DIR=app_dir</code> <code>CHKPNT_PERIOD=360</code>  In <code>lsb.queues</code> , <code>CHKPNT=other_dir</code>	<ul style="list-style-type: none"> <li>LSF saves the checkpoint file to <code>app_dir/job_ID</code> every 240 minutes</li> </ul>

## Configuration to modify job checkpoint and restart

There are configuration parameters that modify various aspects of job checkpoint and restart behavior by:

- Specifying mandatory application-level checkpoint and restart executables that apply to all checkpointable batch jobs in the cluster
- Specifying the directory that contains customized application-level checkpoint and restart executables
- Saving standard output and standard error to files in the checkpoint directory
- Automatically checkpointing jobs before suspending or terminating them
- For Cray systems only, copying all open job files to the checkpoint directory

## Configuration to specify mandatory application-level executables

You can specify mandatory checkpoint and restart executables by defining the parameter `LSB_ECHKPNT_METHOD` in `lsf.conf` or as an environment variable.

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSB_ECHKPNT_METHOD=" <i>echknt_application</i> "	<ul style="list-style-type: none"> <li>The specified <i>echknt</i> runs for all batch jobs submitted to the cluster. At restart, the corresponding <i>erestart</i> runs.</li> <li>For example, if <code>LSB_ECHKPNT_METHOD=fluent</code>, at checkpoint, LSF runs <code>echknt.fluent</code> and at restart, LSF runs <code>erestart.fluent</code>.</li> <li>If an LSF user specifies a different <i>echknt_application</i> at the job level using <code>bsub -k</code> or <code>bmod -k</code>, the job level value overrides the value in <code>lsf.conf</code>.</li> </ul>

## Configuration to specify the directory for application-level executables

By default, LSF looks for application-level checkpoint and restart executables in `LSF_SERVERDIR`. You can modify this behavior by specifying a different directory as an environment variable or in `lsf.conf`.

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSB_ECHKPNT_METHOD_DIR= <i>path</i>	<ul style="list-style-type: none"> <li>Specifies the absolute path to the directory that contains the <code>echknt.application</code> and <code>erestart.application</code> executables</li> <li>User accounts that run these executables must have the correct permissions for the <code>LSB_ECHKPNT_METHOD_DIR</code> directory.</li> </ul>

## Configuration to save standard output and standard error

By default, LSF redirects the standard output and standard error from checkpoint and restart executables to `/dev/null` and discards the data. You can modify this behavior by defining the parameter `LSB_ECHKPNT_KEEP_OUTPUT` as an environment variable or in `lsf.conf`.

Configuration file	Parameter and syntax	Behavior
lsf.conf	LSB_ECHKPNT_KEEP_OUTPUT=y	<ul style="list-style-type: none"> <li>The stdout and stderr for <code>echknt.application</code> or <code>echknt.default</code> are redirected to <code>checkpoint_dir/job_ID/</code> <ul style="list-style-type: none"> <li><code>echknt.out</code></li> <li><code>echknt.err</code></li> </ul> </li> <li>The stdout and stderr for <code>erestart.application</code> or <code>erestart.default</code> are redirected to <code>checkpoint_dir/job_ID/</code> <ul style="list-style-type: none"> <li><code>erestart.out</code></li> <li><code>erestart.err</code></li> </ul> </li> </ul>

## Configuration to checkpoint jobs before suspending or terminating them

LSF administrators can configure LSF at the queue level to checkpoint jobs before suspending or terminating them.

Configuration file	Parameter and syntax	Behavior
lsb.queues	JOB_CONTROLS=SUSPEND CHKPNT TERMINATE	<ul style="list-style-type: none"> <li>LSF checkpoints jobs before suspending or terminating them</li> <li>When suspending a job, LSF checkpoints the job and then stops it by sending the SIGSTOP signal</li> <li>When terminating a job, LSF checkpoints the job and then kills it</li> </ul>

## Configuration to copy open job files to the checkpoint directory

For hosts that use the Cray operating system, LSF administrators can configure LSF at the host level to copy all open job files to the checkpoint directory every time the job is checkpointed.

Configuration file	Parameter and syntax	Behavior
lsb.hosts	HOST_NAME CHKPNT <i>host_name</i> C	<ul style="list-style-type: none"> <li>LSF copies all open job files to the checkpoint directory when a job is checkpointed</li> </ul>

## Job checkpoint and restart commands

### Commands for submission

Command	Description
<code>bsub -k "checkpoint_dir [checkpoint_period] [method=echkpt_application]"</code>	<ul style="list-style-type: none"> <li>Specifies a relative or absolute path for the checkpoint directory and makes the job checkpointable.</li> <li>If the specified checkpoint directory does not already exist, LSF creates the checkpoint directory.</li> <li>If a user specifies a checkpoint period (in minutes), LSF creates a checkpoint file every <i>chkpt_period</i> during job execution.</li> <li>The command-line values for the checkpoint directory and checkpoint period override the values specified for the queue.</li> <li>If a user specifies an <i>echkpt_application</i>, LSF runs the corresponding restart executable when the job restarts. For example, for <code>bsub -k "my_dir method=fluent"</code> LSF runs <code>echkpt.fluent</code> at job checkpoint and <code>erestart.fluent</code> at job restart.</li> <li>The command-line value for <i>echkpt_application</i> overrides the value specified by <code>LSB_ECHKPNT_METHOD</code> in <code>lsf.conf</code> or as an environment variable. Users can override <code>LSB_ECHKPNT_METHOD</code> and use the default checkpoint and restart executables by defining <code>method=default</code>.</li> </ul>

## Commands to monitor

Command	Description
<code>bacct -l</code>	<ul style="list-style-type: none"> <li>Displays accounting statistics for finished jobs, including termination reasons. <code>TERM_CHKPNT</code> indicates that a job was checkpointed and killed.</li> <li>If <code>JOB_CONTROL</code> is defined for a queue, LSF does not display the result of the action.</li> </ul>
<code>bhist -l</code>	<ul style="list-style-type: none"> <li>Displays the actions that LSF took on a completed job, including job checkpoint, restart, and migration to another host.</li> </ul>
<code>bjobs -l</code>	<ul style="list-style-type: none"> <li>Displays information about pending, running, and suspended jobs, including the checkpoint directory, the checkpoint period, and the checkpoint method (either <i>application</i> or default).</li> </ul>

## Commands to control

Command	Description
<code>bmod -k "checkpoint_dir [checkpoint_period] [method=echkpt_application]"</code>	<ul style="list-style-type: none"> <li>Resubmits a job and changes the checkpoint directory, checkpoint period, and the checkpoint and restart executables associated with the job.</li> </ul>
<code>bmod -kn</code>	<ul style="list-style-type: none"> <li>Dissociates the checkpoint directory from a job, which makes the job no longer checkpointable.</li> </ul>

Command	Description
<code>bchkpnt</code>	<ul style="list-style-type: none"> <li>• Checkpoints the most recently submitted checkpointable job. Users can specify particular jobs to checkpoint by including various <code>bchkpnt</code> options.</li> </ul>
<code>bchkpnt -p <i>checkpoint_period job_ID</i></code>	<ul style="list-style-type: none"> <li>• Checkpoints a job immediately and changes the checkpoint period for the job.</li> </ul>
<code>bchkpnt -k <i>job_ID</i></code>	<ul style="list-style-type: none"> <li>• Checkpoints a job immediately and kills the job.</li> </ul>
<code>bchkpnt -p 0 <i>job_ID</i></code>	<ul style="list-style-type: none"> <li>• Checkpoints a job immediately and disables periodic checkpointing.</li> </ul>
<code>brstart</code>	<ul style="list-style-type: none"> <li>• Restarts a checkpointed job on the first available host.</li> </ul>
<code>brstart -m</code>	<ul style="list-style-type: none"> <li>• Restarts a checkpointed job on the specified host or host group.</li> </ul>
<code>bmi g</code>	<ul style="list-style-type: none"> <li>• Migrates one or more running jobs from one host to another. The jobs must be checkpointable or rerunnable.</li> <li>• Checkpoints, kills, and restarts one or more checkpointable jobs.</li> </ul>


## Commands to display configuration

Command	Description
<code>bqueues -l</code>	<ul style="list-style-type: none"> <li>• Displays information about queues configured in <code>lsb.queues</code>, including the values defined for checkpoint directory and checkpoint period.</li> </ul> <p><b>Note:</b></p> <p>The <code>bqueues</code> command displays the checkpoint period in seconds; the <code>lsb.queues</code> <code>CHKPNT</code> parameter defines the checkpoint period in minutes.</p>
<code>badmi n showconf</code>	<ul style="list-style-type: none"> <li>• Displays all configured parameters and their values set in <code>lsf.conf</code> or <code>ego.conf</code> that affect <code>mbatchd</code> and <code>sbatchd</code>.</li> </ul> <p>Use a text editor to view other parameters in the <code>lsf.conf</code> or <code>ego.conf</code> configuration files.</p> <ul style="list-style-type: none"> <li>• In a MultiCluster environment, <code>badmi n showconf</code> only displays the parameters of daemons on the local cluster.</li> </ul>

# Feature: Resizable Jobs

Enabling resizable jobs allows LSF to run a job with minimum and maximum slots requested and have it dynamically use the number of slots available at any given time.

By default, if a job specifies minimum and maximum slots requests (`bsub -n min, max`), LSF makes a one time allocation and schedules the job. You can configure resizable jobs, where LSF dispatches jobs as long as minimum slot request is satisfied. After the job successfully starts, LSF continues to schedule and allocate additional resources to satisfy the maximum slot request for the job. For example, a job asks for `-n 4,32` processors. The Job starts to run and gets 20 slots at time  $t_0$ . After that, LSF continues to allocate more job resources; for instance, 4 slots to jobs at time  $t_1$ . Then, another 8 slots at time  $t_2$ , which finally satisfies 32 slot requirement.



## About resizable jobs

### Resizable Job

A job whose job slot allocation can grow and shrink during its run time. The allocation change request may be triggered automatically or by the `resize` command. For example, after the job starts, you can explicitly cancel resize allocation requests or have the job release idle resources back to the LSF.

### Autoresizable job

A resizable job with a minimum and maximum slot request. LSF automatically schedules and allocates additional resources to satisfy job maximum request as the job runs.

For autoresizable jobs, LSF automatically calculates the pending allocation requests. The maximum pending allocation request is calculated based on the maximum number of requested slots minus the number of allocated slots. And the minimum pending allocation request is always 1. Because the job is running and its previous minimum request is already satisfied, LSF is able to allocate any number of additional slots to the running job. For instance, if job requests `-n 4, 32`, if LSF allocates 20 slots to the job initially, its active pending allocation request is 1 to 12. 1 is minimum slot request. 12 is maximum slot request. After LSF assigns another 4 slots, the pending allocation request is 1 to 8.

## Pending allocation request

An additional resource request attached to a resizable job. Only running jobs can have pending allocation requests. At any given time, the job only has one allocation request.

LSF creates a new pending allocation request and schedules it after job physically starts on the remote host (after LSF receives the `JOB_EXECUTE` event from `sbat chd`) or notification successfully completes.

## Notification command

A notification command is an executable that is invoked on the first execution host of a job in response to an allocation (grow or shrink) event. It can be used to inform the running application for allocation change. Due to the various implementations of applications, each resizable application may have its own notification command provided by the application developer.

The notification command runs under the same user ID environment, home, and working directory as the actual job. The standard input, output, and error of the program are redirected to the NULL device. If the notification command is not in the user's normal execution path (the `SPATH` variable), the full path name of the command must be specified.

A notification command exits with one of the following values:

```
LSB_RESIZE_NOTIFY_OK=0
```

```
LSB_RESIZE_NOTIFY_FAIL=1
```

LSF sets these environment variables in notification command environment.

`LSB_RESIZE_NOTIFY_OK` indicates notification succeeds. For allocation both "grow" and "shrink" events, LSF updates the job allocation to reflect the new allocation.

`LSB_RESIZE_NOTIFY_FAIL` indicates notification failure. For allocation "grow" event, LSF reschedules the pending allocation request. For allocation "shrink" event, LSF fails the allocation release request.

## Configuration to enable resizable jobs

The resizable jobs feature is enabled by defining an application profile using the `RESIZABLE_JOBS` parameter in `lsb. applications`.

Configuration file	Parameter and syntax	Behavior
lsb. applications	RESIZABLE_JOBS=Y N auto	<ul style="list-style-type: none"> <li>When RESIZABLE_JOBS=Y jobs submitted to the application profile are resizable.</li> <li>When RESIZABLE_JOBS=auto jobs submitted to the application profile are automatically resizable.</li> <li>To enable cluster-wide resizable behavior by default, define RESIZABLE_JOBS=Y in the default application profile.</li> </ul>
	RESIZE_NOTIFY_CMD=notify_cmd	<p>RESIZE_NOTIFY_CMD specifies an application-level resize notification command. The resize notification command is invoked on the first execution host of a running resizable job when a resize event occurs, including releasing resources and adding resources.</p> <p>LSF set appropriate environment variables to indicate the event type and before running the notification command.</p>

## Configuration to modify resizable job behavior

There is no configuration to modify resizable job behavior.

## Resizable job commands

### Commands for submission

Command	Description
<code>bsub -app application_profile_name</code>	Submits the job to the specified application profile configured for resizable jobs
<code>bsub -app application_profile_name -rnc resize_notification_command</code>	Submits the job to the specified application profile configured for resizable jobs, with the specified resize notification command. The job-level resize notification command overrides the application-level RESIZE_NOTIFY_CMD setting.
<code>bsub -ar -app application_profile_name</code>	Submits the job to the specified application profile configured for resizable jobs, as an autoresizable job. The job-level -ar option overrides the application-level RESIZABLE_JOBS setting. For example, if the application profile is not autoresizable, job level <code>bsub -ar</code> will make the job autoresizable.

### Commands to monitor

Command	Description
<code>bacct</code>	<ul style="list-style-type: none"> <li>Displays resize notification command.</li> <li>Displays resize allocation changes.</li> </ul>
<code>bhist</code>	<ul style="list-style-type: none"> <li>Displays resize notification command.</li> <li>Displays resize allocation changes.</li> <li>Displays the job-level autoresizable attribute.</li> </ul>

Command	Description
<code>bj obs -l</code>	<ul style="list-style-type: none"> <li>• Displays resize notification command.</li> <li>• Displays resize allocation changes.</li> <li>• Displays the job-level autoresizeable attribute.</li> <li>• Displays pending resize allocation requests.</li> </ul>

## Commands to control

Command	Description
<code>bmod -ar   -arn</code>	Add or remove the job-level autoresizeable attribute. <code>bmod</code> only updates the autoresizeable attribute for pending jobs.
<code>bmod -rnc</code> <code>resize_notification_cmd   -rncn</code>	Modify or remove resize notification command for submitted job.
<code>bresize release</code>	<p>Release allocated resources from a running resizable job.</p> <ul style="list-style-type: none"> <li>• Release all slots except one slot from the first execution node.</li> <li>• Release all hosts except the first execution node.</li> <li>• Release a list of hosts and different slots for each explicitly.</li> <li>• Specify a resize notification command to be invoked on the first execution host of the job.</li> </ul> <p>To release resources from a running job, the job must be submitted to an application profile configured as resizable.</p> <ul style="list-style-type: none"> <li>• By default, only cluster administrators, queue administrators, root and the job owner are allowed to run <code>bresize</code> to change job allocations.</li> <li>• User group administrators are allowed to run <code>bresize</code> to change the allocation of jobs within their user groups.</li> </ul>
<code>bresize cancel</code>	Cancel a pending allocation request. The active pending allocation request is from <code>r</code> auto-resize request generated by LSF automatically. If job does not have active pending request, the command fails with an error message.
<code>bresize release -rnc</code> <code>resize_notification_cmd</code>	<p>Specify or remove a resize notification command. The resize notification is invoked on the job first execution node. The resize notification command only applies to the release request and overrides the corresponding resize notification parameters defined in either the application profile (<code>RESIZE_NOTIFY_CMD</code> in <code>lsb. applications</code>) and job level (<code>bsub -rnc notify_cmd</code>).</p> <p>If the resize notification command completes successfully, LSF considers the allocation release done and updates the job allocation. If the resize notification command fails, LSF does not update the job allocation.</p> <p>The <code>resize_notification_cmd</code> specifies the name of the executable to be invoked on the first execution host when the job's allocation has been modified.</p> <p>The resize notification command runs under the user account of job.</p> <p><code>-rncn</code> removes the resize notification command in both job-level and application-level.</p>

Command	Description
<code>bresize release -c</code>	<p>By default, if the job has an active pending allocation request, LSF does not allow users to release resource. Use the <code>bresize release -c</code> command to cancel the active pending resource request when releasing slots from existing allocation. By default, the command only releases slots.</p> <p>If a job still has an active pending allocation request, but you do not want to allocate more resources to the job, use the <code>bresize cancel</code> command to cancel allocation request.</p> <p>Only the job owner, cluster administrators, queue administrators, user group administrators, and root are allowed to cancel pending resource allocation requests.</p>

## Commands to display configuration

Command	Description
<code>bapp</code>	Displays the value of parameters defined in <code>lsb. applications</code> .

## Feature: External load indices

External load indices report the values of dynamic external resources. A dynamic external resource is a customer-defined resource with a numeric value that changes over time, such as the space available in a directory. Use the external load indices feature to make the values of dynamic external resources available to LSF, or to override the values reported for an LSF built-in load index.

### About external load indices

LSF bases job scheduling and host selection decisions on the resources available within your cluster. A *resource* is a characteristic of a host (such as available memory) or a cluster (such as the number of shared software licenses) that LSF uses to make job scheduling and host selection decisions.

A *static resource* has a value that does not change, such as a host's maximum swap space. A *dynamic resource* has a numeric value that changes over time, such as a host's currently available swap space. *Load indices* supply the values of dynamic resources to a host's load information manager (LIM), which periodically collects those values.

LSF has a number of built-in load indices that measure the values of dynamic, *host-based resources* (resources that exist on a single host)—for example, CPU, memory, disk space, and I/O. You can also define *shared resources* (resources that hosts in your cluster share, such as floating software licenses) and make these values available to LSF to use for job scheduling decisions.

If you have specific workload or resource requirements at your site, the LSF administrator can define *external resources*. You can use both built-in and external resources for LSF job scheduling and host selection.

To supply the LIM with the values of dynamic external resources, either host-based or shared, the LSF administrator writes a site-specific executable called an *external load information manager* (e*l i m*) executable. The LSF administrator programs the e*l i m* to define external load indices, populate those indices with the values of dynamic external resources, and return the indices and their values to stdout. An e*l i m* can be as simple as a small script, or as complicated as a sophisticated C program.

---



#### Note:

LSF does not include a default e*l i m*; you should write your own executable to meet the requirements of your site.



---

The following illustrations show the benefits of using the external load indices feature. In these examples, jobs require the use of floating software licenses.

## Default behavior (feature not enabled)



## With external load indices enabled



## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX</li> <li>• Windows</li> <li>• A mix of UNIX and Windows hosts</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> <li>• All <code>elim</code> executables run under the same user account as the load information manager (LIM)—by default, the LSF administrator (<code>lsfadmin</code>) account.</li> <li>• External dynamic resources (host-based or shared) must be defined in <code>lsf.shared</code>.</li> </ul>

## Configuration to enable external load indices

To enable the use of external load indices, you must

- Define the dynamic external resources in `lsf.shared`. By default, these resources are host-based (local to each host) until the LSF administrator configures a resource-to-host-mapping in the ResourceMap section of `lsf.cluster.cluster_name`. The presence of the dynamic external resource in `lsf.shared` and `lsf.cluster.cluster_name` triggers LSF to start the `elim` executables.
- Map the external resources to hosts in your cluster in `lsf.cluster.cluster_name`.

### Important:

You must run the command **lsadmin reconfig** followed by **lsadmin mbdrestart** to apply changes.

- Create one or more `elim` executables in the directory specified by the parameter `LSF_SERVERDIR`. LSF does not include a default `elim`; you should write your own executable to meet the requirements of your site. The section [Create an elim executable](#) provides guidelines for writing an `elim`.

## Define a dynamic external resource

To define a dynamic external resource for which `elim` collects an external load index value, define the following parameters in the Resource section of `lsf.shared`:

Configuration file	Parameter and syntax	Description
lsf.shared	RESOURCENAME <i>resource_name</i>	<ul style="list-style-type: none"> <li>Specifies the name of the external resource.</li> </ul>
	TYPE Numeric	<ul style="list-style-type: none"> <li>Specifies the type of external resource: Numeric resources have numeric values.</li> <li>Specify Numeric for all dynamic resources.</li> </ul>
	INTERVAL <i>seconds</i>	<ul style="list-style-type: none"> <li>Specifies the interval for data collection by an <code>elim</code>.</li> <li>For numeric resources, defining an interval identifies the resource as a dynamic resource with a corresponding external load index.</li> </ul> <p><b>Important:</b></p> <p>You must specify an interval: LSF treats a numeric resource with no interval as a static resource and, therefore, does not collect load index values for that resource.</p>
	INCREASING Y   N	<ul style="list-style-type: none"> <li>Specifies whether a larger value indicates a greater load.               <ul style="list-style-type: none"> <li>Y—a larger value indicates a greater load. For example, if you define an external load index for the number of shared software licenses <i>in use</i>, the larger the value, the heavier the load.</li> <li>N—a larger value indicates a lighter load. For example, if you define an external load index for the number of shared software licenses <i>currently available</i>, the larger the value, the lighter the load, and the more licenses are available.</li> </ul> </li> </ul>
	RELEASE Y   N	<ul style="list-style-type: none"> <li>For shared resources only, specifies whether LSF releases the resource when a job that uses the resource is suspended.               <ul style="list-style-type: none"> <li>Y—Releases the resource when a job is suspended.</li> <li>N—Holds the resource when a job is suspended.</li> </ul> </li> </ul>
	DESCRIPTION <i>description</i>	<ul style="list-style-type: none"> <li>Brief description of the resource. Enter a description that enables you to easily identify the type and purpose of the resource.</li> <li>The <code>lsinfo</code> command and the <code>ls_info()</code> API call return the contents of the DESCRIPTION parameter.</li> </ul>

## Map an external resource

Once external resources are defined in `lsf.shared`, they must be mapped to hosts in the ResourceMap section of `lsf.cluster.cluster_name`.

Configuration file	Parameter and syntax	Default behavior
<code>lsf.cluster.cluster_name</code>	RESOURCENAME <i>resource_name</i>	<ul style="list-style-type: none"> <li>Specifies the name of the external resource as defined in the Resource section of <code>lsf.shared</code>.</li> </ul>
	LOCATION	<ul style="list-style-type: none"> <li>Maps the resource to the master host only; all hosts share a single instance of the dynamic external resource.</li> <li>To prevent specific hosts from accessing the resource, use the not operator (~) and specify one or more host names. All other hosts can access the resource.</li> </ul>
	<ul style="list-style-type: none"> <li><code>[default]</code></li> </ul>	<ul style="list-style-type: none"> <li>Maps the resource to all hosts in the cluster; every host has an instance of the dynamic external resource.</li> <li>If you use the default keyword for any external resource, all <code>elim</code> executables in <code>LSF_SERVERDIR</code> run on all hosts in the cluster. For information about how to control which <code>elim</code> executables run on each host, see the section How LSF determines which hosts should run an <code>elim</code> executable.</li> </ul>
	<ul style="list-style-type: none"> <li><code>([host_name ...])   ([host_name ...] [host_name ...])</code></li> </ul>	<ul style="list-style-type: none"> <li>Maps the resource to one or more specific hosts.</li> <li>To specify sets of hosts that share a dynamic external resource, enclose each set in square brackets ([ ]) and use a space to separate each host name.</li> </ul>

## Create an elim executable

You can write one or more `elim` executables. The load index names defined in your `elim` executables must be the same as the external resource names defined in the `lsf.shared` configuration file.

All `elim` executables must

- Be located in `LSF_SERVERDIR` and follow these naming conventions:

Operating system	Naming convention
UNIX	<code>LSF_SERVERDIR\elim.application</code>

Operating system	Naming convention
Windows	LSF_SERVERDIR\elim. <i>application.exe</i> or LSF_SERVERDIR\elim. <i>application.bat</i>

**Restriction:**

The name `elim.user` is reserved for backward compatibility. Do not use the name `elim.user` for your application-specific `elim`.

**Note:**

LSF invokes any `elim` that follows this naming convention,— move backup copies out of LSF\_SERVERDIR or choose a name that does not follow the convention. For example, use `elim_backup` instead of `elim.backup`.

- Exit upon receipt of a SIGTERM signal from the load information manager (LIM).
- Periodically output a *load update string* to stdout in the format *number\_indices index\_name index\_value [index\_name index\_value ...]* where

Value	Defines
<i>number_indices</i>	• The number of external load indices collected by the <code>elim</code> .
<i>index_name</i>	• The name of the external load index.
<i>index_value</i>	• The external load index value returned by your <code>elim</code> .

For example, the string

```
3 tmp2 47.5 ni o 344.0 licenses 5
```

reports three indices: `tmp2`, `ni o`, and `licenses`, with values 47.5, 344.0, and 5, respectively.

- The load update string must report values between `-INFINIT_LOAD` and `INFINIT_LOAD` as defined in the `lsf.h` header file.
- The `elim` should ensure that the entire load update string is written successfully to stdout. Program the `elim` to exit if it fails to write the load update string to stdout.
  - If the `elim` executable is a C program, check the return value of `printf(3s)`.
  - If the `elim` executable is a shell script, check the return code of `/bin/echo(1)`.
- If the `elim` executable is implemented as a C program, use `setbuf(3)` during initialization to send unbuffered output to stdout.
- Each LIM sends updated load information to the master LIM every 15 seconds; the `elim` executable should write the load update string at most once every 15 seconds. If the external load index values rarely change, program the `elim` to report the new values only when a change is detected.

If you map any external resource as default in `lsf.cluster.cluster_name`, all `elim` executables in LSF\_SERVERDIR run on all hosts in the cluster. If LSF\_SERVERDIR contains more than one `elim` executable, you should include a header that checks whether the `elim`

is programmed to report values for the resources expected on the host. For detailed information about using a checking header, see the section How environment variables determine elim hosts.

## Overriding built-in load indices

An `elim` executable can be used to override the value of a built-in load index. For example, if your site stores temporary files in the `/usr/tmp` directory, you might want to monitor the amount of space available in that directory. An `elim` can report the space available in the `/usr/tmp` directory as the value for the `tmp` built-in load index. However, the value reported by an `elim` must be less than the maximum size of `/usr/tmp`.

To override a built-in load index value, you must:

- Write an `elim` executable that periodically measures the value of the dynamic external resource and writes the numeric value to standard output. The external load index must correspond to a numeric, dynamic external resource as defined by `TYPE` and `INTERVAL` in `lsf.shared`.
- Configure an external resource in `lsf.shared` and map the resource in `lsf.cluster.cluster_name`, even though you are overriding a built-in load index. Use a name other than the built-in load index, for example, `mytmp` rather than `tmp`.
- Program your `elim` to output the formal name of the built-in index (for example, `r1m`, `it`, `ls`, or `swp`), *not* the resource name alias (`cpu`, `idle`, `login`, or `swap`). For example, an `elim` that collects the value of the external resource `mytmp` reports the value as `tmp` (the built-in load index) in the load update string: `1 tmp 20`.

## Setting up an ELIM to support JSDL

To support the use of Job Submission Description Language (JSDL) files at job submission, LSF collects the following load indices:

Attribute name	Attribute type	Resource name
OperatingSystemName	string	osname
OperatingSystemVersion	string	osver
CPUArchitectureName	string	cpuarch
IndividualCPUSpeed	int64	cpuspeed
IndividualNetworkBandwidth	int64	bandwidth (This is the maximum bandwidth).

The file `elim.jSDL` is automatically configured to collect these resources. To enable the use of `elim.jSDL`, uncomment the lines for these resources in the `ResourceMap` section of the file `lsf.cluster.cluster_name`.

## Example of an elim executable

See the section How environment variables determine elim hosts for an example of a simple `elim` script.

You can find additional `elim` examples in the `LSF_MISC/examples` directory. The `elim.c` file is an `elim` written in C. You can modify this example to collect the external load indices required at your site.

## External load indices behavior

### How LSF manages multiple `elim` executables

The LSF administrator can write one `elim` executable to collect multiple external load indices, or the LSF administrator can divide external load index collection among multiple `elim` executables. On each host, the load information manager (LIM) starts a master `elim` (MELIM), which manages all `elim` executables on the host and reports the external load index values to the LIM. Specifically, the MELIM

- Starts `elim` executables on the host. The LIM checks the ResourceMap section LOCATION settings (default, all, or host list) and directs the MELIM to start `elim` executables on the corresponding hosts.

---

#### Note:

If the ResourceMap section contains even one resource mapped as default, and if there are multiple `elim` executables in `LSF_SERVERDIR`, the MELIM starts all of the `elim` executables in `LSF_SERVERDIR` on all hosts in the cluster. Not all of the `elim` executables continue to run, however. Those that use a checking header could exit with `ELIM_ABORT_VALUE` if they are not programmed to report values for the resources listed in `LSF_RESOURCES`.

- Restarts an `elim` if the `elim` exits. To prevent system-wide problems in case of a fatal error in the `elim`, the maximum restart frequency is once every 90 seconds. The MELIM does *not* restart any `elim` that exits with `ELIM_ABORT_VALUE`.
- Collects the load information reported by the `elim` executables.
- Checks the syntax of load update strings before sending the information to the LIM.
- Merges the load reports from each `elim` and sends the merged load information to the LIM. If there is more than one value reported for a single resource, the MELIM reports the latest value.
- Logs its activities and data into the log file `LSF_LOGDIR/melim.log. host_name`
- Increases system reliability by buffering output from multiple `elim` executables; failure of one `elim` does not affect other `elim` executables running on the same host.

### How LSF determines which hosts should run an `elim` executable

LSF provides configuration options to ensure that your `elim` executables run only when they can report the resources values expected on a host. This maximizes system performance and simplifies the implementation of external load indices. To control which hosts run `elim` executables, you

- Must map external resource names to locations in `lsf.cluster.cluster_name`
- Optionally, use the environment variables `LSF_RESOURCES`, `LSF_MASTER`, and `ELIM_ABORT_VALUE` in your `elim` executables

## How resource mapping determines elim hosts

The following table shows how the resource mapping defined in `lsf.cluster.cluster_name` determines the hosts on which your `elim` executables start.

If the specified LOCATION is ...	Then the elim executables start on ...
<ul style="list-style-type: none"> <li><code>([all])</code>   <code>([all ~host_name ...])</code></li> </ul>	<ul style="list-style-type: none"> <li>The master host, because all hosts in the cluster (except those identified by the not operator <code>[~]</code>) share a single instance of the external resource.</li> </ul>
<ul style="list-style-type: none"> <li><code>[default]</code></li> </ul>	<ul style="list-style-type: none"> <li>Every host in the cluster, because the default setting identifies the external resource as host-based.</li> <li>If you use the default keyword for any external resource, all <code>elim</code> executables in <code>LSF_SERVERDIR</code> run on all hosts in the cluster. For information about how to program an <code>elim</code> to exit when it cannot collect information about resources on a host, see <a href="#">How environment variables determine elim hosts</a>.</li> </ul>
<ul style="list-style-type: none"> <li><code>([host_name ...])</code>   <code>([host_name ...]</code> <code>[host_name ...])</code></li> </ul>	<ul style="list-style-type: none"> <li>On the specified hosts.</li> <li>If you specify a set of hosts, the <code>elim</code> executables start on the first host in the list. For example, if the LOCATION in the ResourceMap section of <code>lsf.cluster.cluster_name</code> is <code>([hostA hostB hostC]</code> <code>[hostD hostE hostF])</code>: <ul style="list-style-type: none"> <li>LSF starts the <code>elim</code> executables on <code>hostA</code> and <code>hostD</code> to report values for the resources shared by that set of hosts.</li> <li>If the host reporting the external load index values becomes unavailable, LSF starts the <code>elim</code> executables on the next available host in the list. In this example, if <code>hostA</code> becomes unavailable, LSF starts the <code>elim</code> executables on <code>hostB</code>.</li> <li>If <code>hostA</code> becomes available again, LSF starts the <code>elim</code> executables on <code>hostA</code> and shuts down the <code>elim</code> executables on <code>hostB</code>.</li> </ul> </li> </ul>

## How environment variables determine elim hosts

If you use the default keyword for any external resource in `lsf.cluster.cluster_name`, all `elim` executables in `LSF_SERVERDIR` run on all hosts in the cluster. You can control the hosts on which your `elim` executables run by using the environment variables `LSF_MASTER`, `LSF_RESOURCES`, and `ELIM_ABORT_VALUE`. These environment variables provide a way to ensure that `elim` executables run only when they are programmed to report the values for resources expected on a host.

- LSF\_MASTER**—You can program your `elim` to check the value of the `LSF_MASTER` environment variable. The value is `Y` on the master host and `N` on all other hosts. An `elim` executable can use this parameter to check the host on which the `elim` is currently running.
- LSF\_RESOURCES**—When the LIM starts an MELIM on a host, the LIM checks the resource mapping defined in the ResourceMap section of `lsf.cluster.cluster_name`. Based on the mapping (default, all, or a host list), the LIM sets `LSF_RESOURCES` to the list of resources expected on the host. Use

LSF\_RESOURCES in a checking header to verify that an `elim` is programmed to collect values for at least one of the resources listed in LSF\_RESOURCES.

- **ELIM\_ABORT\_VALUE**—An `elim` should exit with ELIM\_ABORT\_VALUE if the `elim` is not programmed to collect values for at least one of the resources listed in LSF\_RESOURCES. The MELIM does not restart an `elim` that exits with ELIM\_ABORT\_VALUE.

The following sample code shows how to use a header to verify that an `elim` is programmed to collect load indices for the resources expected on the host. If the `elim` is not programmed to report on the requested resources, the `elim` does not need to run on the host.

```
#!/bin/sh
# list the resources that the elim can report to lim
my_resource="myrsc"
# do the check when $LSF_RESOURCES is defined by lim
if [ -n "$LSF_RESOURCES" ]; then
# check if the resources elim can report are listed in $LSF_RESOURCES
res_ok=`echo " $LSF_RESOURCES " | /bin/grep " $my_resource "`
# exit with $ELIM_ABORT_VALUE if the elim cannot report on at least
# one resource listed in $LSF_RESOURCES
  if [ "$res_ok" = "" ]; then
    exit $ELIM_ABORT_VALUE
  fi
fi
while [ 1 ];do
# set the value for resource "myrsc"
val="1"
# create an output string in the format:
# number_indices index_name index_value...
reportStr="1 $my_resource $val "
echo "$reportStr"
# wait for 30 seconds before reporting again
sleep 30
done
```

## Configuration to modify external load indices

Configuration file	Parameter and syntax	Behavior
<code>lsf.cluster</code> , <code>cluster_name</code>	<code>ELIMARGS=cmd_line_args</code>	<ul style="list-style-type: none"> <li>Specifies the command-line arguments required by an <code>elim</code> on startup.</li> </ul>
Parameters section	<code>ELIM_POLL_INTERVAL=seconds</code>	<ul style="list-style-type: none"> <li>Specifies the frequency with which the LIM samples external load index information from the MELIM.</li> </ul>
	<code>LSF_ELIM_BLOCKTIME=seconds</code>	<ul style="list-style-type: none"> <li>UNIX only. Specifies how long the MELIM waits before restarting an <code>elim</code> that fails to send a complete load update string.</li> <li>The MELIM does not restart an <code>elim</code> that exits with <code>ELIM_ABORT_VALUE</code>.</li> </ul>
	<code>LSF_ELIM_DEBUG=y</code>	<ul style="list-style-type: none"> <li>UNIX only. Used for debugging; logs all load information received from <code>elim</code> executables to the MELIM log file (<code>melim.log</code>, <code>host_name</code>).</li> </ul>
	<code>LSF_ELIM_RESTARTS=integer</code>	<ul style="list-style-type: none"> <li>UNIX only. Limits the number of times an <code>elim</code> can be restarted.</li> <li>You must also define either <code>LSF_ELIM_DEBUG</code> or <code>LSF_ELIM_BLOCKTIME</code>.</li> <li>Defining this parameter prevents an ongoing restart loop in the case of a faulty <code>elim</code>.</li> </ul>

## External load indices commands

### Commands to submit workload

Command	Description
<code>bsub -R "res_req" [-R "res_req"] ...</code>	<ul style="list-style-type: none"> <li>Runs the job on a host that meets the specified resource requirements.</li> <li>If you specify a value for a dynamic external resource in the resource requirements string, LSF uses the most recent values provided by your <code>elim</code> executables for host selection.</li> <li>For example: <ul style="list-style-type: none"> <li>Define a dynamic external resource called <code>usr_tmp</code> that represents the space available in the <code>/usr/tmp</code> directory.</li> <li>Write an <code>elim</code> executable to report the value of <code>usr_tmp</code> to LSF.</li> <li>To run the job on hosts that have more than 15 MB available in the <code>/usr/tmp</code> directory, run the command <code>bsub -R "usr_tmp &gt; 15" myjob</code></li> <li>LSF uses the external load index value for <code>usr_tmp</code> to locate a host with more than 15 MB available in the <code>/usr/tmp</code> directory.</li> </ul> </li> </ul>

## Commands to monitor

Command	Description
<code>lsl oad</code>	<ul style="list-style-type: none"> <li>Displays load information for all hosts in the cluster on a per host basis.</li> </ul>
<code>lsl oad -R "res_req"</code>	<ul style="list-style-type: none"> <li>Displays load information for specific resources.</li> </ul>

## Commands to control

Command	Description
<code>lsadmin reconfig</code> followed by <code>badmin mbdrestart</code>	<ul style="list-style-type: none"> <li>Applies changes when you modify <code>lsf. shared</code> or <code>lsf. cluster. cluster_name</code>.</li> </ul>

## Commands to display configuration

Command	Description
<code>lsinfo</code>	<ul style="list-style-type: none"> <li>Displays configuration information for all resources, including the external resources defined in <code>lsf. shared</code>.</li> </ul>
<code>lsinfo -l</code>	<ul style="list-style-type: none"> <li>Displays detailed configuration information for external resources.</li> </ul>
<code>lsinfo resource_name ...</code>	<ul style="list-style-type: none"> <li>Displays configuration information for the specified resources.</li> </ul>
<code>bhosts -s</code>	<ul style="list-style-type: none"> <li>Displays information about numeric shared resources, including which hosts that share each resource.</li> </ul>
<code>bhosts -s shared_resource_name ...</code>	<ul style="list-style-type: none"> <li>Displays configuration information for the specified resources.</li> </ul>

# Feature: External host and user groups

Use the external host and user groups feature to maintain group definitions for your site in a location external to LSF, and to import the group definitions on demand.

## About external host and user groups

LSF provides you with the option to configure host groups, user groups, or both. When the membership of a host or user group changes frequently, or when the group contains a large number of members, you can use an external executable called `egroup` to retrieve a list of members rather than having to configure the group membership manually. You can write a site-specific `egroup` executable that retrieves host or user group names and the hosts or users that belong to each group.


You can write your `egroup` executable to retrieve group members for:

- One or more host groups
- One or more user groups
- Any combination of host and user groups


LSF does not include a default `egroup`; you should write your own executable to meet the requirements of your site.

## Default behavior (feature not enabled)

The following illustrations show the benefits of using the external host and user groups feature.



## With external host and user groups enabled



## Scope

Applicability	Details
Operating system	<ul style="list-style-type: none"> <li>• UNIX</li> <li>• Windows</li> <li>• A mix of UNIX and Windows hosts</li> </ul>
Dependencies	<ul style="list-style-type: none"> <li>• UNIX and Windows user accounts must be valid on all hosts in the cluster and must have the correct permissions to successfully run jobs.</li> <li>• You must reconfigure the cluster using <code>badmin reconfig</code> each time you want to run the <code>egroup</code> executable to retrieve host or user group members.</li> </ul>
Limitations	<ul style="list-style-type: none"> <li>• The <code>egroup</code> executable works with static hosts only; you cannot use an <code>egroup</code> executable to add a dynamically added host to a host group.</li> </ul>
Not used with	<ul style="list-style-type: none"> <li>• Host groups when you have configured EGO-enabled service-level agreement (SLA) scheduling, because EGO resource groups replace LSF host groups.</li> </ul>

## Configuration to enable external host and user groups

To enable the use of external host and user groups, you must

- Define the host group in `l sb. hosts`, or the user group in `l sb. users`, and put an exclamation mark (!) in the `GROUP_MEMBER` column.
- Create an `egroup` executable in the directory specified by the parameter `LSF_SERVERDIR` in `l sf. conf`. LSF does not include a default `egroup`; you should write your own executable to meet the requirements of your site.
- Run the command `badmi n reconf i g` to reconfigure the cluster and import your external host and user groups.

## Define an external host or user group

External host groups are defined in `l sb. hosts`, and external user groups are defined in `l sb. users`. Your `egroup` executable must define the same group names that you use in the `l sb. hosts` and `l sb. users` configuration files.

Configuration file	Parameter and syntax	Default behavior
<code>l sb. hosts</code>	<p><code>GROUP_NAME GROUP_MEMBER</code></p> <p><i>hostgroup_name</i> (!)</p>	<ul style="list-style-type: none"> <li>• Enables the use of an <code>egroup</code> executable to retrieve external host group members.</li> <li>• The <i>hostgroup_name</i> specified in <code>l sb. hosts</code> must correspond to the group name defined by the <code>egroup</code> executable.</li> <li>• You can configure one or more host groups to use the <code>egroup</code> executable.</li> <li>• LSF does not support the use of external host groups that contain dynamically added hosts.</li> </ul>
<code>l sb. users</code>	<p><code>GROUP_NAME GROUP_MEMBER</code></p> <p><i>usergroup_name</i> (!)</p>	<ul style="list-style-type: none"> <li>• Enables the use of an <code>egroup</code> executable to retrieve external user group members.</li> <li>• The <i>usergroup_name</i> specified in <code>l sb. users</code> must correspond to the group name defined by the <code>egroup</code> executable.</li> <li>• You can configure one or more user groups to use the <code>egroup</code> executable.</li> </ul>

## Create an `egroup` executable

The `egroup` executable must

- Be located in `LSF_SERVERDIR` and follow these naming conventions:

Operating system	Naming convention
UNIX	LSF_SERVERDIR\egroup
Windows	LSF_SERVERDIR\egroup. exe or LSF_SERVERDIR\egroup. bat

- Run when invoked by the commands `egroup -m hostgroup_name` and `egroup -u usergroup_name`. When `mbatchd` finds an exclamation mark (!) in the `GROUP_MEMBER` column of `lsb. hosts` or `lsb. users`, `mbatchd` runs the `egroup` command to invoke your `egroup` executable.
- Output a space-delimited list of group members (hosts, users, or both) to `stdout`.
- Retrieve a list of static hosts only. You cannot use the `egroup` executable to retrieve hosts that have been dynamically added to the cluster.

The following example shows a simple `egroup` script that retrieves both host and user group members:

```
#!/bin/sh
if [ "$1"="-m" ]; then
    #host group
    if [ "$2"="linux_grp" ]; then
        #Linux hostgroup
        echo "linux01 linux 02 linux03 linux04"
    elif [ "$2"="sol_grp" ]; then
        #Solaris hostgroup
        echo "Sol02 Sol02 Sol03 Sol04"
    fi
else
    #user group
    if [ "$2"="srv_grp" ]; then
        #srvgrp user group
        echo "userA userB userC userD"
    elif [ "$2"="dev_grp" ]; then
        #devgrp user group
        echo "user1 user2 user3 user4"
    fi
fi
```

## External host and user groups behavior

On restart and reconfiguration, `mbatchd` invokes the `egroup` executable to retrieve external host and user groups and then creates the groups in memory; `mbatchd` does *not* write the groups to `lsb. hosts` or `lsb. users`. The `egroup` executable runs under the same user account as `mbatchd`. By default, this is the root account on UNIX hosts and the cluster administrator account on Windows hosts.

Once LSF creates the groups in memory, the external host and user groups work the same way as any other LSF host and user groups, including configuration and batch command usage.

## Configuration to modify external host and user groups

Not applicable: There are no parameters that modify the behavior of the `egroup` executable.

By defining additional parameters in `lsb. hosts` and `lsb. users`, however, you can configure the behavior of your external host and user groups the same way as you would for any LSF host or user group.

## External host and user groups commands

### Commands to submit workload

Command	Description
<b>bsub -m <i>host_group</i></b>	<ul style="list-style-type: none"><li>Submits a job to run on any host that belongs to the specified host group.</li></ul>
<b>bsub -G <i>user_group</i></b>	<ul style="list-style-type: none"><li>For fairshare scheduling only. Associates the job with the specified group. Specify any group that you belong to that does not contain subgroups.</li></ul>

### Commands to monitor

Although you cannot monitor `egroup` behavior directly, you can display information about running jobs for specific host or user groups.

Command	Description
<b>bjobs -m <i>host_group</i></b>	<ul style="list-style-type: none"><li>Displays jobs submitted to run on any host that belongs to the specified host group.</li></ul>
<b>bjobs -G <i>user_group</i></b>	<ul style="list-style-type: none"><li>Displays jobs submitted using <code>bsub -G</code> for the specified user group.</li></ul>
<b>bjobs -u <i>user_group</i></b>	<ul style="list-style-type: none"><li>Displays jobs submitted by users that belong to the specified user group.</li></ul>


### Commands to control

Command	Description
<b>badmin reconfig</b>	<ul style="list-style-type: none"><li>Imports group members on demand from your external host and user group lists.</li></ul>

### Commands to display configuration

Command	Description
<b>bmgroup</b>	<ul style="list-style-type: none"><li>Displays a list of host groups and the names of hosts that belong to each group.</li></ul>
<b>bugroup</b>	<ul style="list-style-type: none"><li>Displays a list of user groups and the names of users that belong to each group.</li></ul>

Use a text editor to view the `lsb.hosts` and `lsb.users` configuration files.



# Configuration Files

---

**Important:**

Specify any domain names in all uppercase letters in all configuration files.

---



# bld.license.acct

The `bld.license.acct` file is the license and accounting file for LSF License Scheduler.

## bld.license.acct structure

The license accounting log file is an ASCII file with one record per line. The fields of a record are separated by blanks. LSF License Scheduler adds a new record to the file every hour.

## File properties

### Location

The default location of this file is `LSF_SHAREDIR/db`. Use `LSF_LICENSE_ACCT_PATH` in `lsf.conf` to specify another location.

### Owner

The primary LSF License Scheduler admin is the owner of this file.

### Permissions

```
-rw-r--r--
```

## Records and fields

The fields in order of occurrence are as follows:

### timestamp (%d)

Time stamp of the logged event (in seconds since the epoch).

### type (%s)

The LSF product type. For LSF License Scheduler, this is `LICENSE_SCHEDULER`.

### version (%s)

The version of the LSF License Scheduler product.

### value (%d)

The total number of tokens that LSF License Scheduler is using.

### status (%s)

The results of the license usage check. The valid values are as follows:

- OK  
Token usage is less than the currently licensed amount
- OVERUSE  
Token usage is more than the currently licensed amount

### hash (%s)

Line encryption used to authenticate the record.

## Example record format

```
1107961731 LICENSE_SCHEDULER 7.0 0 OK 335a33c2bd9c9428140a61e57bd06da02b623a42
1107961792 LICENSE_SCHEDULER 7.0 2 OK 58e45b891f371811edfcceb6f5270059a74ee31a
1126639979 LICENSE_SCHEDULER 7.0 0 5 OK b3efd43ee28346f2d125b445fd16aa96875da35
1126640028 LICENSE_SCHEDULER 7.0 6 5 OVERUSE 2865775920372225fa7f8ed4b9a8eb2b15
```

## See also

- `LSF_LOGDIR` in `lsf.conf`
- `LSF_LICENSE_ACCT_PATH` in `lsf.conf`
- `lsf.cluster_name.license.acct`

# cshrc.lsf and profile.lsf

## About cshrc.lsf and profile.lsf

The user environment shell files `cshrc.lsf` and `profile.lsf` set the LSF operating environment on an LSF host. They define machine-dependent paths to LSF commands and libraries as environment variables:

- `cshrc.lsf` sets the C shell (`csh` or `tcsh`) user environment for LSF commands and libraries
- `profile.lsf` sets and exports the Bourne shell/Korn shell (`sh`, `ksh`, or `bash`) user environment for LSF commands and libraries

---

### Tip:

LSF Administrators should make sure that `cshrc.lsf` or `profile.lsf` are available for users to set the LSF environment variables correctly for the host type running LSF.

---

## Location

`cshrc.lsf` and `profile.lsf` are created by `lsfinstall` during installation. After installation, they are located in `LSF_CONFDIR` (`LSF_TOP/conf/`).

## Format

`cshrc.lsf` and `profile.lsf` are conventional UNIX shell scripts:

- `cshrc.lsf` runs under `/bin/csh`
- `profile.lsf` runs under `/bin/sh`

## What cshrc.lsf and profile.lsf do

`cshrc.lsf` and `profile.lsf` determine the binary type (`BINARY_TYPE`) of the host and set environment variables for the paths to the following machine-dependent LSF directories, according to the LSF version (`LSF_VERSION`) and the location of the top-level installation directory (`LSF_TOP`) defined at installation:

- `LSF_BINDIR`
- `LSF_SERVERDIR`
- `LSF_LIBDIR`
- `XLSF_UIDDIR`

`cshrc.lsf` and `profile.lsf` also set the following user environment variables:

- `LSF_ENVDIR`
- `LD_LIBRARY_PATH`
- `PATH` to include the paths to:
  - `LSF_BINDIR`
  - `LSF_SERVERDIR`
- `MANPATH` to include the path to the LSF man pages

## If Platform EGO is enabled

If Platform EGO is enabled in the LSF cluster (`LSF_ENABLE_EGO=Y` and `LSF_EGO_ENVDIR` are defined in `lsf.conf`), `cshrc.lsf` and `profile.lsf` set the following environment variables.

- EGO\_BINDIR
- EGO\_CONFDIR
- EGO\_ESRVDIR
- EGO\_LIBDIR
- EGO\_LOCAL\_CONFDIR
- EGO\_SERVERDIR
- EGO\_TOP

See the *Platform EGO Reference* for more information about these variables.

## Setting the LSF environment with cshrc.lsf and profile.lsf

Before using LSF, you must set the LSF execution environment.

After logging on to an LSF host, use one of the following shell environment files to set your LSF environment:

- For example, in `cs`h or `tc`sh:  
**source /usr/share/lsf/lsf\_7/conf/cshrc.lsf**
- For example, in `sh`, `ksh`, or `bash`:  
**./usr/share/lsf/lsf\_7/conf/profile.lsf**

## Making your cluster available to users with cshrc.lsf and profile.lsf

To set the LSF user environment, run one of the following two shell files:

- `LSF_CONFDIR/cshrc.lsf` (for `cs`h, `tc`sh)
- `LSF_CONFDIR/profile.lsf` (for `sh`, `ksh`, or `bash`)

### Tip:

LSF administrators should make sure all LSF users include one of these files at the end of their own `.cshrc` or `.profile` file, or run one of these two files before using LSF.

## For csh or tcsh

Add `cshrc.lsf` to the end of the `.cshrc` file for all users:

- Copy the `cshrc.lsf` file into `.cshrc`, or
- Add a line similar to the following to the end of `.cshrc`:  
**source /usr/share/lsf/lsf\_7/conf/cshrc.lsf**

After running `cshrc.lsf`, use `setenv` to see the environment variable settings. For example:

```
setenv PATH=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/bin:/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc:/home/user1/bin:/local/private/user1/bin:/etc:/usr/etc:/usr/local/bin:/usr/local/sbin:/bin:/usr/bin:/usr/sbin:/opt/local/bin:/local/share/bin:/opt/gnu/bin:/sbin:/usr/bin/X11:/usr/bsd:/usr/ucb:/local/bin/X11:/usr/hosts:/usr/openwin/bin:/usr/ccs/bin:/usr/vue/bin:
... MANPATH=/usr/share/lsf/lsf_7/7.0/man:/home/user1/man:/opt/SUNWhpc/man:/usr/man:/usr/local/man:/usr/softbench/man:/usr/openwin/man:/opt/SUNWmotif/man:/opt/ansi c/share/man:/opt/hpnp/man:/usr/share/man:/usr/share/catman
...
LSF_BINDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/bin LSF_SERVERDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc LSF_LIBDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib LD_LIBRARY_PATH=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib XLSF_UIDDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib/uid LSF_ENVDIR=/usr/share/lsf/lsf_7/conf
```

### Note:

These variable settings are an example only. Your system may set additional variables.

## For sh, ksh, or bash

Add `profile.lsf` to the end of the `.profile` file for all users:

- Copy the `profile.lsf` file into `.profile`, or
- Add a line similar to following to the end of `.profile`:

```
./usr/share/lsf/lsf_7/conf/profile.lsf
```

After running `profile.lsf`, use the `set` command to see the environment variable settings. For example:

```
set
...
LD_LIBRARY_PATH=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/lib LSF_BINDIR=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/bin LSF_ENVDIR=/usr/share/lsf/lsf_7/conf LSF_LIBDIR=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/lib LSF_SERVERDIR=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/etc MANPATH=/usr/share/lsf/lsf_7/0/man:/home/user1/man:/opt/SUNWhpc/man:/usr/man:/usr/local/man:/usr/softbench/man:/usr/openwin/man:/opt/SUNWmotif/man:/opt/ansic/share/man:/opt/hpnp/man:/usr/share/man:/usr/share/catman PATH=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/bin:/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/etc:/home/user1/bin:/local/private/user1/bin:/etc:/usr/etc:/usr/local/bin:/usr/local/sbin:/bin:/usr/bin:/usr/sbin:/opt/local/bin:/local/share/bin:/opt/gnu/bin:/sbin:/usr/bin/X11:/usr/bsd:/usr/ucb:/local/bin/X11:/usr/hosts:/usr/openwin/bin:/usr/ccs/bin:/usr/vue/bin:
...
XLSF_UIDDIR=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/lib/ui d
...
```

### Note:

These variable settings are an example only. Your system may set additional variables.

## cshrc.lsf and profile.lsf on dynamically added LSF slave hosts

Dynamically added LSF hosts that will not be master candidates are *slave hosts*. Each dynamic slave host has its own LSF binaries and local `lsf.conf` and shell environment scripts (`cshrc.lsf` and `profile.lsf`).

## LSF environment variables set by cshrc.lsf and profile.lsf

### LSF\_BINDIR

#### Syntax

```
LSF_BINDIR=dir
```

#### Description

Directory where LSF user commands are installed.

#### Examples

- Set in `csh` and `tcsh` by `cshrc.lsf`:

```
setenv LSF_BINDIR /usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/bin
```

- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:

```
LSF_BINDIR=/usr/share/lsf/lsf_7/0/linux2.6-glibc2.3-x86/bin
```

## Values

- In `cshrc.lsf` for `csh` and `tcsh`:  

```
setenv LSF_BINDIR $LSF_TOP/$LSF_VERSION/$BINARY_TYPE/bin
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  

```
LSF_BINDIR=$LSF_TOP/$LSF_VERSION/$BINARY_TYPE/bin
```

## LSF\_ENVDIR

### Syntax

**LSF\_ENVDIR**=*dir*

### Description

Directory containing the `lsf.conf` file.

By default, `lsf.conf` is installed by creating a shared copy in `LSF_CONFDIR` and adding a symbolic link from `/etc/lsf.conf` to the shared copy. If `LSF_ENVDIR` is set, the symbolic link is installed in `LSF_ENVDIR/lsf.conf`.

The `lsf.conf` file is a global environment configuration file for all LSF services and applications. The LSF default installation places the file in `LSF_CONFDIR`.

### Examples

- Set in `csh` and `tcsh` by `cshrc.lsf`:  

```
setenv LSF_ENVDIR /usr/share/lsf/lsf_7/conf
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  

```
LSF_ENVDIR=/usr/share/lsf/lsf_7/conf
```

## Values

- In `cshrc.lsf` for `csh` and `tcsh`:  

```
setenv LSF_ENVDIR $LSF_TOP/conf
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  

```
LSF_DIR=$LSF_TOP/conf
```

## LSF\_LIBDIR

### Syntax

**LSF\_LIBDIR**=*dir*

### Description

Directory where LSF libraries are installed. Library files are shared by all hosts of the same type.

### Examples

- Set in `csh` and `tcsh` by `cshrc.lsf`:  

```
setenv LSF_LIBDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  

```
LSF_LIBDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib
```

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:
 

```
setenv LSF_LIBDIR $LSF_TOP/$LSF_VERSION/$BINARY_TYPE/lib
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:
 

```
LSF_LIBDIR=$LSF_TOP/$LSF_VERSION/$BINARY_TYPE/lib
```

## LSF\_SERVERDIR

### Syntax

**LSF\_SERVERDIR**=*dir*

### Description

Directory where LSF server binaries and shell scripts are installed.

These include `lim`, `res`, `ni`os, `sbatchd`, `mbatchd`, and `mbschd`. If you use `elim`, `eauth`, `eexec`, `esub`, etc, they are also installed in this directory.

### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:
 

```
setenv LSF_SERVERDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:
 

```
LSF_SERVERDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc
```

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:
 

```
setenv LSF_SERVERDIR $LSF_TOP/$LSF_VERSION/$BINARY_TYPE/etc
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:
 

```
LSF_SERVERDIR=$LSF_TOP/$LSF_VERSION/$BINARY_TYPE/etc
```

## XLSF\_UIDDIR

### Syntax

**XLSF\_UIDDIR**=*dir*

### Description

(UNIX and Linux only) Directory where Motif User Interface Definition files are stored.

These files are platform-specific.

### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:
 

```
setenv XLSF_UIDDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib/ui d
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:
 

```
XLSF_UIDDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib/ui d
```

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:  
`setenv XLSF_UIDDIR $LSF_TOP/$LSF_VERSION/SBINARY_TYPE/lib/ui d`
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  
`XLSF_UIDDIR=$LSF_TOP/$LSF_VERSION/SBINARY_TYPE/lib/ui d`

## Platform EGO environment variables set by cshrc.lsf and profile.lsf

See the *Platform EGO Reference* for more information about these variables.

### EGO\_BINDIR

#### Syntax

**EGO\_BINDIR**=*dir*

#### Description

Directory where Platform EGO user commands are installed.

#### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:  
`setenv EGO_BINDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/bin`
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  
`EGO_BINDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/bin`

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:  
`setenv EGO_BINDIR $LSF_BINDIR`
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  
`EGO_BINDIR=$LSF_BINDIR`

### EGO\_CONFDIR

#### Syntax

**EGO\_CONFDIR**=*dir*

#### Description

Directory containing the `ego.conf` file.

#### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:  
`setenv EGO_CONFDIR /usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel`
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  
`EGO_CONFDIR=/usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel`

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:  

```
setenv EGO_CONFDIR /usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  

```
EGO_CONFDIR=/usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```

## EGO\_ESRVDIR

### Syntax

**EGO\_ESRVDIR**=*dir*

### Description

Directory where the EGO the service controller configuration files are stored.

### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:  

```
setenv EGO_ESRVDIR /usr/share/lsf/lsf_7/conf/ego/lsf702/eservice
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  

```
EGO_ESRVDIR=/usr/share/lsf/lsf_7/conf/ego/lsf702/eservice
```

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:  

```
setenv EGO_ESRVDIR /usr/share/lsf/lsf_7/conf/ego/lsf702/eservice
```
- Set and exported in `profile.lsf` for `sh`, `ksh`, or `bash`:  

```
EGO_ESRVDIR=/usr/share/lsf/lsf_7/conf/ego/lsf702/eservice
```

## EGO\_LIBDIR

### Syntax

**EGO\_LIBDIR**=*dir*

### Description

Directory where EGO libraries are installed. Library files are shared by all hosts of the same type.

### Examples

- Set in `cs`h and `tc`sh by `cshrc.lsf`:  

```
setenv EGO_LIBDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib
```
- Set and exported in `sh`, `ksh`, or `bash` by `profile.lsf`:  

```
EGO_LIBDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/lib
```

## Values

- In `cshrc.lsf` for `cs`h and `tc`sh:  

```
setenv EGO_LIBDIR $LSF_LIBDIR
```

- Set and exported in profile.lsf for sh, ksh, or bash:

```
EGO_LOCAL_CONFDIR=$LSF_LOCAL_CONFDIR
```

## EGO\_LOCAL\_CONFDIR

### Syntax

```
EGO_LOCAL_CONFDIR=dir
```

### Description

The local EGO configuration directory containing the ego.conf file.

### Examples

- Set in csh and tcsh by cshrc.lsf:

```
setenv EGO_LOCAL_CONFDIR /usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```

- Set and exported in sh, ksh, or bash by profile.lsf:

```
EGO_LOCAL_CONFDIR=/usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```

### Values

- In cshrc.lsf for csh and tcsh:

```
setenv EGO_LOCAL_CONFDIR /usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```

- Set and exported in profile.lsf for sh, ksh, or bash:

```
EGO_LOCAL_CONFDIR=/usr/share/lsf/lsf_7/conf/ego/lsf1.2.3/kernel
```

## EGO\_SERVERDIR

### Syntax

```
EGO_SERVERDIR=dir
```

### Description

Directory where EGO server binaries and shell scripts are installed. These include vemkd, pem, egosc, and shell scripts for EGO startup and shutdown.

### Examples

- Set in csh and tcsh by cshrc.lsf:

```
setenv EGO_SERVERDIR /usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc
```

- Set and exported in sh, ksh, or bash by profile.lsf:

```
EGO_SERVERDIR=/usr/share/lsf/lsf_7/7.0/linux2.6-glibc2.3-x86/etc
```

### Values

- In cshrc.lsf for csh and tcsh:

```
setenv EGO_SERVERDIR $LSF_SERVERDIR
```

- Set and exported in profile.lsf for sh, ksh, or bash:

```
EGO_SERVERDIR=$LSF_SERVERDIR
```

# EGO\_TOP

## Syntax

**EGO\_TOP=dir**

## Description

The the top-level installation directory. The path to EGO\_TOP must be shared and accessible to all hosts in the cluster. Equivalent to LSF\_TOP.

## Examples

- Set in csh and tcsh by cshrc.lsf:  

```
setenv EGO_TOP /usr/share/lsf/lsf_7
```
- Set and exported in sh, ksh, or bash by profile.lsf:  

```
EGO_TOP=/usr/share/lsf/lsf_7
```

## Values

- In cshrc.lsf for csh and tcsh:  

```
setenv EGO_TOP /usr/share/lsf/lsf_7
```
- Set and exported in profile.lsf for sh, ksh, or bash:  

```
EGO_TOP=/usr/share/lsf/lsf_7
```

# hosts

For hosts with multiple IP addresses and different official host names configured at the system level, this file associates the host names and IP addresses in LSF.

By default, LSF assumes each host in the cluster:

- Has a unique “official” host name
- Can resolve its IP address from its name
- Can resolve its official name from its IP address

Hosts with only one IP address, or hosts with multiple IP addresses that already resolve to a unique official host name should not be configured in this file: they are resolved using the default method for your system (for example, local configuration files like `/etc/hosts` or through DNS.)

The LSF `hosts` file is used in environments where:

- Machines in cluster have multiple network interfaces and cannot be set up in the system with a unique official host name
- DNS is slow or not configured properly
- Machines have special topology requirements; for example, in HPC systems where it is desirable to map multiple actual hosts to a single “head end” host

The LSF `hosts` file is not installed by default. It is usually located in the directory specified by `LSF_CONFDIR`. The format of `LSF_CONFDIR/hosts` is similar to the format of the `/etc/hosts` file on UNIX machines.

## hosts file structure

One line for each IP address, consisting of the IP address, followed by the official host name, optionally followed by host aliases, all separated by spaces or tabs. Each line has the form:

```
ip_address official_name [ alias [ alias ... ] ]
```

IP addresses can have either a dotted quad notation (IPv4) or IP Next Generation (IPv6) format. You can use IPv6 addresses if you define the parameter `LSF_ENABLE_SUPPORT_IPV6` in `lsf.conf`; you do not have to map IPv4 addresses to an IPv6 format.

Use consecutive lines for IP addresses belonging to the same host. You can assign different aliases to different addresses.

Use a pound sign (#) to indicate a comment (the rest of the line is not read by LSF). Do not use `#if` as this is reserved syntax for time-based configuration.

## IP address

Written using an IPv4 or IPv6 format. LSF supports both formats; you do not have to map IPv4 addresses to an IPv6 format (if you define the parameter `LSF_ENABLE_SUPPORT_IPV6` in `lsf.conf`).

- IPv4 format: `nnn.nnn.nnn.nnn`
- IPv6 format: `nnnn:nnnn:nnnn:nnnn:nnnn:nnnn:nnnn:nnnn`

## Official host name

The official host name. Single character names are not allowed.

Specify `-GATEWAY` or `-GW` as part of the host name if the host serves as a GATEWAY.

Specify `-TAC` as the last part of the host name if the host is a TAC and is a DoD host.

Specify the host name in the format defined in Internet RFC 952, which states:

A “name” (Net, Host, Gateway, or Domain name) is a text string up to 24 characters drawn from the alphabet (A-Z), digits (0-9), minus sign (-), and period (.). Periods are only allowed when they serve to delimit components of “domain style names”. (See RFC 921, “Domain Name System Implementation Schedule”, for background). No blank or space characters are permitted as part of a name. No distinction is made between upper and lower case. The first character must be an alpha character. The last character must not be a minus sign or a period.

RFC 952 has been modified by RFC 1123 to relax the restriction on the first character being a digit.

For maximum interoperability with the Internet, you should use host names no longer than 24 characters for the host portion (exclusive of the domain component).

## Aliases

Optional. Aliases to the host name.

The default host file syntax

```
ip_address official_name [ alias [ alias ... ] ]
```

is powerful and flexible, but it is difficult to configure in systems where a single host name has many aliases, and in multihomed host environments.

In these cases, the `hosts` file can become very large and unmanageable, and configuration is prone to error.

The syntax of the LSF `hosts` file supports host name ranges as aliases for an IP address. This simplifies the host name alias specification.

To use host name ranges as aliases, the host names must consist of a fixed node group name prefix and node indices, specified in a form like:

```
host_name[ index_x- index_y, index_m, index_a- index_b ]
```

For example:

```
atl asD0[ 0- 3, 4, 5- 6, ... ]
```

is equivalent to:

```
atl asD0[ 0- 6, ... ]
```

The node list does not need to be a continuous range (some nodes can be configured out). Node indices can be numbers or letters (both upper case and lower case).

For example, some systems map internal compute nodes to single LSF host names. A host file might contain 64 lines, each specifying an LSF host name and 32 node names that correspond to each LSF host:

```
...
177.16.1.1 atl asD0 atl as0 atl as1 atl as2 atl as3 atl as4 ... atl as31
177.16.1.2 atl asD1 atl as32 atl as33 atl as34 atl as35 atl as36 ... atl as63
...
```

In the new format, you still map the nodes to the LSF hosts, so the number of lines remains the same, but the format is simplified because you only have to specify ranges for the nodes, not each node individually as an alias:

```
...
177.16.1.1 atl asD0 atl as[ 0- 31 ]
177.16.1.2 atl asD1 atl as[ 32- 63 ]
...
```

You can use either an IPv4 or an IPv6 format for the IP address (if you define the parameter `LSF_ENABLE_SUPPORT_IPV6` in `lsf.conf`).

## IPv4 Example

```
192.168.1.1 hostA hostB 192.168.2.2 hostA hostC host-C
```

hosts

In this example, `hostA` has 2 IP addresses and 3 aliases. The alias `hostB` specifies the first address, and the aliases `hostC` and `host - C` specify the second address. LSF uses the official host name, `hostA`, to identify that both IP addresses belong to the same host.

## IPv6 Example

```
3ffe:b80:3:1a91::2 hostA hostB 3ffe:b80:3:1a91::3 hostA hostC host - C
```

In this example, `hostA` has 2 IP addresses and 3 aliases. The alias `hostB` specifies the first address, and the aliases `hostC` and `host - C` specify the second address. LSF uses the official host name, `hostA`, to identify that both IP addresses belong to the same host.

# install.config

## About install.config

The `install.config` file contains options for LSF installation and configuration. Use `lsfinstall -f install.config` to install LSF using the options specified in `install.config`.

## Template location

A template `install.config` is included in the installation script tar file `lsf7Update5_lsfinstall.tar.Z` and is located in the `lsf7Update5_lsfinstall` directory created when you uncompress and extract installation script tar file. Edit the file and uncomment the options you want in the template file. Replace the example values with your own settings to specify the options for your new installation.

---

### Important:

The sample values in the `install.config` template file are examples only. They are not default installation values.

---

After installation, the `install.config` containing the options you specified is located in `LSF_TOP/7.0/install/`.

## Format

Each entry in `install.config` has the form:

```
NAME="STRING1 STRING2 . . ."
```

The equal sign = must follow each NAME even if no value follows and there should be no spaces around the equal sign.

A value that contains multiple strings separated by spaces must be enclosed in quotation marks.

Blank lines and lines starting with a pound sign (#) are ignored.

## Parameters

- DERBY\_DB\_HOST
- EGO\_DAEMON\_CONTROL
- EGO\_PERF\_CONTROL
- EGO\_PMC\_CONTROL
- ENABLE\_DYNAMIC\_HOSTS
- ENABLE\_EGO
- ENABLE\_HPC\_CONFIG
- EP\_BACKUP
- LSF\_ADD\_SERVERS
- LSF\_ADD\_CLIENTS
- LSF\_ADMINS
- LSF\_CLUSTER\_NAME
- LSF\_DYNAMIC\_HOST\_WAIT\_TIME
- LSF\_LICENSE
- LSF\_MASTER\_LIST

- LSF\_QUIET\_INST
- LSF\_TARDIR
- LSF\_TOP
- PATCH\_BACKUP\_DIR
- PATCH\_HISTORY\_DIR
- PERF\_HOST
- PMC\_HOST

## DERBY\_DB\_HOST

### Syntax

```
DERBY_DB_HOST="host_name"
```

### Description

Reporting database host. This parameter is used when you install the Platform Management Console package for the first time, and is ignored for all other cases.

Specify the name of a reliable host where the Derby database for Reporting data collection will be installed. You must specify a host from LSF\_MASTER\_LIST. Leave this parameter undefined if you will use another database for Reporting.

### Example

```
DERBY_DB_HOST="host d"
```

### Default

Database is undefined.

## EGO\_DAEMON\_CONTROL

### Syntax

```
EGO_DAEMON_CONTROL="Y" | "N"
```

### Description

Enables EGO to control LSF `res` and `sbatchd`. Set the value to "Y" if you want EGO Service Controller to start `res` and `sbatchd`, and restart if they fail. To avoid conflicts, leave this parameter undefined if you use a script to start up LSF daemons.

---

**Note:**

If you specify EGO\_ENABLE="N", this parameter is ignored.

---

### Example

```
EGO_DAEMON_CONTROL="N"
```

### Default

N (`res` and `sbatchd` are started manually)

## EGO\_PERF\_CONTROL

### Syntax

```
EGO_PERF_CONTROL="Y" | "N"
```

### Description

Enables EGO Service Controller to control PERF daemons. Set the value to "N" if you want to control PERF daemons manually. If you do this, you must define PERF\_HOST in this file.

---

**Note:**

If you specify EGO\_ENABLE="N", this parameter is ignored.

---

**Note:**

This parameter only takes effect when you install the Platform Management Console package for the first time.

---

### Example

```
EGO_PERF_CONTROL=" N"
```

### Default

Y (PERF daemons are controlled by EGO unless EGO is disabled)

## EGO\_PMC\_CONTROL

### Syntax

```
EGO_PMC_CONTROL="Y" | "N"
```

### Description

Enables EGO Service Controller to control the Platform Management Console. Set the value to "N" if you want to control the Platform Management Console manually.

---

**Note:**

If you specify EGO\_ENABLE="N", this parameter is ignored.

---

**Note:**

This parameter only takes effect when you install the Platform Management Console package for the first time.

---

### Example

```
EGO_PMC_CONTROL=" N"
```

### Default

Y (Platform Management Console is controlled by EGO unless EGO is disabled)

## ENABLE\_DYNAMIC\_HOSTS

### Syntax

```
ENABLE_DYNAMIC_HOSTS="Y" | "N"
```

### Description

Enables dynamically adding and removing hosts. Set the value to "Y" if you want to allow dynamically added hosts.

If you enable dynamic hosts, any host can connect to cluster. To enable security, configure `LSF_HOST_ADDR_RANGE` in `lsf.cluster.cluster_name` after installation and restrict the hosts that can connect to your cluster.

### Example

```
ENABLE_DYNAMIC_HOSTS="N"
```

### Default

N (dynamic hosts not allowed)

## ENABLE\_EGO

### Syntax

```
ENABLE_EGO="Y" | "N"
```

### Description

Enables Platform EGO functionality in the LSF cluster.

`ENABLE_EGO="Y"` causes `lsfinstall` to uncomment `LSF_EGO_ENVDIR` and sets `LSF_ENABLE_EGO="Y"` in `lsf.conf`.

`ENABLE_EGO="N"` causes `lsfinstall` to comment out `LSF_EGO_ENVDIR` and sets `LSF_ENABLE_EGO="N"` in `lsf.conf`.

Set the value to "N" if you do not want to take advantage of the following LSF features that depend on EGO:

- LSF daemon control by EGO Service Controller
- EGO-enabled SLA scheduling
- Platform Management Console (PMC)
- LSF reporting

### Default

Y (EGO is enabled in the LSF cluster)

## ENABLE\_HPC\_CONFIG

### Syntax

```
ENABLE_HPC_CONFIG="Y" | "N"
```

## Description

Set the value to "Y" to add LSF HPC configuration parameters to the cluster.

## Default

Y (Platform LSF HPC is enabled.)

## EP\_BACKUP

### Syntax

```
EP_BACKUP="Y" | "N"
```

## Description

Enables backup and rollback for enhancement packs. Set the value to "N" to disable backups when installing enhancement packs (you will not be able to roll back to the previous patch level after installing an EP, but you will still be able to roll back any fixes installed on the new EP).

You may disable backups to speed up install time, to save disk space, or because you have your own methods to back up the cluster.

## Default

Y (backup and rollback are fully enabled)

## LSF\_ADD\_SERVERS

### Syntax

```
LSF_ADD_SERVERS="host_name [host_name...]"
```

## Description

List of additional LSF server hosts.

The hosts in LSF\_MASTER\_LIST are always LSF servers. You can specify additional server hosts. Specify a list of host names two ways:

- Host names separated by spaces
- Name of a file containing a list of host names, one host per line.

## Valid Values

Any valid LSF host name.

## Example 1

List of host names:

```
LSF_ADD_SERVERS="hosta hostb hostc hostd"
```

## Example 2

Host list file:

```
LSF_ADD_SERVERS=:lsf_server_hosts
```

The file `lsf_server_hosts` contains a list of hosts:

```
hosta  
hostb  
hostc  
hostd
```

## Default

Only hosts in `LSF_MASTER_LIST` are LSF servers.

## LSF\_ADD\_CLIENTS

### Syntax

```
LSF_ADD_CLIENTS="host_name [host_name...]"
```

### Description

List of LSF client-only hosts.

---

**Tip:**

After installation, you must manually edit `lsf.cluster.cluster_name` to include the host model and type of each client listed in `LSF_ADD_CLIENTS`.

---

### Valid Values

Any valid LSF host name.

### Example 1

List of host names:

```
LSF_ADD_CLIENTS="hoste hostf"
```

### Example 2

Host list file:

```
LSF_ADD_CLIENTS=:lsf_client_hosts
```

The file `lsf_client_hosts` contains a list of hosts:

```
hoste  
hostf
```

## Default

No client hosts installed.

## LSF\_ADMINS

### Syntax

```
LSF_ADMINS="user_name [user_name ...]"
```

### Description

Required. List of LSF administrators.

The first user account name in the list is the primary LSF administrator. It cannot be the root user account.

Typically this account is named `lsfadmin`. It owns the LSF configuration files and log files for job events. It also has permission to reconfigure LSF and to control batch jobs submitted by other users. It typically does not have authority to start LSF daemons. Usually, only root has permission to start LSF daemons.

All the LSF administrator accounts must exist on all hosts in the cluster before you install LSF. Secondary LSF administrators are optional.

---

**Caution:**

You should *not* configure the root account as the primary LSF administrator.

---

## Valid Values

Existing user accounts

## Example

```
LSF_ADMINS="lsfadmin user1 user2"
```

## Default

None—required variable

## LSF\_CLUSTER\_NAME

### Syntax

```
LSF_CLUSTER_NAME="cluster_name"
```

### Description

Required. The name of the LSF cluster.

### Example

```
LSF_CLUSTER_NAME="cluster1"
```

## Valid Values

Any alphanumeric string containing no more than 39 characters. The name cannot contain white spaces.

---

**Important:**

Do not use the name of any host, user, or user group as the name of your cluster.

---

## Default

None—required variable

## LSF\_DYNAMIC\_HOST\_WAIT\_TIME

### Syntax

```
LSF_DYNAMIC_HOST_WAIT_TIME=seconds
```

### Description

Time in seconds slave LIM waits after startup before calling master LIM to add the slave host dynamically.

This parameter only takes effect if you set `ENABLE_DYNAMIC_HOSTS="Y"` in this file. If the slave LIM receives the master announcement while it is waiting, it does not call the master LIM to add itself.

### Recommended value

Up to 60 seconds for every 1000 hosts in the cluster, for a maximum of 15 minutes. Selecting a smaller value will result in a quicker response time for new hosts at the expense of an increased load on the master LIM.

### Example

```
LSF_DYNAMIC_HOST_WAIT_TIME=60
```

Hosts will wait 60 seconds from startup to receive an acknowledgement from the master LIM. If it does not receive the acknowledgement within the 60 seconds, it will send a request for the master LIM to add it to the cluster.

### Default

Slave LIM waits forever

## LSF\_LICENSE

### Syntax

```
LSF_LICENSE="/path/license_file"
```

### Description

Full path to the name of the LSF license file, `license.dat`.

You must have a valid license file to install LSF.

---

**Caution:**

If you do not specify `LSF_LICENSE`, or `lsfinstall` cannot find a valid license file in the default location, `lsfinstall` exits.

---

### Example

```
LSF_LICENSE="/usr/share/lsf_distribution/license.dat"
```

## Default

The parent directory of the current working directory. For example, if `lsfinstall` is running under `usr/share/lsf_distribution/lsf_install` the `LSF_LICENSE` default value is `usr/share/lsf_distribution/license.dat`.

## LSF\_MASTER\_LIST

### Syntax

```
LSF_MASTER_LIST="host_name [host_name ...]"
```

### Description

Required for a first-time installation. List of LSF server hosts to be master or master candidates in the cluster.

You must specify at least one valid server host to start the cluster. The first host listed is the LSF master host.

During upgrade, specify the existing value.

### Valid Values

LSF server host names

### Example

```
LSF_MASTER_LIST="hosta hostb hostc hostd"
```

## Default

None — required variable

## LSF\_QUIET\_INST

### Syntax

```
LSF_QUIET_INST="Y" | "N"
```

### Description

Enables quiet installation.

Set the value to Y if you want to hide the LSF installation messages.

### Example

```
LSF_QUIET_INST="Y"
```

## Default

N (installer displays messages during installation)

## LSF\_TARDIR

### Syntax

**LSF\_TARDIR="/path"**

### Description

Full path to the directory containing the LSF distribution tar files.

### Example

LSF\_TARDIR="/usr/share/l sf\_ di stri b"

### Default

The parent directory of the current working directory. For example, if `l sf_ i nst al l` is running under `usr/share/l sf_ di stri b/l sf_ l sf_ i nst al l` the LSF\_TARDIR default value is `usr/share/l sf_ di stri b`.

## LSF\_TOP

### Syntax

**LSF\_TOP="/path"**

### Description

Required. Full path to the top-level LSF installation directory.

### Valid Value

The path to LSF\_TOP must be shared and accessible to all hosts in the cluster. It cannot be the root directory (`/`). The file system containing LSF\_TOP must have enough disk space for all host types (approximately 300 MB per host type).

### Example

LSF\_TOP="/usr/share/l sf"

### Default

None — required variable

## PATCH\_BACKUP\_DIR

### Syntax

**PATCH\_BACKUP\_DIR="/path"**

### Description

Full path to the patch backup directory. This parameter is used when you install a new cluster for the first time, and is ignored for all other cases.

The file system containing the patch backup directory must have sufficient disk space to back up your files (approximately 400 MB per binary type if you want to be able to install and roll back one enhancement pack and a few additional fixes). It cannot be the root directory (/).

If the directory already exists, it must be writable by the cluster administrator (`lsfadmin`).

If you need to change the directory after installation, edit `PATCH_BACKUP_DIR` in `LSF_TOP/patch.conf` and move the saved backup files to the new directory manually.

## Example

```
PATCH_BACKUP_DIR="/usr/share/lsf/patch/backup"
```

## Default

```
LSF_TOP/patch/backup
```

## PATCH\_HISTORY\_DIR

### Syntax

```
PATCH_HISTORY_DIR="/path"
```

### Description

Full path to the patch history directory. This parameter is used when you install a new cluster for the first time, and is ignored for all other cases.

It cannot be the root directory (/). If the directory already exists, it must be writable by `lsfadmin`.

The location is saved as `PATCH_HISTORY_DIR` in `LSF_TOP/patch.conf`. Do not change the directory after installation.

## Example

```
PATCH_BACKUP_DIR="/usr/share/lsf/patch"
```

## Default

```
LSF_TOP/patch
```

## PERF\_HOST

### Syntax

```
PERF_HOST="host_name"
```

### Description

Dedicated host for PERF daemons. Required if `EGO_PERF_CONTROL="N"`. To allow failover, we recommend that you leave this parameter undefined when EGO control is enabled for the PERF daemons.

Specify the name of one host that will run PERF daemons: `plc`, `j obdt`, and `purger`. If EGO controls PERF daemons, you must specify a host from `LSF_MASTER_LIST`.

---

**Note:**

This parameter only takes effect when you install the Platform Management Console package for the first time.

---

## Example

```
PERF_HOST="host p"
```

## Default

Undefined.

## PMC\_HOST

### Syntax

```
PMC_HOST="host_name"
```

## Description

Dedicated host for Platform Management Console. Required if EGO\_PMC\_CONTROL="N". To allow failover, we recommend that you leave this parameter undefined when EGO control is enabled for the Platform Management Console.

Specify the name of one host that will always run the Platform Management Console. If EGO controls PMC, you must specify a host from LSF\_MASTER\_LIST.

---

**Note:**

This parameter only takes effect when you install the Platform Management Console package for the first time.

---

## Example

```
PMC_HOST="host g"
```

## Default

Undefined.

# lim.acct

The `lim.acct` file is the log file for Load Information Manager (LIM). Produced by `lsmmon`, `lim.acct` contains host load information collected and distributed by LIM.

## lim.acct structure

The first line of `lim.acct` contains a list of load index names separated by spaces. This list of load index names can be specified in the `lsmmon` command line. The default list is "r15s r1m r15m ut pg ls it swp mem tmp". Subsequent lines in the file contain the host's load information at the time the information was recorded.

## Fields

Fields are ordered in the following sequence:

### **time (%ld)**

The time when the load information is written to the log file

### **host name (%s)**

The name of the host.

### **status of host (%d)**

An array of integers. The first integer marks the operation status of the host. Additional integers are used as a bit map to indicate load status of the host. An integer can be used for 32 load indices. If the number of user defined load indices is not more than 21, only one integer is used for both built-in load indices and external load indices. See the `hostload` structure in `ls_load(3)` for the description of these fields.

### **indexvalue (%f)**

A sequence of load index values. Each value corresponds to the index name in the first line of `lim.acct`. The order in which the index values are listed is the same as the order of the index names.

## lsb.acct

The `lsb.acct` file is the batch job log file of LSF. The master batch daemon (see `mbatchd(8)`) generates a record for each job completion or failure. The record is appended to the job log file `lsb.acct`.

The file is located in `LSB_SHAREDIR/cluster_name/logdir`, where `LSB_SHAREDIR` must be defined in `lsf.conf(5)` and `cluster_name` is the name of the LSF cluster, as returned by `lsid(1)`. See `mbatchd(8)` for the description of `LSB_SHAREDIR`.

The `bacct` command uses the current `lsb.acct` file for its output.

### lsb.acct structure

The job log file is an ASCII file with one record per line. The fields of a record are separated by blanks. If the value of some field is unavailable, a pair of double quotation marks (") is logged for character string, 0 for time and number, and -1 for resource usage.

### Configuring automatic archiving

The following parameters in `lsb.params` affect how records are logged to `lsb.acct`:

#### **ACCT\_ARCHIVE\_AGE=days**

Enables automatic archiving of LSF accounting log files, and specifies the archive interval. LSF archives the current log file if the length of time from its creation date exceeds the specified number of days.

By default there is no limit to the age of `lsb.acct`.

#### **ACCT\_ARCHIVE\_SIZE=kilobytes**

Enables automatic archiving of LSF accounting log files, and specifies the archive threshold. LSF archives the current log file if its size exceeds the specified number of kilobytes.

By default, there is no limit to the size of `lsb.acct`.

#### **ACCT\_ARCHIVE\_TIME=hh:mm**

Enables automatic archiving of LSF accounting log file `lsb.acct`, and specifies the time of day to archive the current log file.

By default, no time is set for archiving `lsb.acct`.

#### **MAX\_ACCT\_ARCHIVE\_FILE=integer**

Enables automatic deletion of archived LSF accounting log files and specifies the archive limit.

By default, `lsb.acct.n` files are not automatically deleted.

### Records and fields

The fields of a record are separated by blanks. The first string of an event record indicates its type. The following types of events are recorded:

- `JOB_FINISH`

- EVENT\_ADRSV\_FINISH

## JOB\_FINISH

A job has finished.

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in `lsf.conf`, older daemons and commands (pre-LSF Version 6.0) cannot recognize the `lsb.acct` file format.

The fields in order of occurrence are:

### Event type (%s)

Which is "JOB\_FINISH"

### Version Number (%s)

Version number of the log file format

### Event Time (%d)

Time the event was logged (in seconds since the epoch)

### jobId (%d)

ID for the job

### userId (%d)

UNIX user ID of the submitter

### options (%d)

Bit flags for job processing

### numProcessors (%d)

Number of processors initially requested for execution

### submitTime (%d)

Job submission time

### beginTime (%d)

Job start time – the job should be started at or after this time

### termTime (%d)

Job termination deadline – the job should be terminated by this time

### startTime (%d)

Job dispatch time – time job was dispatched for execution

### userName (%s)

User name of the submitter

### queue (%s)

Name of the job queue to which the job was submitted

### resReq (%s)

Resource requirement specified by the user

**dependCond (%s)**

Job dependency condition specified by the user

**preExecCmd (%s)**

Pre-execution command specified by the user

**fromHost (%s)**

Submission host name

**cwd (%s)**

Current working directory (up to 4094 characters for UNIX or 512 characters for Windows)

**inFile (%s)**

Input file name (up to 4094 characters for UNIX or 512 characters for Windows)

**outFile (%s)**

output file name (up to 4094 characters for UNIX or 512 characters for Windows)

**errFile (%s)**

Error output file name (up to 4094 characters for UNIX or 512 characters for Windows)

**jobFile (%s)**

Job script file name

**numAskedHosts (%d)**

Number of host names to which job dispatching will be limited

**askedHosts (%s)**

List of host names to which job dispatching will be limited (%s for each); nothing is logged to the record for this value if the last field value is 0. If there is more than one host name, then each additional host name will be returned in its own field

**numExHosts (%d)**

Number of processors used for execution

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in `lsf.conf`, the value of this field is the number of `.hosts` listed in the `execHosts` field.

Logged value reflects the allocation at job finish time.

**execHosts (%s)**

List of execution host names (%s for each); nothing is logged to the record for this value if the last field value is 0.

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in `lsf.conf`, the value of this field is logged in a shortened format.

The logged value reflects the allocation at job finish time.

**jStatus (%d)**

Job status. The number 32 represents EXIT, 64 represents DONE

**hostFactor (%f)**

CPU factor of the first execution host.

**jobName (%s)**

Job name (up to 4094 characters for UNIX or 512 characters for Windows).

**command (%s)**

Complete batch job command specified by the user (up to 4094 characters for UNIX or 512 characters for Windows).

**lsfRusage (%f)**

The following fields contain resource usage information for the job (see `get rusage (2)`). If the value of some field is unavailable (due to job exit or the difference among the operating systems), -1 will be logged. Times are measured in seconds, and sizes are measured in KB.

**ru\_utime (%f)**

User time used

**ru\_stime (%f)**

System time used

**ru\_maxrss (%f)**

Maximum shared text size

**ru\_ixrss (%f)**

Integral of the shared text size over time (in KB seconds)

**ru\_ismrss (%f)**

Integral of the shared memory size over time (valid only on Ultrix)

**ru\_idrss (%f)**

Integral of the unshared data size over time

**ru\_isrss (%f)**

Integral of the unshared stack size over time

**ru\_minflt (%f)**

Number of page reclaims

**ru\_majflt (%f)**

Number of page faults

**ru\_nswap (%f)**

	Number of times the process was swapped out
<b>ru_inblock (%f)</b>	Number of block input operations
<b>ru_oublock (%f)</b>	Number of block output operations
<b>ru_ioch (%f)</b>	Number of characters read and written (valid only on HP-UX)
<b>ru_msgsnd (%f)</b>	Number of System V IPC messages sent
<b>ru_msgrcv (%f)</b>	Number of messages received
<b>ru_nsignals (%f)</b>	Number of signals received
<b>ru_nvcsw (%f)</b>	Number of voluntary context switches
<b>ru_nivcsw (%f)</b>	Number of involuntary context switches
<b>ru_exutime (%f)</b>	Exact user time used (valid only on ConvexOS)
<b>mailUser (%s)</b>	Name of the user to whom job related mail was sent
<b>projectName (%s)</b>	LSF project name
<b>exitStatus (%d)</b>	UNIX exit status of the job
<b>maxNumProcessors (%d)</b>	Maximum number of processors specified for the job
<b>loginShell (%s)</b>	Login shell used for the job
<b>timeEvent (%s)</b>	Time event string for the job - JobScheduler only
<b>idx (%d)</b>	Job array index

**maxRMem (%d)**

Maximum resident memory usage in the unit specified by LSF\_UNIT\_FOR\_LIMITS in `lsf.conf` of all processes in the job

**maxRSwap (%d)**

Maximum virtual memory usage in the unit specified by LSF\_UNIT\_FOR\_LIMITS in `lsf.conf` of all processes in the job

**inFileSpool (%s)**

Spool input file (up to 4094 characters for UNIX or 512 characters for Windows)

**commandSpool (%s)**

Spool command file (up to 4094 characters for UNIX or 512 characters for Windows)

**rsvId %s**

Advance reservation ID for a user group name less than 120 characters long; for example, "user2#0"

If the advance reservation user group name is longer than 120 characters, the `rsvId` field output appears last.

**sla (%s)**

SLA service class name under which the job runs

**exceptMask (%d)**

Job exception handling

Values:

- J\_EXCEPT\_OVERRUN 0x02
- J\_EXCEPT\_UNDERUN 0x04
- J\_EXCEPT\_IDLE 0x80

**additionalInfo (%s)**

Placement information of HPC jobs

**exitInfo (%d)**

Job termination reason, mapped to corresponding termination keyword displayed by `bacct`.

**warningTimePeriod (%d)**

Job warning time period in seconds

**warningAction (%s)**

Job warning action

**chargedSAAP (%s)**

SAAP charged to a job

**licenseProject (%s)**

LSF License Scheduler project name

**options3 (%d)**

Bit flags for job processing

**app (%s)**

Application profile name

**postExecCmd (%s)**

Post-execution command to run on the execution host after the job finishes

**runtimeEstimation (%d)**

Estimated run time for the job

**jobGroupName (%s)**

Job group name

**resizeNotifyCmd**

Resize notification command to be invoked on the first execution host upon a resize request.

**lastResizeTime**

Last resize time. The latest wall clock time when a job allocation is changed.

**rsvId %s**

Advance reservation ID for a user group name more than 120 characters long.

If the advance reservation user group name is longer than 120 characters, the rsvId field output appears last.

## EVENT\_ADRSV\_FINISH

An advance reservation has expired. The fields in order of occurrence are:

**Event type (%s)**

Which is "EVENT\_ADRSV\_FINISH"

**Version Number (%s)**

Version number of the log file format

**Event Logging Time (%d)**

Time the event was logged (in seconds since the epoch); for example, "1038942015"

**Reservation Creation Time (%d)**

Time the advance reservation was created (in seconds since the epoch); for example, "1038938898"

**Reservation Type (%d)**

Type of advance reservation request:

- User reservation (RSV\_OPTION\_USER, defined as 0x001)
- User group reservation (RSV\_OPTION\_GROUP, defined as 0x002)

- System reservation (RSV\_OPTION\_SYSTEM, defined as 0x004)
- Recurring reservation (RSV\_OPTION\_RECUR, defined as 0x008)

For example, "9" is a recurring reservation created for a user.

**Creator ID (%d)**

UNIX user ID of the reservation creator; for example, "30408"

**Reservation ID (rsvid %s)**

For example, "user2#0"

**User Name (%s)**

User name of the reservation user; for example, "user2"

**Time Window (%s)**

Time window of the reservation:

- One-time reservation in seconds since the epoch; for example, "1033761000- 1033761600"
- Recurring reservation; for example, "17: 50- 18: 00"

**Creator Name (%s)**

User name of the reservation creator; for example, "user1"

**Duration (%d)**

Duration of the reservation, in hours, minutes, seconds; for example, "600" is 6 hours, 0 minutes, 0 seconds

**Number of Resources (%d)**

Number of reserved resource pairs in the resource list; for example "2" indicates 2 resource pairs ("hostA 1 hostB 1")

**Host Name (%s)**

Reservation host name; for example, "hostA"

**Number of CPUs (%d)**

Number of reserved CPUs; for example "1"

## JOB\_RESIZE

When there is an allocation change, LSF logs the event after mbatchd receives "JOB\_RESIZE\_NOTIFY\_DONE" event. From lastResizeTime and eventTime, people can easily calculate the duration of previous job allocation. The fields in order of occurrence are:

**Version number (%s)**

The version number.

**Event Time (%d)**

Time the event was logged (in seconds since the epoch).

**jobId (%d)**

lsb.acct

ID for the job.

**tdx (%d)**

Job array index.

**startTime (%d)**

The start time of the running job.

**userId (%d)**

UNIX user ID of the user invoking the command

**userName (%s)**

User name of the submitter

**resizeType (%d)**

Resize event type, 0, grow, 1 shrink.

**lastResizeTime(%d)**

The wall clock time when job allocation is changed previously. The first lastResizeTime is the job start time.

**numExecHosts (%d)**

The number of execution hosts before allocation is changed. Support LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE".

**execHosts (%s)**

Execution host list before allocation is changed. Support LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE".

**numResizeHosts (%d)**

Number of processors used for execution during resize. If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is the number of hosts listed in short format.

**resizeHosts (%s)**

List of execution host names during resize. If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is logged in a shortened format.

# lsb.applications

The `lsb.applications` file defines application profiles. Use application profiles to define common parameters for the same type of jobs, including the execution requirements of the applications, the resources they require, and how they should be run and managed.

This file is optional. Use the `DEFAULT_APPLICATION` parameter in `lsb.params` to specify a default application profile for all jobs. LSF does not automatically assign a default application profile.

This file is installed by default in `LSB_CONFDIR/cluster_name/confidir`.

## Changing lsb.applications configuration

After making any changes to `lsb.applications`, run `badminton reconfig` to reconfigure `mbatchd`. Configuration changes apply to pending jobs only. Running jobs are not affected.

## lsb.applications structure

Each application profile definition begins with the line `Begin Application` and ends with the line `End Application`. The application name must be specified. All other parameters are optional.

### Example

```
Begin Application
NAME           = catia
DESCRIPTION    = CATIA V5
CPULIMIT      = 24:0/hostA      # 24 hours of hostA
FILELIMIT     = 20000
DATALIMIT     = 20000          # jobs data segment limit
CORELIMIT     = 20000
PROCLIMIT     = 5              # job processor limit
REQUEUE_EXIT_VALUES = 55 34 78
End Application
```

See the `lsb.applications` template file for additional application profile examples.

## Parameters

- ABS\_RUNLIMIT
- BIND\_JOB
- CHKPNT\_DIR
- CHKPNT\_INITPERIOD
- CHKPNT\_PERIOD
- CHKPNT\_METHOD
- CHUNK\_JOB\_SIZE
- CORELIMIT
- CPULIMIT
- DATALIMIT
- DESCRIPTION
- DJOB\_COMMFAIL\_ACTION

- DJOB\_ENV\_SCRIPT
- DJOB\_HB\_INTERVAL
- DJOB\_RESIZE\_GRACE\_PERIOD
- DJOB\_RU\_INTERVAL
- JOB\_INCLUDE\_POSTPROC
- JOB\_POSTPROC\_TIMEOUT
- FILELIMIT
- JOB\_STARTER
- LOCAL\_MAX\_PREEEXEC\_RETRY
- MAX\_JOB\_PREEMPT
- MAX\_JOB\_REQUEUE
- MAX\_PREEEXEC\_RETRY
- MEMLIMIT
- MEMLIMIT\_TYPE
- MIG
- NAME
- NO\_PREEMPT\_FINISH\_TIME
- NO\_PREEMPT\_RUN\_TIME
- PERSISTENT\_HOST\_ORDER
- POST\_EXEC
- PRE\_EXEC
- PROCESSLIMIT
- PROCLIMIT
- REMOTE\_MAX\_PREEEXEC\_RETRY
- REQUEUE\_EXIT\_VALUES
- RERUNNABLE
- RES\_REQ
- RESIZABLE\_JOBS
- RESIZE\_NOTIFY\_CMD
- RESUME\_CONTROL
- RTASK\_GONE\_ACTION
- RUNLIMIT
- RUNTIME
- STACKLIMIT
- SUCCESS\_EXIT\_VALUES
- SUSPEND\_CONTROL
- SWAPLIMIT
- TERMINATE\_CONTROL
- THREADLIMIT
- USE\_PAM\_CREDS

## ABS\_RUNLIMIT

### Syntax

**ABS\_RUNLIMIT=y | Y**

## Description

If set, absolute (wall-clock) run time is used instead of normalized run time for all jobs submitted with the following values:

- Run time limit specified by the `-W` option of `bsub`
- `RUNLIMIT` queue-level parameter in `lsb.queues`
- `RUNLIMIT` application-level parameter in `lsb.applications`
- `RUNTIME` parameter in `lsb.applications`

The runtime estimates and limits are not normalized by the host CPU factor.

## Default

Not defined. Run limit and runtime estimate are normalized.

## BIND\_JOB

### Syntax

**BIND\_JOB=NONE | BALANCE | PACK | ANY | USER | USER\_CPU\_LIST**

## Description

Specifies the processor binding policy for sequential and parallel job processes that run on a single host. On Linux execution hosts that support this feature, job processes are hard bound to selected processors.

If processor binding feature is not configured with the `BIND_JOB` parameter in an application profile in `lsb.applications`, the `lsf.conf` configuration setting takes effect. The application profile configuration for processor binding overrides the `lsf.conf` configuration.

For backwards compatibility:

- `BIND_JOB=Y` is interpreted as `BIND_JOB=BALANCE`
- `BIND_JOB=N` is interpreted as `BIND_JOB=NONE`

## Supported platforms

Linux with kernel version 2.6 or higher

## Default

Not defined. Processor binding is disabled.

## CHKPNT\_DIR

### Syntax

**CHKPNT\_DIR=*chkpnt\_dir***

## Description

Specifies the checkpoint directory for automatic checkpointing for the application. To enable automatic checkpoint for the application profile, administrators must specify a checkpoint directory in the configuration of the application profile.

If `CHKPNT_PERIOD`, `CHKPNT_INITPERIOD` or `CHKPNT_METHOD` was set in an application profile but `CHKPNT_DIR` was not set, a warning message is issued and those settings are ignored.

The checkpoint directory is the directory where the checkpoint files are created. Specify an absolute path or a path relative to the current working directory for the job. Do not use environment variables in the directory path.

If checkpoint-related configuration is specified in both the queue and an application profile, the application profile setting overrides queue level configuration.

If checkpoint-related configuration is specified in the queue, application profile, and at job level:

- Application-level and job-level parameters are merged. If the same parameter is defined at both job-level and in the application profile, the job-level value overrides the application profile value.
- The merged result of job-level and application profile settings override queue-level configuration.

To enable checkpointing of MultiCluster jobs, define a checkpoint directory in an application profile (`CHKPNT_DIR`, `CHKPNT_PERIOD`, `CHKPNT_INITPERIOD`, `CHKPNT_METHOD` in `lsb.applications`) of both submission cluster and execution cluster. LSF uses the directory specified in the execution cluster.

Checkpointing is not supported if a job runs on a leased host.

The file path of the checkpoint directory can contain up to 4000 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.

## Default

Not defined

## CHKPNT\_INITPERIOD

## Syntax

`CHKPNT_INITPERIOD=init_chkpnt_period`

## Description

Specifies the initial checkpoint period in minutes. `CHKPNT_DIR` must be set in the application profile for this parameter to take effect. The periodic checkpoint specified by `CHKPNT_PERIOD` does not happen until the initial period has elapsed.

Specify a positive integer.

Job-level command line values override the application profile configuration.

If administrators specify an initial checkpoint period and do not specify a checkpoint period (`CHKPNT_PERIOD`), the job will only checkpoint once.

If the initial checkpoint period of a job is specified, and you run `bchkpnt` to checkpoint the job at a time before the initial checkpoint period, the initial checkpoint period is not changed by `bchkpnt`. The first automatic checkpoint still happens after the specified number of minutes.

## Default

Not defined

## CHKPNT\_PERIOD

### Syntax

**CHKPNT\_PERIOD**=*chkpnt\_period*

### Description

Specifies the checkpoint period for the application in minutes. CHKPNT\_DIR must be set in the application profile for this parameter to take effect. The running job is checkpointed automatically every checkpoint period.

Specify a positive integer.

Job-level command line values override the application profile and queue level configurations. Application profile level configuration overrides the queue level configuration.

## Default

Not defined

## CHKPNT\_METHOD

### Syntax

**CHKPNT\_METHOD**=*chkpnt\_method*

### Description

Specifies the checkpoint method. CHKPNT\_DIR must be set in the application profile for this parameter to take effect. Job-level command line values override the application profile configuration.

## Default

Not defined

## CHUNK\_JOB\_SIZE

### Syntax

**CHUNK\_JOB\_SIZE**=*integer*

### Description

Chunk jobs only. Allows jobs submitted to the same application profile to be chunked together and specifies the maximum number of jobs allowed to be dispatched together in a chunk. Specify a positive integer greater than or equal to 1.

All of the jobs in the chunk are scheduled and dispatched as a unit, rather than individually.

Specify CHUNK\_JOB\_SIZE=1 to disable job chunking for the application. This value overrides chunk job dispatch configured in the queue.

Use the `CHUNK_JOB_SIZE` parameter to configure application profiles that chunk small, short-running jobs. The ideal candidates for job chunking are jobs that have the same host and resource requirements and typically take 1 to 2 minutes to run.

The ideal candidates for job chunking are jobs that have the same host and resource requirements and typically take 1 to 2 minutes to run.

Job chunking can have the following advantages:

- Reduces communication between `sbatchd` and `mbatchd` and reduces scheduling overhead in `mbschd`.
- Increases job throughput in `mbatchd` and CPU utilization on the execution hosts.

However, throughput can deteriorate if the chunk job size is too big. Performance may decrease on profiles with `CHUNK_JOB_SIZE` greater than 30. You should evaluate the chunk job size on your own systems for best performance.

With MultiCluster job forwarding model, this parameter does not affect MultiCluster jobs that are forwarded to a remote cluster.

## Compatibility

This parameter is ignored and jobs are not chunked under the following conditions:

- CPU limit greater than 30 minutes (`CPULIMIT` parameter in `lsb.queues` or `lsb.applications`)
- Run limit greater than 30 minutes (`RUNLIMIT` parameter in `lsb.queues` or `lsb.applications`)
- Runtime estimate greater than 30 minutes (`RUNTIME` parameter in `lsb.applications`)

If `CHUNK_JOB_DURATION` is set in `lsb.params`, chunk jobs are accepted regardless of the value of `CPULIMIT`, `RUNLIMIT` or `RUNTIME`.

## Default

Not defined

## CORELIMIT

### Syntax

**CORELIMIT**=*integer*

### Description

The per-process (soft) core file size limit for all of the processes belonging to a job from this application profile (see `getrlimit(2)`). Application-level limits override any default limit specified in the queue, but must be less than the hard limit of the submission queue. Job-level core limit (`bsub -C`) overrides queue-level and application-level limits.

By default, the limit is specified in KB. Use `LSF_UNIT_FOR_LIMITS` in `lsf.conf` to specify a larger unit for the the limit (MB, GB, TB, PB, or EB).

## Default

Unlimited

## CPULIMIT

### Syntax

**CPULIMIT**=[*[hour:]minute*]/*host\_name* | *host\_model*]

### Description

Normalized CPU time allowed for all processes of a job running in the application profile. The name of a host or host model specifies the CPU time normalization host to use.

Limits the total CPU time the job can use. This parameter is useful for preventing runaway jobs or jobs that use up too many resources.

When the total CPU time for the whole job has reached the limit, a SIGXCPU signal is sent to all processes belonging to the job. If the job has no signal handler for SIGXCPU, the job is killed immediately. If the SIGXCPU signal is handled, blocked, or ignored by the application, then after the grace period expires, LSF sends SIGINT, SIGTERM, and SIGKILL to the job to kill it.

If a job dynamically spawns processes, the CPU time used by these processes is accumulated over the life of the job.

Processes that exist for fewer than 30 seconds may be ignored.

By default, jobs submitted to the application profile without a job-level CPU limit (`bsub -c`) are killed when the CPU limit is reached. Application-level limits override any default limit specified in the queue.

The number of minutes may be greater than 59. For example, three and a half hours can be specified either as 3:30 or 210.

If no host or host model is given with the CPU time, LSF uses the default CPU time normalization host defined at the queue level (`DEFAULT_HOST_SPEC` in `lsb.queues`) if it has been configured, otherwise uses the default CPU time normalization host defined at the cluster level (`DEFAULT_HOST_SPEC` in `lsb.params`) if it has been configured, otherwise uses the host with the largest CPU factor (the fastest host in the cluster).

On Windows, a job that runs under a CPU time limit may exceed that limit by up to `SBD_SLEEP_TIME`. This is because `sbatchd` periodically checks if the limit has been exceeded.

On UNIX systems, the CPU limit can be enforced by the operating system at the process level.

You can define whether the CPU limit is a per-process limit enforced by the OS or a per-job limit enforced by LSF with `LSB_JOB_CPULIMIT` in `lsf.conf`.

### Default

Unlimited

## DATALIMIT

### Syntax

**DATALIMIT**=*integer*

## Description

The per-process (soft) data segment size limit (in KB) for all of the processes belonging to a job running in the application profile (see `getrlimit(2)`).

By default, jobs submitted to the application profile without a job-level data limit (`bsub -D`) are killed when the data limit is reached. Application-level limits override any default limit specified in the queue, but must be less than the hard limit of the submission queue.

## Default

Unlimited

## DESCRIPTION

## Syntax

**DESCRIPTION**=*text*

## Description

Description of the application profile. The description is displayed by `bapp -l`.

The description should clearly describe the service features of the application profile to help users select the proper profile for each job.

The text can include any characters, including white space. The text can be extended to multiple lines by ending the preceding line with a backslash (`\`). The maximum length for the text is 512 characters.

## DJOB\_COMMFAIL\_ACTION

## Syntax

**DJOB\_COMMFAIL\_ACTION**="KILL\_TASKS"

## Description

Defines the action LSF should take if it detects a communication failure with one or more remote parallel or distributed tasks. If defined, LSF tries to kill all the current tasks of a parallel or distributed job associated with the communication failure. If not defined, LSF terminates all tasks and shuts down the entire job.

This parameter only applies to the `blaunch` distributed application framework.

When defined in an application profile, the `LSB_DJOB_COMMFAIL_ACTION` variable is set when running `bsub -app` for the specified application.

## Default

Not defined. Terminate all tasks, and shut down the entire job.

## DJOB\_DISABLED

## Syntax

**DJOB\_DISABLED**=Y | N

## Description

Disables the bl aunch distributed application framework.

## Default

Not defined. Distributed application framework is enabled.

## DJOB\_ENV\_SCRIPT

## Syntax

**DJOB\_ENV\_SCRIPT**=*script\_name*

## Description

Defines the name of a user-defined script for setting and cleaning up the parallel or distributed job environment.

The specified script must support a setup argument and a cleanup argument. The script is executed by LSF with the setup argument before launching a parallel or distributed job, and with argument cleanup after the job is finished.

The script runs as the user, and is part of the job.

If a full path is specified, LSF uses the path name for the execution. Otherwise, LSF looks for the executable from \$LSF\_BINDIR.

This parameter only applies to the bl aunch distributed application framework.

When defined in an application profile, the LSB\_DJOB\_ENV\_SCRIPT variable is set when running `bsub - app` for the specified application.

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for %J (*job\_ID*) and %I (*index\_ID*).

## Default

Not defined.

## DJOB\_HB\_INTERVAL

## Syntax

**DJOB\_HB\_INTERVAL**=*seconds*

## Description

Value in seconds used to calculate the heartbeat interval between the task RES and job RES of a parallel or distributed job.

This parameter only applies to the bl aunch distributed application framework.

When DJOB\_HB\_INTERVAL is specified, the interval is scaled according to the number of tasks in the job:

$\max(\text{DJOB\_HB\_INTERVAL}, 10) + \text{host\_factor}$

where

$host\_factor = 0.01 * number\ of\ hosts\ allocated\ for\ the\ job$

## Default

Not defined. Interval is equal to SBD\_SLEEP\_TIME in lsb.params, where the default value of SBD\_SLEEP\_TIME is 30 seconds.

## DJOB\_RESIZE\_GRACE\_PERIOD

### Syntax

DJOB\_RESIZE\_GRACE\_PERIOD = *seconds*

### Description

When a resizable job releases resources, the LSF distributed parallel job framework terminates running tasks if a host has been completely removed. A DJOB\_RESIZE\_GRACE\_PERIOD defines a grace period in seconds for the application to clean up tasks itself before LSF forcibly terminates them.

## Default

No grace period.

## DJOB\_RU\_INTERVAL

### Syntax

DJOB\_RU\_INTERVAL=*seconds*

### Description

Value in seconds used to calculate the resource usage update interval for the tasks of a parallel or distributed job.

This parameter only applies to the b1 launch distributed application framework.

When DJOB\_RU\_INTERVAL is specified, the interval is scaled according to the number of tasks in the job:

$\max(\text{DJOB\_RU\_INTERVAL}, 10) + host\_factor$

where

$host\_factor = 0.01 * number\ of\ hosts\ allocated\ for\ the\ job$

## Default

Not defined. Interval is equal to SBD\_SLEEP\_TIME in lsb.params, where the default value of SBD\_SLEEP\_TIME is 30 seconds.

## JOB\_INCLUDE\_POSTPROC

### Syntax

JOB\_INCLUDE\_POSTPROC=Y | N

## Description

Specifies whether LSF includes the post-execution processing of the job as part of the job. When set to Y:

- Prevents a new job from starting on a host until post-execution processing is finished on that host
- Includes the CPU and run times of post-execution processing with the job CPU and run times
- sbatchd sends both job finish status (DONE or EXIT) and post-execution processing status (POST\_DONE or POST\_ERR) to mbatchd at the same time

The variable LSB\_JOB\_INCLUDE\_POSTPROC in the user environment overrides the value of JOB\_INCLUDE\_POSTPROC in an application profile in `lsb.applications`.

JOB\_INCLUDE\_POSTPROC in an application profile in `lsb.applications` overrides the value of JOB\_INCLUDE\_POSTPROC in `lsb.params`.

For SGI cpusets, if JOB\_INCLUDE\_POSTPROC=Y, LSF does not release the cpuset until post-execution processing has finished, even though post-execution processes are not attached to the cpuset.

## Default

N. Post-execution processing is not included as part of the job, and a new job can start on the execution host before post-execution processing finishes.

## JOB\_POSTPROC\_TIMEOUT

### Syntax

**JOB\_POSTPROC\_TIMEOUT**=*minutes*

### Description

Specifies a timeout in minutes for job post-execution processing. The specified timeout must be greater than zero

If post-execution processing takes longer than the timeout, sbatchd reports that post-execution has failed (POST\_ERR status), and kills the process group of the job's post-execution processes. Only the parent process of the post-execution command is killed when the timeout expires. The child processes of the post-execution command are not killed.

If JOB\_INCLUDE\_POSTPROC=Y, and sbatchd kills the post-execution processes because the timeout has been reached, the CPU time of the post-execution processing is set to 0, and the job's CPU time does not include the CPU time of post-execution processing.

JOB\_POSTPROC\_TIMEOUT defined in an application profile in `lsb.applications` overrides the value in `lsb.params`. JOB\_POSTPROC\_TIMEOUT cannot be defined in user environment.

## Default

Not defined. Post-execution processing does not time out.

## FILELIMIT

### Syntax

**FILELIMIT**=*integer*

## Description

The per-process (soft) file size limit (in KB) for all of the processes belonging to a job running in the application profile (see `getrlimit(2)`). Application-level limits override any default limit specified in the queue, but must be less than the hard limit of the submission queue.

## Default

Unlimited

## JOB\_STARTER

### Syntax

```
JOB_STARTER=starter [starter] ["%USRCMD"] [starter]
```

### Description

Creates a specific environment for submitted jobs prior to execution. An application-level job starter overrides a queue-level job starter.

*starter* is any executable that can be used to start the job (i.e., can accept the job as an input argument). Optionally, additional strings can be specified.

By default, the user commands run after the job starter. A special string, %USRCMD, can be used to represent the position of the user's job in the job starter command line. The %USRCMD string and any additional commands must be enclosed in quotation marks (" ").

### Example

```
JOB_STARTER=csh -c "%USRCMD; sleep 10"
```

In this case, if a user submits a job

```
bsub myjob arguments
```

the command that actually runs is:

```
csh -c "myjob arguments; sleep 10"
```

## Default

Not defined. No job starter is used,

## LOCAL\_MAX\_PREEEXEC\_RETRY

### Syntax

```
LOCAL_MAX_PREEEXEC_RETRY=integer
```

### Description

The maximum number of times to attempt the pre-execution command of a job on the local cluster.

### Valid values

$0 < \text{MAX\_PREEEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in `lsf.h`.

## Default

Not defined. The number of preexec retry times is unlimited

## MAX\_JOB\_PREEMPT

### Syntax

**MAX\_JOB\_PREEMPT=integer**

### Description

The maximum number of times a job can be preempted. Applies to queue-level jobs only.

### Valid values

$0 < \text{MAX\_JOB\_PREEMPT} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in l sf . h.

## Default

Not defined. The number of preemption times is unlimited.

## MAX\_JOB\_REQUEUE

### Syntax

**MAX\_JOB\_REQUEUE=integer**

### Description

The maximum number of times to requeue a job automatically.

### Valid values

$0 < \text{MAX\_JOB\_REQUEUE} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in l sf . h.

## Default

Not defined. The number of requeue times is unlimited

## MAX\_PREEEXEC\_RETRY

### Syntax

**MAX\_PREEEXEC\_RETRY=integer**

### Description

MultiCluster job forwarding model only. The maximum number of times to attempt the pre-execution command of a job from a remote cluster.

If the job's pre-execution command fails all attempts, the job is returned to the submission cluster.

## Valid values

$0 < \text{MAX\_PREEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in `lsf.h`.

## Default

5

## MEMLIMIT

## Syntax

**MEMLIMIT**=*integer*

## Description

The per-process (soft) process resident set size limit for all of the processes belonging to a job running in the application profile.

Sets the maximum amount of physical memory (resident set size, RSS) that may be allocated to a process.

By default, the limit is specified in KB. Use `LSF_UNIT_FOR_LIMITS` in `lsf.conf` to specify a larger unit for the limit (MB, GB, TB, PB, or EB).

By default, jobs submitted to the application profile without a job-level memory limit are killed when the memory limit is reached. Application-level limits override any default limit specified in the queue, but must be less than the hard limit of the submission queue.

LSF has two methods of enforcing memory usage:

- OS Memory Limit Enforcement
- LSF Memory Limit Enforcement

## OS memory limit enforcement

OS memory limit enforcement is the default MEMLIMIT behavior and does not require further configuration. OS enforcement usually allows the process to eventually run to completion. LSF passes MEMLIMIT to the OS, which uses it as a guide for the system scheduler and memory allocator. The system may allocate more memory to a process if there is a surplus. When memory is low, the system takes memory from and lowers the scheduling priority (renice) of a process that has exceeded its declared MEMLIMIT. Only available on systems that support `RLIMIT_RSS` for `setrlimit()`.

Not supported on:

- Sun Solaris 2.x
- Windows

## LSF memory limit enforcement

To enable LSF memory limit enforcement, set `LSB_MEMPLIMIT_ENFORCE` in `lsf.conf` to `y`. LSF memory limit enforcement explicitly sends a signal to kill a running process once it has allocated memory past MEMLIMIT.

You can also enable LSF memory limit enforcement by setting `LSB_JOB_MEMPLIMIT` in `lsf.conf` to `y`. The difference between `LSB_JOB_MEMPLIMIT` set to `y` and

LSB\_MEMLIMIT\_ENFORCE set to y is that with LSB\_JOB\_MEMLIMIT, only the per-job memory limit enforced by LSF is enabled. The per-process memory limit enforced by the OS is disabled. With LSB\_MEMLIMIT\_ENFORCE set to y, both the per-job memory limit enforced by LSF and the per-process memory limit enforced by the OS are enabled.

Available for all systems on which LSF collects total memory usage.

## Default

Unlimited

## MEMLIMIT\_TYPE

## Syntax

**MEMLIMIT\_TYPE=JOB [PROCESS] [TASK]**

**MEMLIMIT\_TYPE=PROCESS [JOB] [TASK]**

**MEMLIMIT\_TYPE=TASK [PROCESS] [JOB]**

## Description

A memory limit is the maximum amount of memory a job is allowed to consume. Jobs that exceed the level are killed. You can specify different types of memory limits to enforce. Use any combination of JOB, PROCESS, and TASK.

By specifying a value in the application profile, you overwrite these three parameters: LSB\_JOB\_MEMLIMIT, LSB\_MEMLIMIT\_ENFORCE, LSF\_HPC\_EXTENSIONS (TASK\_MEMLIMIT).

---

### Note:

A task list is a list in LSF that keeps track of the default resource requirements for different applications and task eligibility for remote execution.

---

- **PROCESS:** Applies a memory limit by OS process, which is enforced by the OS on the slave machine (where the job is running). When the memory allocated to one process of the job exceeds the memory limit, LSF kills the job.
- **TASK:** Applies a memory limit based on the task list file. It is enforced by LSF. LSF terminates the entire parallel job if any single task exceeds the limit setting for memory and swap limits.
- **JOB:** Applies a memory limit identified in a job and enforced by LSF. When the sum of the memory allocated to all processes of the job exceeds the memory limit, LSF kills the job.
- **PROCESS TASK:** Enables both process-level memory limit enforced by OS and task-level memory limit enforced by LSF.
- **PROCESS JOB:** Enables both process-level memory limit enforced by OS and job-level memory limit enforced by LSF.
- **TASK JOB:** Enables both task-level memory limit enforced by LSF and job-level memory limit enforced by LSF.
- **PROCESS TASK JOB:** Enables process-level memory limit enforced by OS, task-level memory limit enforced by LSF, and job-level memory limit enforced by LSF.

## Default

Not defined. The memory limit-level is still controlled by LSF\_HPC\_EXTENSIONS=TASK\_MEMLIMIT, LSB\_JOB\_MEMLIMIT, LSB\_MEMLIMIT\_ENFORCE

## MIG

### Syntax

**MIG**=*minutes*

### Description

Enables automatic job migration and specifies the migration threshold for checkpointable or rerunnable jobs, in minutes.

LSF automatically migrates jobs that have been in the SSUSP state for more than the specified number of minutes. A value of 0 specifies that a suspended job is migrated immediately. The migration threshold applies to all jobs running on the host.

Job-level command line migration threshold overrides threshold configuration in application profile and queue. Application profile configuration overrides queue level configuration.

When a host migration threshold is specified, and is lower than the value for the job, the queue, or the application, the host value is used.

Members of a chunk job can be migrated. Chunk jobs in WAIT state are removed from the job chunk and put into PEND state.

Does not affect MultiCluster jobs that are forwarded to a remote cluster.

## Default

Not defined. LSF does not migrate checkpointable or rerunnable jobs automatically.

## NAME

### Syntax

**NAME**=*string*

### Description

*Required.* Unique name for the application profile.

Specify any ASCII string up to 60 characters long. You can use letters, digits, underscores (`_`), dashes (`-`), periods (`.`) or spaces in the name. The application profile name must be unique within the cluster.

---

**Note:**

If you want to specify the ApplicationVersion in a JSDL file, include the version when you define the application profile name. Separate the name and version by a space, as shown in the following example:

```
NAME=myapp 1.0
```

---

## Default

You must specify this parameter to define an application profile. LSF does not automatically assign a default application profile name.

## NO\_PREEMPT\_FINISH\_TIME

### Syntax

**NO\_PREEMPT\_FINISH\_TIME**=*minutes* | *percentage*

### Description

Prevents preemption of jobs that will finish within the specified number of minutes or the specified percentage of the estimated run time or run limit.

Specifies that jobs due to finish within the specified number of minutes or percentage of job duration should not be preempted, where *minutes* is wall-clock time, not normalized time. Percentage must be greater than 0 or less than 100% (between 1% and 99%).

For example, if the job run limit is 60 minutes and NO\_PREEMPT\_FINISH\_TIME=10%, the job cannot be preempted after it running 54 minutes or longer.

If you specify percentage for NO\_PREEMPT\_RUN\_TIME, requires a run time (bsub - We or RUNTIME in l sb. appl i cat i ons), or run limit to be specified for the job (bsub - W, or RUNLIMIT in l sb. queues, or RUNLIMIT in l sb. appl i cat i ons)

## NO\_PREEMPT\_RUN\_TIME

### Syntax

**NO\_PREEMPT\_RUN\_TIME**=*minutes* | *percentage*

### Description

Prevents preemption of jobs that have been running for the specified number of minutes or the specified percentage of the estimated run time or run limit.

Specifies that jobs that have been running for the specified number of minutes or longer should not be preempted, where *minutes* is wall-clock time, not normalized time. Percentage must be greater than 0 or less than 100% (between 1% and 99%).

For example, if the job run limit is 60 minutes and NO\_PREEMPT\_RUN\_TIME=50%, the job cannot be preempted after it running 30 minutes or longer.

If you specify percentage for NO\_PREEMPT\_RUN\_TIME, requires a run time (bsub - We or RUNTIME in l sb. appl i cat i ons), or run limit to be specified for the job (bsub - W, or RUNLIMIT in l sb. queues, or RUNLIMIT in l sb. appl i cat i ons)

## PERSISTENT\_HOST\_ORDER

### Syntax

**PERSISTENT\_HOST\_ORDER**=Y | yes | N | no

### Description

Applies when migrating parallel jobs in a multicluster environment. Setting PERSISTENT\_HOST\_ORDER=Y ensures that jobs are restarted on hosts based on

alphabetical names of the hosts, preventing them from being restarted on the same hosts that they ran on before migration.

## Default

PERSISTENT\_HOST\_ORDER=N. Migrated jobs in a multicluster environment could run on the same hosts that they ran on before.

## POST\_EXEC

### Syntax

**POST\_EXEC=command**

### Description

Enables post-execution processing at the application level. The POST\_EXEC command runs on the execution host after the job finishes. Post-execution commands can be configured at the job, application, and queue levels.

If both application-level (POST\_EXEC in `lsb.applications`) and job-level post-execution commands are specified, job level post-execution overrides application-level post-execution commands. Queue-level post-execution commands (POST\_EXEC in `lsb.queues`) run after application-level post-execution and job-level post-execution commands.

The POST\_EXEC command uses the same environment variable values as the job, and runs under the user account of the user who submits the job. To run post-execution commands under a different user account (such as root for privileged operations), configure the parameter LSB\_PRE\_POST\_EXEC\_USER in `lsf.sudoers`.

When a job exits with one of the application profile's REQUEUE\_EXIT\_VALUES, LSF requeues the job and sets the environment variable LSB\_JOBPEND. The post-execution command runs after the requeued job finishes.

When the post-execution command is run, the environment variable LSB\_JOBEXIT\_STAT is set to the exit status of the job. If the execution environment for the job cannot be set up, LSB\_JOBEXIT\_STAT is set to 0 (zero).

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for %J (*job\_ID*) and %I (*index\_ID*).

For UNIX:

- The pre- and post-execution commands run in the `/tmp` directory under `/bin/sh -c`, which allows the use of shell features in the commands. The following example shows valid configuration lines:

```
PRE_EXEC= /usr/share/lsf/misc/testq_pre >> /tmp/pre.out
```

```
POST_EXEC= /usr/share/lsf/misc/testq_post | grep -v "Hey!"
```

- LSF sets the PATH environment variable to

```
PATH='/bin /usr/bin /sbin /usr/sbin'
```

- The stdin, stdout, and stderr are set to `/dev/null`

- To allow UNIX users to define their own post-execution commands, an LSF administrator specifies the environment variable \$USER\_POSTEXEC as the POST\_EXEC command. A user then defines the post-execution command:

```
setenv USER_POSTEXEC /path_name
```

---

**Note:**

The path name for the post-execution command must be an absolute path. Do not define `POST_EXEC=$USER_POSTEXEC` when `LSB_PRE_POST_EXEC_USER=root`.

---

For Windows:

- The pre- and post-execution commands run under `cmd. exe /c`
  - The standard input, standard output, and standard error are set to NULL
  - The PATH is determined by the setup of the LSF Service
- 

**Note:**

For post-execution commands that execute on a Windows Server 2003, x64 Edition platform, users must have read and execute privileges for `cmd. exe`.

---

## Default

Not defined. No post-execution commands are associated with the application profile.

## PRE\_EXEC

## Syntax

**PRE\_EXEC=command**

## Description

Enables pre-execution processing at the application level. The `PRE_EXEC` command runs on the execution host before the job starts. If the `PRE_EXEC` command exits with a non-zero exit code, LSF requeues the job to the front of the queue.

Pre-execution commands can be configured at the application, queue, and job levels and run in the following order:

1. The queue-level command
2. The application-level or job-level command. If you specify a command at both the application and job levels, the job-level command overrides the application-level command; the application-level command is ignored.

The `PRE_EXEC` command uses the same environment variable values as the job, and runs under the user account of the user who submits the job. To run pre-execution commands under a different user account (such as root for privileged operations), configure the parameter `LSB_PRE_POST_EXEC_USER` in `lsf. sudoers`.

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

For UNIX:

- The pre- and post-execution commands run in the `/tmp` directory under `/bin/sh -c`, which allows the use of shell features in the commands. The following example shows valid configuration lines:

```
PRE_EXEC= /usr/share/lsf/misc/testq_pre >> /tmp/pre.out
```

```
POST_EXEC= /usr/share/lsf/misc/testq_post | grep -v "Hey!"
```

- LSF sets the PATH environment variable to
- ```
PATH='/bin /usr/bin /sbin /usr/sbin'
```
- The stdin, stdout, and stderr are set to `/dev/null`

For Windows:

- The pre- and post-execution commands run under `cmd. exe /c`
- The standard input, standard output, and standard error are set to NULL
- The PATH is determined by the setup of the LSF Service

---

#### Note:

For pre-execution commands that execute on a Windows Server 2003, x64 Edition platform, users must have read and execute privileges for `cmd. exe`.

---

## Default

Not defined. No pre-execution commands are associated with the application profile.

## PROCESSLIMIT

### Syntax

**PROCESSLIMIT**=*integer*

### Description

Limits the number of concurrent processes that can be part of a job.

By default, jobs submitted to the application profile without a job-level process limit are killed when the process limit is reached. Application-level limits override any default limit specified in the queue.

SIGINT, SIGTERM, and SIGKILL are sent to the job in sequence when the limit is reached.

### Default

Unlimited

## PROCLIMIT

### Syntax

**PROCLIMIT**=[*minimum\_limit*] [*default\_limit*] *maximum\_limit*

### Description

Maximum number of slots that can be allocated to a job. For parallel jobs, the maximum number of processors that can be allocated to the job.

Optionally specifies the minimum and default number of job slots. All limits must be positive integers greater than or equal to 1 that satisfy the following relationship:

$1 \leq \text{minimum} \leq \text{default} \leq \text{maximum}$

Job-level processor limits (bsub -n) override application-level PROCLIMIT, which overrides queue-level PROCLIMIT. Job-level limits must fall within the maximum and minimum limits of the application profile and the queue.

You can specify up to three limits in the PROCLIMIT parameter:

- One limit—Is the maximum processor limit. The minimum and default limits are set to 1.
- Two limits—The first is the minimum processor limit, and the second one is the maximum. The default is set equal to the minimum. The minimum must be less than or equal to the maximum.
- Three limits—The first is the minimum processor limit, the second is the default processor limit, and the third is the maximum. The minimum must be less than the default and the maximum.

Jobs that request fewer slots than the minimum PROCLIMIT or more slots than the maximum PROCLIMIT cannot use the application profile and are rejected. If the job requests minimum and maximum job slots, the maximum slots requested cannot be less than the minimum PROCLIMIT, and the minimum slots requested cannot be more than the maximum PROCLIMIT.

## Default

Unlimited, the default number of slots is 1

## REMOTE\_MAX\_PREEEXEC\_RETRY

### Syntax

**REMOTE\_MAX\_PREEEXEC\_RETRY**=*integer*

### Description

The maximum number of times to attempt the pre-execution command of a job on the remote cluster.

### Valid values

$0 < \text{MAX\_PREEEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in lsf.h.

## Default

5

## REQUEUE\_EXIT\_VALUES

### Syntax

**REQUEUE\_EXIT\_VALUES**=[*exit\_code* ...] [**EXCLUDE**(*exit\_code* ...)]

## Description

Enables automatic job requeue and sets the `LSB_EXIT_REQUEUE` environment variable. Use spaces to separate multiple exit code values. Application-level exit values override queue-level values. Job-level exit values (`bsub -Q`) override application-level and queue-level values.

`exit_code` has the following form:

```
"[all] [~number ...] | [number ...]"
```

The reserved keyword `all` specifies all exit codes. Exit codes are typically between 0 and 255. Use a tilde (~) to exclude specified exit codes from the list.

Jobs running the same applications generally shared the same exit values under the same conditions. Setting `REQUEUE_EXIT_VALUES` in an application profile instead of in the queue allows different applications with different exit values to share the same queue.

Jobs are requeued to the head of the queue. The output from the failed run is not saved, and the user is not notified by LSF.

Define an exit code as `EXCLUDE(exit_code)` to enable exclusive job requeue. Exclusive job requeue does not work for parallel jobs.

If `mbatchd` is restarted, it does not remember the previous hosts from which the job exited with an exclusive requeue exit code. In this situation, it is possible for a job to be dispatched to hosts on which the job has previously exited with an exclusive exit code.

## Example

```
REQUEUE_EXIT_VALUES=30 EXCLUDE(20)
```

means that jobs with exit code 30 are requeued, jobs with exit code 20 are requeued exclusively, and jobs with any other exit code are not requeued.

## Default

Not defined, Jobs in the application profile are not requeued.

## RERUNNABLE

### Syntax

```
RERUNNABLE=yes | no
```

### Description

If yes, enables automatic job rerun (restart) for any job associated with the application profile.

Rerun is disabled when `RERUNNABLE` is set to no. The yes and no arguments are not case-sensitive.

Members of a chunk job can be rerunnable. If the execution host becomes unavailable, rerunnable chunk job members are removed from the job chunk and dispatched to a different execution host.

Job level rerun (`bsub -r`) overrides the `RERUNNABLE` value specified in the application profile, which overrides the queue specification. `bmod -rn` to make rerunnable jobs non-rerunnable overrides both the application profile and the queue.

## Default

Not defined.

## RES\_REQ

## Syntax

**RES\_REQ**=*res\_req*

## Description

Resource requirements used to determine eligible hosts. Specify a resource requirement string as usual. The resource requirement string lets you specify conditions in a more flexible manner than using the load thresholds.

Resource requirement strings can be simple (applying to the entire job) or compound (applying to the specified number of slots). When a compound resource requirement is set at the application-level, it will be ignored if any job-level resource requirements (simple or compound) are defined.

In the event no job-level resource requirements are set, the compound application-level requirements interact with queue resource requirement strings in the following ways:

In the event no job-level resource requirements are set, the compound application-level requirements interact with queue-level resource requirement strings in the following ways:

- If no queue-level resource requirement is defined or a compound queue-level resource requirement is defined, the compound application-level requirement is used.
- If a simple queue-level requirement is defined, the application-level and queue-level requirements combine as follows:

| section       | compound application and simple queue behavior                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| select        | both levels satisfied; queue requirement applies to all compound terms                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| same          | queue level ignored                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| order<br>span | application-level section overwrites queue-level section (if a given level is present); queue requirement (if used) applies to all compound terms                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| rusage        | <ul style="list-style-type: none"> <li>• both levels merge</li> <li>• queue requirement if a job-based resource is applied to the first compound term, otherwise applies to all compound terms</li> <li>• if conflicts occur the application-level section overwrites the queue-level section.</li> </ul> <p>For example: if the application-level requirement is <math>\text{num1}*\{\text{rusage}[\text{R1}]\} + \text{num2}*\{\text{rusage}[\text{R2}]\}</math> and the queue-level requirement is <math>\text{rusage}[\text{RQ}]</math> where RQ is a job resource, the merged requirement is <math>\text{num1}*\{\text{rusage}[\text{merge}(\text{R1}, \text{RQ})]\} + \text{num2}*\{\text{rusage}[\text{R2}]\}</math></p> |

The following resource requirement sections are supported:

- select
- rusage
- order
- span

- same
- cu

Compound resource requirements do not support the `cu` section, multiple `-R` options, or the `||` operator within the `rusage` section.

For internal load indices and duration, jobs are rejected if they specify resource reservation requirements at the job or application level that exceed the requirements specified in the queue.

If `RES_REQ` is defined at the queue level and there are no load thresholds defined, the pending reasons for each individual load index are not be displayed by `bj obs`.

By default, memory (`mem`) and swap (`swp`) limits in `select[]` and `rusage[]` sections are specified in MB. Use `LSF_UNIT_FOR_LIMITS` in `lsf.conf` to specify a larger unit for these limits (GB, TB, PB, or EB).

When `LSF_STRICT_RESREQ=Y` is configured in `lsf.conf`, resource requirement strings in `select` sections must conform to a more strict syntax. The strict resource requirement syntax only applies to the `select` section. It does not apply to the other resource requirement sections (`order`, `rusage`, `same`, `span`, or `cu`). When `LSF_STRICT_RESREQ=Y` in `lsf.conf`, LSF rejects resource requirement strings where an `rusage` section contains a non-consumable resource.

## select section

For simple resource requirements, the `select` section defined at the application, queue, and job level must all be satisfied.

## rusage section

The `rusage` section can specify additional requests. To do this, use the OR (`|`) operator to separate additional `rusage` strings. The job-level `rusage` section takes precedence. Compound resource requirements do not support use of the `||` operator within the component `rusage` simple resource requirements.

When both job-level and application-level `rusage` sections are defined using simple resource requirement strings, the `rusage` section defined for the job overrides the `rusage` section defined in the application profile. The `rusage` definitions are merged, with the job-level `rusage` taking precedence. Any queue-level requirements are then merged with that result.

For example:

Application-level `RES_REQ`: `RES_REQ=rusage[mem=200:lic=1] ...`

For the job submission:

`bsub -R' rusage[mem=100]' ...`

the resulting requirement for the job is

`rusage[mem=100:lic=1]`

where `mem=100` specified by the job overrides `mem=200` specified by the application profile. However, `lic=1` from application profile is kept, since job does not specify it.

Application-level `RES_REQ` with decay and duration: `RES_REQ=rusage[mem=200:duration=20:decay=1] ...`

For a job submission with no decay or duration:

`bsub -R' rusage[mem=100]' ...`

duration  
defined:

the resulting requirement for the job is:

```
rusage[mem=100: duration=20: decay=1]
```

Application-level duration and decay are merged with the job-level specification, and `mem=100` for the job overrides `mem=200` specified by the application profile. However, `duration=20` and `decay=1` from application profile are kept, since job does not specify them.

## order section

For simple resource requirements the `order` section defined at the job-level overrides any application-level order section. An application-level order section overrides queue-level specification. The `order` section defined at the application level is ignored if any resource requirements are specified at the job level. If the no resource requirements include an `order` section, the default `order r15s: pg` is used.

## span section

For simple resource requirements the `span` section defined at the job-level overrides an application-level span section, which overrides a queue-level span section.

---

### Note:

Define `span[hosts=-1]` in the application profile or in `bsub -R` resource requirement string to disable the span section setting in the queue.

---

## same section

For simple resource requirements all `same` sections defined at the job-level, application-level, and queue-level are combined before the job is dispatched.

---

### Note:

Define `span[hosts=-1]` in the application profile or in `bsub -R` resource requirement string to disable the span section setting in the queue.

---

## cu section

For simple resource requirements the job-level `cu` section overwrites the application-level, and the application-level `cu` section overwrites the queue-level.

## Default

```
select[type==local] order[r15s:pg]
```

If this parameter is defined and a host model or Boolean resource is specified, the default type is any.

## RESIZABLE\_JOBS

### Syntax

```
RESIZABLE_JOBS = [Y|N|auto]
```

## Description

**N|n:** The resizable job feature is disabled in the application profile. Under this setting, all jobs attached to this application profile are not resizable. All `resize` and `bsub -ar` commands will be rejected with a proper error message.

**Y|y:** Resize is enabled in the application profile and all jobs belonging to the application are resizable by default. Under this setting, users can run `resize` commands to cancel pending resource allocation requests for the job or release resources from an existing job allocation, or use `bsub` to submit an autoresizable job.

**auto:** All jobs belonging to the application will be autoresizable.

Resizable jobs must be submitted with an application profile that defines `RESIZABLE_JOBS` as either `auto` or `Y`. If application defines `RESIZABLE_JOBS=auto`, but administrator changes it to `N` and reconfigures LSF, jobs without job-level auto resizable attribute become not autoresizable. For running jobs that are in the middle of notification stage, LSF lets current notification complete and stops scheduling. Changing `RESIZABLE_JOBS` configuration does not affect jobs with job-level autoresizable attribute. (This behavior is same as exclusive job, `bsub -x` and `EXCLUSIVE` parameter in queue level.)

Auto-resizable jobs cannot be submitted with compute unit resource requirements. In the event a `bswitch` call or queue reconfiguration results in an auto-resizable job running in a queue with compute unit resource requirements, the job will no longer be auto-resizable.

Resizable jobs cannot have compound resource requirements.

## Default

If the parameter is undefined, the default value is `N`.

## RESIZE\_NOTIFY\_CMD

### Syntax

`RESIZE_NOTIFY_CMD = notification_command`

## Description

Defines an executable command to be invoked on the first execution host of a job when a resize event occurs. The maximum length of notification command is 4 KB.

## Default

Not defined. No resize notification command is invoked.

## RESUME\_CONTROL

### Syntax

`RESUME_CONTROL=signal | command`

---

#### Remember:

Unlike the `JOB_CONTROLS` parameter in `lsb_queues`, the `RESUME_CONTROL` parameter does not require square brackets (`[ ]`) around the action.

---

- *signal* is a UNIX signal name. The specified signal is sent to the job. The same set of signals is not supported on all UNIX systems. To display a list of the symbolic names of the signals (without the SIG prefix) supported on your system, use the `kill -l` command.
- *command* specifies a `/bin/sh` command line to be invoked. Do not quote the command line inside an action definition. Do not specify a signal followed by an action that triggers the same signal. For example, do not specify `RESUME_CONTROL=br resume`. This causes a deadlock between the signal and the action.

## Description

Changes the behavior of the RESUME action in LSF.

- The contents of the configuration line for the action are run with `/bin/sh -c` so you can use shell features in the command.
- The standard input, output, and error of the command are redirected to the NULL device, so you cannot tell directly whether the command runs correctly. The default null device on UNIX is `/dev/null`.
- The command is run as the user of the job.
- All environment variables set for the job are also set for the command action. The following additional environment variables are set:
  - `LSB_JOBPGIDS` — a list of current process group IDs of the job
  - `LSB_JOBPIIDS` — a list of current process IDs of the job

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

## Default

- On UNIX, by default, RESUME sends SIGCONT.
- On Windows, actions equivalent to the UNIX signals have been implemented to do the default job control actions. Job control messages replace the SIGINT and SIGTERM signals, but only customized applications are able to process them.

## RTASK\_GONE\_ACTION

### Syntax

```
RTASK_GONE_ACTION="[KILLJOB_TASKDONE | KILLJOB_TASKEXIT]
[IGNORE_TASKCRASH]"
```

### Description

Defines the actions LSF should take if it detects that a remote task of a parallel or distributed job is gone.

This parameter only applies to the `blaunch` distributed application framework.

#### IGNORE\_TASKCRASH

A remote task crashes. LSF does nothing. The job continues to launch the next task.

#### KILLJOB\_TASKDONE

A remote task exits with zero value. LSF terminates all tasks in the job.

**KILLJOB\_TASKEXIT**

A remote task exits with non-zero value. LSF terminates all tasks in the job.

**Environment variable**

When defined in an application profile, the `LSB_DJOB_RTASK_GONE_ACTION` variable is set when running `bsub - app` for the specified application.

You can also use the environment variable `LSB_DJOB_RTASK_GONE_ACTION` to override the value set in the application profile.

**Example**

```
RTASK_GONE_ACTION="IGNORE_TASKCRASH KILLJOB_TASKEXIT"
```

**Default**

Not defined. LSF does nothing.

**RUNLIMIT****Syntax**

```
RUNLIMIT=[hour:]minute[/host_name | host_model]
```

**Description**

The default run limit. The name of a host or host model specifies the runtime normalization host to use.

By default, jobs that are in the RUN state for longer than the specified run limit are killed by LSF. You can optionally provide your own termination job action to override this default.

Jobs submitted with a job-level run limit (`bsub - W`) that is less than the run limit are killed when their job-level run limit is reached. Jobs submitted with a run limit greater than the maximum run limit are rejected. Application-level limits override any default limit specified in the queue.

**Note:**

If you want to provide an estimated run time for scheduling purposes without killing jobs that exceed the estimate, define the `RUNTIME` parameter in the application profile, or submit the job with `-We` instead of a run limit.

The run limit is in the form of [*hour*:]*minute*. The minutes can be specified as a number greater than 59. For example, three and a half hours can either be specified as 3:30, or 210.

The run limit you specify is the normalized run time. This is done so that the job does approximately the same amount of processing, even if it is sent to host with a faster or slower CPU. Whenever a normalized run time is given, the actual time on the execution host is the specified time multiplied by the CPU factor of the normalization host then divided by the CPU factor of the execution host.

If `ABS_RUNLIMIT=Y` is defined in `lsb.params` or in the application profile, the runtime limit is not normalized by the host CPU factor. Absolute wall-clock run time is used for all jobs submitted to an application profile with a run limit configured.

Optionally, you can supply a host name or a host model name defined in LSF. You must insert '/' between the run limit and the host name or model name. (See `l s i n f o(1)` to get host model information.)

If no host or host model is given, LSF uses the default runtime normalization host defined at the queue level (`DEFAULT_HOST_SPEC` in `l sb. queues`) if it has been configured; otherwise, LSF uses the default CPU time normalization host defined at the cluster level (`DEFAULT_HOST_SPEC` in `l sb. par ams`) if it has been configured; otherwise, the host with the largest CPU factor (the fastest host in the cluster).

For MultiCluster jobs, if no other CPU time normalization host is defined and information about the submission host is not available, LSF uses the host with the largest CPU factor (the fastest host in the cluster).

Jobs submitted to a chunk job queue are not chunked if `RUNLIMIT` is greater than 30 minutes.

## Default

Unlimited

## RUNTIME

### Syntax

**RUNTIME**=[*hour*:]*minute*[/*host\_name* | *host\_model*]

### Description

The `RUNTIME` parameter specifies an estimated run time for jobs associated with an application. LSF uses the `RUNTIME` value for scheduling purposes only, and does not kill jobs that exceed this value unless the jobs also exceed a defined `RUNLIMIT`. The format of runtime estimate is same as the `RUNLIMIT` parameter.

The job-level runtime estimate specified by `bsub - We` overrides the `RUNTIME` setting in an application profile.

The following LSF features use the `RUNTIME` value to schedule jobs:

- Job chunking
- Advanced reservation
- SLA
- Slot reservation
- Backfill

## Default

Not defined

## STACKLIMIT

### Syntax

**STACKLIMIT**=*integer*

## Description

The per-process (soft) stack segment size limit for all of the processes belonging to a job from this queue (see `getrlimit(2)`). Application-level limits override any default limit specified in the queue, but must be less than the hard limit of the submission queue.

By default, the limit is specified in KB. Use `LSF_UNIT_FOR_LIMITS` in `lsf.conf` to specify a larger unit for the the limit (MB, GB, TB, PB, or EB).

## Default

Unlimited

## SUCCESS\_EXIT\_VALUES

### Syntax

**SUCCESS\_EXIT\_VALUES**=[*exit\_code* ...]

## Description

Specifies exit values used by LSF to determine if job was done successfully. Use spaces to separate multiple exit codes. Job-level success exit values specified with the `LSB_SUCCESS_EXIT_VALUES` environment variable override the configuration in application profile.

Use `SUCCESS_EXIT_VALUES` for applications that successfully exit with non-zero values so that LSF does not interpret non-zero exit codes as job failure.

*exit\_code* should be the value between 0 and 255. Use spaces to separate exit code values.

## Default

Not defined, Jobs do not specify a success exit value.

## SUSPEND\_CONTROL

### Syntax

**SUSPEND\_CONTROL**=*signal* | *command* | **CHKPNT**

---

#### Remember:

Unlike the `JOB_CONTROLS` parameter in `lsb.queues`, the `SUSPEND_CONTROL` parameter does not require square brackets (`[ ]`) around the action.

---

- *signal* is a UNIX signal name (for example, `SIGTSTP`). The specified signal is sent to the job. The same set of signals is not supported on all UNIX systems. To display a list of the symbolic names of the signals (without the `SIG` prefix) supported on your system, use the `kill -l` command.
- *command* specifies a `/bin/sh` command line to be invoked.
  - Do not quote the command line inside an action definition.
  - Do not specify a signal followed by an action that triggers the same signal. For example, do not specify `SUSPEND_CONTROL=bst op`. This causes a deadlock between the signal and the action.

- CHKPNT is a special action, which causes the system to checkpoint the job. The job is checkpointed and then stopped by sending the SIGSTOP signal to the job automatically.

## Description

Changes the behavior of the SUSPEND action in LSF.

- The contents of the configuration line for the action are run with `/bin/sh -c` so you can use shell features in the command.
- The standard input, output, and error of the command are redirected to the NULL device, so you cannot tell directly whether the command runs correctly. The default null device on UNIX is `/dev/null`.
- The command is run as the user of the job.
- All environment variables set for the job are also set for the command action. The following additional environment variables are set:
  - LSB\_JOBPGIDS — a list of current process group IDs of the job
  - LSB\_JOBPI DS — a list of current process IDs of the job
  - LSB\_SUSP\_REASONS — an integer representing a bitmap of suspending reasons as defined in `lsf.ch.h`. The suspending reason can allow the command to take different actions based on the reason for suspending the job.
  - LSB\_SUSP\_SUBREASONS — an integer representing the load index that caused the job to be suspended

When the suspending reason `SUSP_LOAD_REASON` (suspended by load) is set in `LSB_SUSP_REASONS`, `LSB_SUSP_SUBREASONS` is set to one of the load index values defined in `lsf.h`.

Use `LSB_SUSP_REASONS` and `LSB_SUSP_SUBREASONS` together in your custom job control to determine the exact load threshold that caused a job to be suspended.

- If an additional action is necessary for the SUSPEND command, that action should also send the appropriate signal to the application. Otherwise, a job can continue to run even after being suspended by LSF. For example, `SUSPEND_CONTROL=bkill`  
`LSB_JOBPI DS; command`

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

## Default

- On UNIX, by default, SUSPEND sends SIGTSTP for parallel or interactive jobs and SIGSTOP for other jobs.
- On Windows, actions equivalent to the UNIX signals have been implemented to do the default job control actions. Job control messages replace the SIGINT and SIGTERM signals, but only customized applications are able to process them.

## SWAPLIMIT

### Syntax

**SWAPLIMIT**=*integer*

## Description

Limits the amount of total virtual memory limit for the job.

This limit applies to the whole job, no matter how many processes the job may contain. Application-level limits override any default limit specified in the queue.

The action taken when a job exceeds its SWAPLIMIT or PROCESSLIMIT is to send SIGQUIT, SIGINT, SIGTERM, and SIGKILL in sequence. For CPULIMIT, SIGXCPU is sent before SIGINT, SIGTERM, and SIGKILL.

By default, the limit is specified in KB. Use LSF\_UNIT\_FOR\_LIMITS in `lsf.conf` to specify a larger unit for the the limit (MB, GB, TB, PB, or EB).

## Default

Unlimited

## TERMINATE\_CONTROL

## Syntax

**TERMINATE\_CONTROL=***signal* | *command* | **CHKPNT**

---

### Remember:

Unlike the JOB\_CONTROLS parameter in `lsb.queues`, the TERMINATE\_CONTROL parameter does not require square brackets ( [ ] ) around the action.

---

- *signal* is a UNIX signal name (for example, SIGTERM). The specified signal is sent to the job. The same set of signals is not supported on all UNIX systems. To display a list of the symbolic names of the signals (without the SIG prefix) supported on your system, use the `kill -l` command.
- *command* specifies a `/bin/sh` command line to be invoked.
  - Do not quote the command line inside an action definition.
  - Do not specify a signal followed by an action that triggers the same signal. For example, do not specify `TERMINATE_CONTROL=bkill`. This causes a deadlock between the signal and the action.
- CHKPNT is a special action, which causes the system to checkpoint the job. The job is checkpointed and killed automatically.

## Description

Changes the behavior of the TERMINATE action in LSF.

- The contents of the configuration line for the action are run with `/bin/sh -c` so you can use shell features in the command.
- The standard input, output, and error of the command are redirected to the NULL device, so you cannot tell directly whether the command runs correctly. The default null device on UNIX is `/dev/null`.
- The command is run as the user of the job.
- All environment variables set for the job are also set for the command action. The following additional environment variables are set:

- `LSB_JOBPGIDS` — a list of current process group IDs of the job
- `LSB_JOBPIIDS` — a list of current process IDs of the job

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

## Default

- On UNIX, by default, `TERMINATE` sends `SIGINT`, `SIGTERM` and `SIGKILL` in that order.
- On Windows, actions equivalent to the UNIX signals have been implemented to do the default job control actions. Job control messages replace the `SIGINT` and `SIGTERM` signals, but only customized applications are able to process them. Termination is implemented by the `TerminateProcess()` system call.

## THREADLIMIT

### Syntax

`THREADLIMIT=integer`

### Description

Limits the number of concurrent threads that can be part of a job. Exceeding the limit causes the job to terminate. The system sends the following signals in sequence to all processes belongs to the job: `SIGINT`, `SIGTERM`, and `SIGKILL`.

By default, jobs submitted to the queue without a job-level thread limit are killed when the thread limit is reached. Application-level limits override any default limit specified in the queue.

The limit must be a positive integer.

## Default

Unlimited

## USE\_PAM\_CREDS

### Syntax

`USE_PAM_CREDS=y | n`

### Description

If `USE_PAM_CREDS=y`, applies PAM limits to an application when its job is dispatched to a Linux host using PAM. PAM limits are system resource limits defined in `limits.conf`.

When `USE_PAM_CREDS` is enabled, PAM limits override others.

If the execution host does not have PAM configured and this parameter is enabled, the job fails.

For parallel jobs, only takes effect on the first execution host.

Overrides `MEMLIMIT_TYPE=Process`.

Overridden (for CPU limit only) by `LSB_JOB_CPULIMIT=y`.

lsb.applications

Overridden (for memory limits only) by LSB\_JOB\_MEMLIMIT=y.

**Default**

n

# lsb.events

The LSF batch event log file `lsb.events` is used to display LSF batch event history and for `mbatchd` failure recovery.

Whenever a host, job, or queue changes status, a record is appended to the event log file. The file is located in `LSB_SHAREDIR/cluster_name/logdir`, where `LSB_SHAREDIR` must be defined in `lsf.conf(5)` and `cluster_name` is the name of the LSF cluster, as returned by `lsid`. See `mbatchd(8)` for the description of `LSB_SHAREDIR`.

The `bhist` command searches the most current `lsb.events` file for its output.

## lsb.events structure

The event log file is an ASCII file with one record per line. For the `lsb.events` file, the first line has the format `# history_seek_position>`, which indicates the file position of the first history event after log switch. For the `lsb.events.#` file, the first line has the format `# timestamp_most_recent_event`, which gives the timestamp of the most recent event in the file.

## Limiting the size of lsb.events

Use `MAX_JOB_NUM` in `lsb.params` to set the maximum number of finished jobs whose events are to be stored in the `lsb.events` log file.

Once the limit is reached, `mbatchd` starts a new event log file. The old event log file is saved as `lsb.events.n`, with subsequent sequence number suffixes incremented by 1 each time a new log file is started. Event logging continues in the new `lsb.events` file.

## Records and fields

The fields of a record are separated by blanks. The first string of an event record indicates its type. The following types of events are recorded:

- JOB\_NEW
- JOB\_FORWARD
- JOB\_ACCEPT
- JOB\_START
- JOB\_START\_ACCEPT
- JOB\_STATUS
- JOB\_SWITCH
- JOB\_MOVE
- QUEUE\_CTRL
- HOST\_CTRL
- MBD\_START
- MBD\_DIE
- UNFULFILL
- LOAD\_INDEX
- JOB\_SIGACT
- MIG
- JOB\_MODIFY2
- JOB\_SIGNAL
- JOB\_EXECUTE

- JOB\_REQUEUE
- JOB\_CLEAN
- JOB\_EXCEPTION
- JOB\_EXT\_MSG
- JOB\_ATTA\_DATA
- JOB\_CHUNK
- SBD\_UNREPORTED\_STATUS
- PRE\_EXEC\_START
- JOB\_FORCE
- GRP\_ADD
- GRP\_MOD
- LOG\_SWITCH
- JOB\_RESIZE\_NOTIFY\_START
- JOB\_RESIZE\_NOTIFY\_ACCEPT
- JOB\_RESIZE\_NOTIFY\_DONE
- JOB\_RESIZE\_RELEASE
- JOB\_RESIZE\_CANCEL

## JOB\_NEW

A new job has been submitted. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**userId (%d)**

UNIX user ID of the submitter

**options (%d)**

Bit flags for job processing

**numProcessors (%d)**

Number of processors requested for execution

**submitTime (%d)**

Job submission time

**beginTime (%d)**

Start time – the job should be started on or after this time

**termTime (%d)**

Termination deadline – the job should be terminated by this time (%d)

**sigValue (%d)**

Signal value

**chkpntPeriod (%d)**

Checkpointing period

**restartPid (%d)**

Restart process ID

**userName (%s)**

User name

**rLimits**

Soft CPU time limit (%d), see `getrlimit(2)`

**rLimits**

Soft file size limit (%d), see `getrlimit(2)`

**rLimits**

Soft data segment size limit (%d), see `getrlimit(2)`

**rLimits**

Soft stack segment size limit (%d), see `getrlimit(2)`

**rLimits**

Soft core file size limit (%d), see `getrlimit(2)`

**rLimits**

Soft memory size limit (%d), see `getrlimit(2)`

**rLimits**

Reserved (%d)

**rLimits**

Reserved (%d)

**rLimits**

Reserved (%d)

**rLimits**

Soft run time limit (%d), see `getrlimit(2)`

**rLimits**

Reserved (%d)

**hostSpec (%s)**

Model or host name for normalizing CPU time and run time

**hostFactor (%f)**

CPU factor of the above host

lsb.events

**umask (%d)**

File creation mask for this job

**queue (%s)**

Name of job queue to which the job was submitted

**resReq (%s)**

Resource requirements

**fromHost (%s)**

Submission host name

**cwd (%s)**

Current working directory (up to 4094 characters for UNIX or 255 characters for Windows)

**chkpntDir (%s)**

Checkpoint directory

**inFile (%s)**

Input file name (up to 4094 characters for UNIX or 255 characters for Windows)

**outFile (%s)**

Output file name (up to 4094 characters for UNIX or 255 characters for Windows)

**errFile (%s)**

Error output file name (up to 4094 characters for UNIX or 255 characters for Windows)

**subHomeDir (%s)**

Submitter's home directory

**jobFile (%s)**

Job file name

**numAskedHosts (%d)**

Number of candidate host names

**askedHosts (%s)**

List of names of candidate hosts for job dispatching

**dependCond (%s)**

Job dependency condition

**preExecCmd (%s)**

Job pre-execution command

**timeEvent (%d)**

Time Event, for job dependency condition; specifies when time event ended

**jobName (%s)**  
Job name (up to 4094 characters for UNIX or 255 characters for Windows)

**command (%s)**  
Job command (up to 4094 characters for UNIX or 255 characters for Windows)

**nxf (%d)**  
Number of files to transfer (%d)

**xf (%s)**  
List of file transfer specifications

**mailUser (%s)**  
Mail user name

**projectName (%s)**  
Project name

**niosPort (%d)**  
Callback port if batch interactive job

**maxNumProcessors (%d)**  
Maximum number of processors

**schedHostType (%s)**  
Execution host type

**loginShell (%s)**  
Login shell

**userGroup (%s)**  
User group

**exceptList (%s)**  
Exception handlers for the job

**options2 (%d)**  
Bit flags for job processing

**idx (%d)**  
Job array index

**inFileSpool (%s)**  
Spool input file (up to 4094 characters for UNIX or 255 characters for Windows)

**commandSpool (%s)**  
Spool command file (up to 4094 characters for UNIX or 255 characters for Windows)

**jobSpoolDir (%s)**

Job spool directory (up to 4094 characters for UNIX or 255 characters for Windows)

**userPriority (%d)**

User priority

**rsvld %s**

Advance reservation ID; for example, "user2#0"

**jobGroup (%s)**

The job group under which the job runs

**extsched (%s)**

External scheduling options

**warningAction (%s)**

Job warning action

**warningTimePeriod (%d)**

Job warning time period in seconds

**sla (%s)**

SLA service class name under which the job runs

**SLArunLimit (%d)**

Absolute run time limit of the job for SLA service classes

**licenseProject (%s)**

LSF License Scheduler project name

**options3 (%d)**

Bit flags for job processing

**app (%s)**

Application profile name

**postExecCmd (%s)**

Post-execution command to run on the execution host after the job finishes

**runtimeEstimation (%d)**

Estimated run time for the job

**requeueEValues (%s)**

Job exit values for automatic job requeue

**resizeNotifyCmd (%s)**

Resize notification command to run on the first execution host to inform job of a resize event.

## JOB\_FORWARD

A job has been forwarded to a remote cluster (Platform MultiCluster only).

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, older daemons and commands (pre-LSF Version 6.0) cannot recognize the `lsb.events` file format.

The fields in order of occurrence are:

### Version number (%s)

The version number

### Event time (%d)

The time of the event

### jobId (%d)

Job ID

### numReserHosts (%d)

Number of reserved hosts in the remote cluster

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, the value of this field is the number of `.hosts` listed in the `reserHosts` field.

### cluster (%s)

Remote cluster name

### reserHosts (%s)

List of names of the reserved hosts in the remote cluster

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, the value of this field is logged in a shortened format.

### idx (%d)

Job array index

## JOB\_ACCEPT

A job from a remote cluster has been accepted by this cluster. The fields in order of occurrence are:

### Version number (%s)

The version number

### Event time (%d)

The time of the event

### jobId (%d)

Job ID at the accepting cluster

### remoteJid (%d)

Job ID at the submission cluster

lsb.events

**cluster (%s)**

Job submission cluster name

**idx (%d)**

Job array index

## JOB\_START

A job has been dispatched.

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, older daemons and commands (pre-LSF Version 6.0) cannot recognize the lsb.events file format.

The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**jStatus (%d)**

Job status, (4, indicating the RUN status of the job)

**jobPid (%d)**

Job process ID

**jobPGid (%d)**

Job process group ID

**hostFactor (%f)**

CPU factor of the first execution host

**numExHosts (%d)**

Number of processors used for execution

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is the number of .hosts listed in the execHosts field.

**execHosts (%s)**

List of execution host names

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is logged in a shortened format.

**queuePreCmd (%s)**

Pre-execution command

**queuePostCmd (%s)**

Post-execution command

**jFlags (%d)**

Job processing flags

**userGroup (%s)**

User group name

**idx (%d)**

Job array index

**additionalInfo (%s)**

Placement information of HPC jobs

**jFlags2 (%d)**

## JOB\_START\_ACCEPT

A job has started on the execution host(s). The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**jobPid (%d)**

Job process ID

**jobPGid (%d)**

Job process group ID

**idx (%d)**

Job array index

## JOB\_STATUS

The status of a job changed after dispatch. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

lsb.events

**jStatus (%d)**

New status, see <lsf/l sbatch.h>

**reason (%d)**

Pending or suspended reason code, see <lsf/l sbatch.h>

**subreasons (%d)**

Pending or suspended subreason code, see <lsf/l sbatch.h>

**cpuTime (%f)**

CPU time consumed so far

**endTime (%d)**

Job completion time

**ru (%d)**

Resource usage flag

**lsfRusage (%s)**

Resource usage statistics, see <lsf/l sf.h>

**exitStatus (%d)**

Exit status of the job, see <lsf/l sbatch.h>

**idx (%d)**

Job array index

**exitInfo (%d)**

Job termination reason, see <lsf/l sbatch.h>

**duration4PreemptBackfill**

How long a backfilled job can run; used for preemption backfill jobs

## JOB\_SWITCH

A job switched from one queue to another (bswitch). The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**userId (%d)**

UNIX user ID of the user invoking the command

**jobId (%d)**

Job ID

**queue (%s)**

**idx (%d)** Target queue name

Job array index

**userName (%s)** Name of the job submitter

## JOB\_MOVE

A job moved toward the top or bottom of its queue (bbot or bt op). The fields in order of occurrence are:

**Version number (%s)** The version number

**Event time (%d)** The time of the event

**userId (%d)** UNIX user ID of the user invoking the command

**jobId (%d)** Job ID

**position (%d)** Position number

**base (%d)** Operation code, (TO\_TOP or TO\_BOTTOM), see <1 sf /1 sbat ch. h>

**idx (%d)** Job array index

**userName (%s)** Name of the job submitter

## QUEUE\_CTRL

A job queue has been altered. The fields in order of occurrence are:

**Version number (%s)** The version number

**Event time (%d)** The time of the event

**opCode (%d)** Operation code), see <1 sf /1 sbat ch. h>

**queue (%s)**

lsb.events

Queue name

**userId (%d)**

UNIX user ID of the user invoking the command

**userName (%s)**

Name of the user

**ctrlComments (%s)**

Administrator comment text from the -C option of `badmi n` queue control commands `qclose`, `qopen`, `qact`, and `qi nact`

## HOST\_CTRL

A batch server host changed status. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**opCode (%d)**

Operation code, see `<lsf/l sbatch. h>`

**host (%s)**

Host name

**userId (%d)**

UNIX user ID of the user invoking the command

**userName (%s)**

Name of the user

**ctrlComments (%s)**

Administrator comment text from the -C option of `badmi n` host control commands `hclose` and `hopen`

## MBD\_START

The `mbatchd` has started. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**master (%s)**

Master host name

**cluster (%s)**

cluster name

**numHosts (%d)**

Number of hosts in the cluster

**numQueues (%d)**

Number of queues in the cluster

**MBD\_DIE**

The mbatchd died. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**master (%s)**

Master host name

**numRemoveJobs (%d)**

Number of finished jobs that have been removed from the system and logged in the current event file

**exitCode (%d)**

Exit code from mbatchd

**ctrlComments (%s)**Administrator comment text from the -C option of `badmi n mbdrestart`**UNFULFILL**

Actions that were not taken because the mbatchd was unable to contact the sbatchd on the job execution host. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**notSwitched (%d)**

Not switched: the mbatchd has switched the job to a new queue, but the sbatchd has not been informed of the switch

**sig (%d)**

lsb.events

Signal: this signal has not been sent to the job

**sig1 (%d)**

Checkpoint signal: the job has not been sent this signal to checkpoint itself

**sig1Flags (%d)**

Checkpoint flags, see <lsf/l\_sbat ch. h>

**chkPeriod (%d)**

New checkpoint period for job

**notModified (%s)**

If set to true, then parameters for the job cannot be modified.

**idx (%d)**

Job array index

## LOAD\_INDEX

mbatchd restarted with these load index names (see lsf.cluster(5)). The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**nidx (%d)**

Number of index names

**name (%s)**

List of index names

## JOB\_SIGACT

An action on a job has been taken. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**period (%d)**

Action period

**pid (%d)**

Process ID of the child sbatchd that initiated the action

**jstatus (%d)**

Job status

**reasons (%d)**

Job pending reasons

**flags (%d)**

Action flags, see <1 sf/1 sbatch. h>

**actStatus (%d)**

Action status:

- 1: Action started
- 2: One action preempted other actions
- 3: Action succeeded
- 4: Action Failed

**signalSymbol (%s)**

Action name, accompanied by actFlags

**idx (%d)**

Job array index

## MIG

A job has been migrated (bmi g). The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**numAskedHosts (%d)**

Number of candidate hosts for migration

**askedHosts (%s)**

List of names of candidate hosts

**userId (%d)**

UNIX user ID of the user invoking the command

**idx (%d)**

Job array index

**userName (%s)**

Name of the job submitter

## JOB\_MODIFY2

This is created when the mbatchd modifies a previously submitted job with bmod.

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobIdStr (%s)**

Job ID

**options (%d)**

Bit flags for job modification options processing

**options2 (%d)**

Bit flags for job modification options processing

**delOptions (%d)**

Delete options for the options field

**delOptions2 (%d)**

Delete options for the options2 field

**userId (%d)**

UNIX user ID of the submitter

**userName (%s)**

User name

**submitTime (%d)**

Job submission time

**umask (%d)**

File creation mask for this job

**numProcessors (%d)**

Number of processors requested for execution. The value 2147483646 means the number of processors is undefined.

**beginTime (%d)**

Start time – the job should be started on or after this time

**termTime (%d)**

Termination deadline – the job should be terminated by this time

**sigValue (%d)**

Signal value

**restartPid (%d)**

Restart process ID for the original job

**jobName (%s)**

Job name (up to 4094 characters for UNIX or 255 characters for Windows)

**queue (%s)**

Name of job queue to which the job was submitted

**numAskedHosts (%d)**

Number of candidate host names

**askedHosts (%s)**

List of names of candidate hosts for job dispatching; blank if the last field value is 0. If there is more than one host name, then each additional host name will be returned in its own field

**resReq (%s)**

Resource requirements

**rLimits**Soft CPU time limit (%d), see `getrlimit(2)`**rLimits**Soft file size limit (%d), see `getrlimit(2)`**rLimits**Soft data segment size limit (%d), see `getrlimit(2)`**rLimits**Soft stack segment size limit (%d), see `getrlimit(2)`**rLimits**Soft core file size limit (%d), see `getrlimit(2)`**rLimits**Soft memory size limit (%d), see `getrlimit(2)`**rLimits**

Reserved (%d)

**rLimits**

Reserved (%d)

**rLimits**

Reserved (%d)

lsb.events

**rLimits**

Soft run time limit (%d), see `getrlimit(2)`

**rLimits**

Reserved (%d)

**hostSpec (%s)**

Model or host name for normalizing CPU time and run time

**dependCond (%s)**

Job dependency condition

**timeEvent (%d)**

Time Event, for job dependency condition; specifies when time event ended

**subHomeDir (%s)**

Submitter's home directory

**inFile (%s)**

Input file name (up to 4094 characters for UNIX or 255 characters for Windows)

**outFile (%s)**

Output file name (up to 4094 characters for UNIX or 255 characters for Windows)

**errFile (%s)**

Error output file name (up to 4094 characters for UNIX or 255 characters for Windows)

**command (%s)**

Job command (up to 4094 characters for UNIX or 255 characters for Windows)

**inFileSpool (%s)**

Spool input file (up to 4094 characters for UNIX or 255 characters for Windows)

**commandSpool (%s)**

Spool command file (up to 4094 characters for UNIX or 255 characters for Windows)

**chkpntPeriod (%d)**

Checkpointing period

**chkpntDir (%s)**

Checkpoint directory

**nxf (%d)**

Number of files to transfer

**xf (%s)**

List of file transfer specifications

**jobFile (%s)**

Job file name

**fromHost (%s)**

Submission host name

**cwd (%s)**

Current working directory (up to 4094 characters for UNIX or 255 characters for Windows)

**preExecCmd (%s)**

Job pre-execution command

**mailUser (%s)**

Mail user name

**projectName (%s)**

Project name

**niosPort (%d)**

Callback port if batch interactive job

**maxNumProcessors (%d)**

Maximum number of processors. The value 2147483646 means the maximum number of processors is undefined.

**loginShell (%s)**

Login shell

**schedHostType (%s)**

Execution host type

**userGroup (%s)**

User group

**exceptList (%s)**

Exception handlers for the job

**userPriority (%d)**

User priority

**rsvld %s**

Advance reservation ID; for example, "user2#0"

**extsched (%s)**

External scheduling options

**warningTimePeriod (%d)**

Job warning time period in seconds

**warningAction (%s)**

Job warning action

**jobGroup (%s)**

The job group to which the job is attached

**sla (%s)**

SLA service class name that the job is to be attached to

**licenseProject (%s)**

LSF License Scheduler project name

**options3 (%d)**

Bit flags for job processing

**delOption3 (%d)**

Delete options for the options3 field

**app (%s)**

Application profile name

**apsString (%s)**

Absolute priority scheduling (APS) value set by administrator

**postExecCmd (%s)**

Post-execution command to run on the execution host after the job finishes

**runtimeEstimation (%d)**

Estimated run time for the job

**requeueEValues (%s)**

Job exit values for automatic job requeue

**resizeNotifyCmd (%s)**

Resize notification command to run on the first execution host to inform job of a resize event.

## JOB\_SIGNAL

This is created when a job is signaled with bki 11 or deleted with bdel . The fields are in the order they appended:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

|                          |                                               |
|--------------------------|-----------------------------------------------|
|                          | Job ID                                        |
| <b>userId (%d)</b>       |                                               |
|                          | UNIX user ID of the user invoking the command |
| <b>runCount (%d)</b>     |                                               |
|                          | Number of runs                                |
| <b>signalSymbol (%s)</b> |                                               |
|                          | Signal name                                   |
| <b>idx (%d)</b>          |                                               |
|                          | Job array index                               |
| <b>userName (%s)</b>     |                                               |
|                          | Name of the job submitter                     |

## JOB\_EXECUTE

This is created when a job is actually running on an execution host. The fields in order of occurrence are:

|                            |                                                                                                                     |
|----------------------------|---------------------------------------------------------------------------------------------------------------------|
| <b>Version number (%s)</b> |                                                                                                                     |
|                            | The version number                                                                                                  |
| <b>Event time (%d)</b>     |                                                                                                                     |
|                            | The time of the event                                                                                               |
| <b>jobId (%d)</b>          |                                                                                                                     |
|                            | Job ID                                                                                                              |
| <b>execUid (%d)</b>        |                                                                                                                     |
|                            | Mapped UNIX user ID on execution host                                                                               |
| <b>jobPGid (%d)</b>        |                                                                                                                     |
|                            | Job process group ID                                                                                                |
| <b>execCwd (%s)</b>        |                                                                                                                     |
|                            | Current working directory job used on execution host (up to 4094 characters for UNIX or 255 characters for Windows) |
| <b>execHome (%s)</b>       |                                                                                                                     |
|                            | Home directory job used on execution host                                                                           |
| <b>execUsername (%s)</b>   |                                                                                                                     |
|                            | Mapped user name on execution host                                                                                  |
| <b>jobPid (%d)</b>         |                                                                                                                     |
|                            | Job process ID                                                                                                      |

lsb.events

**idx (%d)**

Job array index

**additionalInfo (%s)**

Placement information of HPC jobs

**SLAscaledRunLimit (%d)**

Run time limit for the job scaled by the execution host

**execRusage**

An internal field used by LSF.

**Position**

An internal field used by LSF.

**duration4PreemptBackfill**

How long a backfilled job can run; used for preemption backfill jobs

## JOB\_QUEUE

This is created when a job ended and requeued by mbatchd. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**idx (%d)**

Job array index

## JOB\_CLEAN

This is created when a job is removed from the mbatchd memory. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**idx (%d)**

Job array index

## JOB\_EXCEPTION

This is created when an exception condition is detected for a job. The fields in order of occurrence are:

### Version number (%s)

The version number

### Event time (%d)

The time of the event

### jobId (%d)

Job ID

### exceptMask (%d)

Exception Id

0x01: missed

0x02: overrun

0x04: underrun

0x08: abend

0x10: cantrun

0x20: hostfail

0x40: startfail

0x100:runtime\_est\_exceeded

### actMask (%d)

Action Id

0x01: kill

0x02: alarm

0x04: rerun

0x08: setexcept

### timeEvent (%d)

Time Event, for missed exception specifies when time event ended.

### exceptInfo (%d)

Except Info, pending reason for missed or can't run exception, the exit code of the job for the abend exception, otherwise 0.

### idx (%d)

Job array index

## JOB\_EXT\_MSG

An external message has been sent to a job. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**idx (%d)**

Job array index

**msgIdx (%d)**

Index in the list

**userId (%d)**

Unique user ID of the user invoking the command

**dataSize (%ld)**

Size of the data if it has any, otherwise 0

**postTime (%ld)**

Message sending time

**dataStatus (%d)**

Status of the attached data

**desc (%s)**

Text description of the message

**userName (%s)**

Name of the author of the message

## JOB\_ATTA\_DATA

An update on the data status of a message for a job has been sent. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**idx (%d)**

Job array index

**msgIdx (%d)**

Index in the list

**dataSize (%ld)**

Size of the data if it has any, otherwise 0

**dataStatus (%d)**

Status of the attached data

**fileName (%s)**

File name of the attached data

## JOB\_CHUNK

This is created when a job is inserted into a chunk.

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, older daemons and commands (pre-LSF Version 6.0) cannot recognize the `lsb.event.s` file format.

The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**membSize (%ld)**Size of array `membJobId`**membJobId (%ld)**

Job IDs of jobs in the chunk

**numExHosts (%ld)**

Number of execution hosts

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, the value of this field is the number of `.hosts` listed in the `execHosts` field.

**execHosts (%s)**

Execution host name array

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, the value of this field is logged in a shortened format.

## SBD\_UNREPORTED\_STATUS

This is created when an unreported status change occurs. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**actPid (%d)**

Acting processing ID

**jobPid (%d)**

Job process ID

**jobPGid (%d)**

Job process group ID

**newStatus (%d)**

New status of the job

**reason (%d)**

Pending or suspending reason code, see <lsf/lsbatch.h>

**suspreason (%d)**

Pending or suspending subreason code, see <lsf/lsbatch.h>

**lsfRusage**

The following fields contain resource usage information for the job (see `getrusage(2)`). If the value of some field is unavailable (due to job exit or the difference among the operating systems), -1 will be logged. Times are measured in seconds, and sizes are measured in KB.

**ru\_utime (%f)**

User time used

**ru\_stime (%f)**

System time used

**ru\_maxrss (%f)**

Maximum shared text size

**ru\_ixrss (%f)**

Integral of the shared text size over time (in KB seconds)

**ru\_ismrss (%f)**

Integral of the shared memory size over time (valid only on Ultrix)

**ru\_idrss (%f)**

|                         |                                                                                                                     |
|-------------------------|---------------------------------------------------------------------------------------------------------------------|
| <b>ru_isrss (%f)</b>    | Integral of the unshared data size over time                                                                        |
| <b>ru_minflt (%f)</b>   | Integral of the unshared stack size over time                                                                       |
| <b>ru_majflt (%f)</b>   | Number of page reclaims                                                                                             |
| <b>ru_nswap (%f)</b>    | Number of page faults                                                                                               |
| <b>ru_inblock (%f)</b>  | Number of times the process was swapped out                                                                         |
| <b>ru_oublock (%f)</b>  | Number of block input operations                                                                                    |
| <b>ru_ioch (%f)</b>     | Number of block output operations                                                                                   |
| <b>ru_msgsnd (%f)</b>   | Number of characters read and written (valid only on HP-UX)                                                         |
| <b>ru_msgrcv (%f)</b>   | Number of System V IPC messages sent                                                                                |
| <b>ru_nsignals (%f)</b> | Number of messages received                                                                                         |
| <b>ru_nvcsw (%f)</b>    | Number of signals received                                                                                          |
| <b>ru_nivcsw (%f)</b>   | Number of voluntary context switches                                                                                |
| <b>ru_exutime (%f)</b>  | Number of involuntary context switches                                                                              |
| <b>exitStatus (%d)</b>  | Exact user time used (valid only on ConvexOS)                                                                       |
| <b>execCwd (%s)</b>     | Exit status of the job, see <l sf/l sbat ch. h>                                                                     |
| <b>execHome (%s)</b>    | Current working directory job used on execution host (up to 4094 characters for UNIX or 255 characters for Windows) |

Home directory job used on execution host

**execUsername (%s)**

Mapped user name on execution host

**msgId (%d)**

ID of the message

**actStatus (%d)**

Action status

1: Action started

2: One action preempted other actions

3: Action succeeded

4: Action Failed

**sigValue (%d)**

Signal value

**seq (%d)**

Sequence status of the job

**idx (%d)**

Job array index

**jRusage**

The following fields contain resource usage information for the job. If the value of some field is unavailable (due to job exit or the difference among the operating systems), -1 will be logged. Times are measured in seconds, and sizes are measured in KB.

**mem (%d)**

Total resident memory usage in KB of all currently running processes in a given process group

**swap (%d)**

Totally virtual memory usage in KB of all currently running processes in given process groups

**utime (%d)**

Cumulative total user time in seconds

**stime (%d)**

Cumulative total system time in seconds

**npids (%d)**

Number of currently active process in given process groups. This entry has four sub-fields:

|                      |                                                           |
|----------------------|-----------------------------------------------------------|
| <b>pid (%d)</b>      | Process ID of the child sbatchd that initiated the action |
| <b>ppid (%d)</b>     | Parent process ID                                         |
| <b>pgid (%d)</b>     | Process group ID                                          |
| <b>jobId (%d)</b>    | Process Job ID                                            |
| <b>npgids (%d)</b>   | Number of currently active process groups                 |
| <b>exitInfo (%d)</b> | Job termination reason, see <lsf/l sbatch.h>              |

## PRE\_EXEC\_START

A pre-execution command has been started.

The fields in order of occurrence are:

|                            |                                                       |
|----------------------------|-------------------------------------------------------|
| <b>Version number (%s)</b> | The version number                                    |
| <b>Event time (%d)</b>     | The time of the event                                 |
| <b>jobId (%d)</b>          | Job ID                                                |
| <b>jStatus (%d)</b>        | Job status, (4, indicating the RUN status of the job) |
| <b>jobPid (%d)</b>         | Job process ID                                        |
| <b>jobPGid (%d)</b>        | Job process group ID                                  |
| <b>hostFactor (%f)</b>     | CPU factor of the first execution host                |
| <b>numExHosts (%d)</b>     | Number of processors used for execution               |
| <b>execHosts (%s)</b>      | List of execution host names                          |

lsb.events

**queuePreCmd (%s)**

Pre-execution command

**queuePostCmd (%s)**

Post-execution command

**jFlags (%d)**

Job processing flags

**userGroup (%s)**

User group name

**idx (%d)**

Job array index

**additionalInfo (%s)**

Placement information of HPC jobs

## JOB\_FORCE

A job has been forced to run with brun.

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

**userId (%d)**

UNIX user ID of the user invoking the command

**idx (%d)**

Job array index

**options (%d)**

Bit flags for job processing

**numExecHosts (%ld)**

Number of execution hosts

If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in `lsf.conf`, the value of this field is the number of `.hosts` listed in the `execHosts` field.

**execHosts (%s)**

Execution host name array

If `LSF_HPC_EXTENSIONS="SHORT_EVENTFILE"` is specified in `lsf.conf`, the value of this field is logged in a shortened format.

**userName (%s)**

Name of the user

**queue (%s)**

Name of queue if a remote brun job ran; otherwise, this field is empty

**GRP\_ADD**

This is created when a job group is added. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**userId (%d)**

UNIX user ID of the job group owner

**submitTime (%d)**

Job submission time

**userName (%s)**

User name of the job group owner

**depCond (%s)**

Job dependency condition

**timeEvent (%d)**

Time Event, for job dependency condition; specifies when time event ended

**groupSpec (%s)**

Job group name

**delOptions (%d)**

Delete options for the options field

**delOptions2 (%d)**

Delete options for the options2 field

**sla (%s)**

SLA service class name that the job group is to be attached to

**maxJLimit (%d)**

Job group limit set by `bgadd -L`

**groupType (%d)**

Job group creation method:

- 0x01 - job group was created explicitly
- 0x02 - job group was created implicitly

## GRP\_MOD

This is created when a job group is modified. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**userId (%d)**

UNIX user ID of the job group owner

**submitTime (%d)**

Job submission time

**userName (%s)**

User name of the job group owner

**depCond (%s)**

Job dependency condition

**timeEvent (%d)**

Time Event, for job dependency condition; specifies when time event ended

**groupSpec (%s)**

Job group name

**delOptions (%d)**

Delete options for the options field

**delOptions2 (%d)**

Delete options for the options2 field

**sla (%s)**

SLA service class name that the job group is to be attached to

**maxJLimit (%d)**

Job group limit set by `bgmod -L`

## LOG\_SWITCH

This is created when switching the event file `lsb.events`. The fields in order of occurrence are:

**Version number (%s)**

The version number

**Event time (%d)**

The time of the event

**jobId (%d)**

Job ID

## JOB\_RESIZE\_NOTIFY\_START

LSF logs this event when a resize (shrink or grow) request has been sent to the first execution host. The fields in order of occurrence are:

**Version number (%s)**

The version number.

**Event time (%d)**

The time of the event.

**jobId (%d)**

The job ID.

**idx (%d)**

Job array index.

**notifyId (%d)**

Identifier or handle for notification.

**numResizeHosts (%d)**

Number of processors used for execution. If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is the number of hosts listed in short format.

**resizeHosts (%s)**

List of execution host names. If LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is specified in lsf.conf, the value of this field is logged in a shortened format.

## JOB\_RESIZE\_NOTIFY\_ACCEPT

LSF logs this event when a resize request has been accepted from the first execution host of a job. The fields in order of occurrence are:

**Version number (%s)**

The version number.

**Event time (%d)**

The time of the event.

**jobId (%d)**

The job ID.

lsb.events

**idx (%d)**

Job array index.

**notifyId (%d)**

Identifier or handle for notification.

**resizeNotifyCmdPid (%d)**

Resize notification executable process ID. If no resize notification executable is defined, this field will be set to 0.

**resizeNotifyCmdPGid (%d)**

Resize notification executable process group ID. If no resize notification executable is defined, this field will be set to 0.

**status (%d)**

Status field used to indicate possible errors. 0 Success, 1 failure.

## JOB\_RESIZE\_NOTIFY\_DONE

LSF logs this event when the resize notification command completes. The fields in order of occurrence are:

**Version number (%s)**

The version number.

**Event time (%d)**

The time of the event.

**jobId (%d)**

The job ID.

**idx (%d)**

Job array index.

**notifyId (%d)**

Identifier or handle for notification.

**status (%d)**

Resize notification exit value. (0, success, 1, failure, 2 failure but cancel request.)

## JOB\_RESIZE\_RELEASE

LSF logs this event when receiving resource release request from client. The fields in order of occurrence are:

**Version number (%s)**

The version number.

**Event time (%d)**

The time of the event.

|                             |                                                                                                                                                                                                 |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>jobId (%d)</b>           | The job ID.                                                                                                                                                                                     |
| <b>idx (%d)</b>             | Job array index.                                                                                                                                                                                |
| <b>reqid (%d)</b>           | Request Identifier or handle.                                                                                                                                                                   |
| <b>options (%d)</b>         | Release options.                                                                                                                                                                                |
| <b>userId (%d)</b>          | UNIX user ID of the user invoking the command.                                                                                                                                                  |
| <b>userName (%s)</b>        | User name of the submitter.                                                                                                                                                                     |
| <b>resizeNotifyCmd (%s)</b> | Resize notification command to run on the first execution host to inform job of a resize event.                                                                                                 |
| <b>numResizeHosts (%d)</b>  | Number of processors used for execution during resize. If LSF_HPC_EXTENSIONS="SHORT_EVENTFILE" is specified in lsf.conf, the value of this field is the number of hosts listed in short format. |
| <b>resizeHosts (%s)</b>     | List of execution host names during resize. If LSF_HPC_EXTENSIONS="SHORT_EVENTFILE" is specified in lsf.conf, the value of this field is logged in a shortened format.                          |

## JOB\_RESIZE\_CANCEL

LSF logs this event when receiving cancel request from client. The fields in order of occurrence are:

|                            |                        |
|----------------------------|------------------------|
| <b>Version number (%s)</b> | The version number.    |
| <b>Event time (%d)</b>     | The time of the event. |
| <b>jobId (%d)</b>          | The job ID.            |
| <b>idx (%d)</b>            | Job array index.       |
| <b>userId (%d)</b>         |                        |

lsb.events

UNIX user ID of the user invoking the command.

**userName (%s)**

User name of the submitter.

# lsb.hosts

The `lsb.hosts` file contains host-related configuration information for the server hosts in the cluster. It is also used to define host groups, host partitions, and compute units.

This file is optional. All sections are optional.

By default, this file is installed in `LSB_CONFDIR/cluster_name/configdir`.

## Changing lsb.hosts configuration

After making any changes to `lsb.hosts`, run `badminton reconfig` to reconfigure `mbatchd`.

## Host section

### Description

Optional. Defines the hosts, host types, and host models used as server hosts, and contains per-host configuration information. If this section is not configured, LSF uses all hosts in the cluster (the hosts listed in `lsf.cluster.cluster_name`) as server hosts.

Each host, host model or host type can be configured to:

- Limit the maximum number of jobs run in total
- Limit the maximum number of jobs run by each user
- Run jobs only under specific load conditions
- Run jobs only under specific time windows

The entries in a line for a host override the entries in a line for its model or type.

When you modify the cluster by adding or removing hosts, no changes are made to `lsb.hosts`. This does not affect the default configuration, but if hosts, host models, or host types are specified in this file, you should check this file whenever you make changes to the cluster and update it manually if necessary.

## Host section structure

The first line consists of keywords identifying the load indices that you wish to configure on a per-host basis. The keyword `HOST_NAME` must be used; the others are optional. Load indices not listed on the keyword line do not affect scheduling decisions.

Each subsequent line describes the configuration information for one host, host model or host type. Each line must contain one entry for each keyword. Use empty parentheses `()` or a dash `(-)` to specify the default value for an entry.

### HOST\_NAME

*Required.* Specify the name, model, or type of a host, or the keyword default.

### host name

The name of a host defined in `lsf.cluster.cluster_name`.

### host model

A host model defined in `lsf.shared`.

lsb.hosts

## host type

A host type defined in `lsf.shared`.

## default

The reserved host name default indicates all hosts in the cluster not otherwise referenced in the section (by name or by listing its model or type).

## CHKPNT

### Description

If C, checkpoint copy is enabled. With checkpoint copy, all opened files are automatically copied to the checkpoint directory by the operating system when a process is checkpointed.

### Example

```
HOST_NAME  CHKPNT hostA          C
```

### Compatibility

Checkpoint copy is only supported on Cray systems.

### Default

No checkpoint copy

## DISPATCH\_WINDOW

### Description

The time windows in which jobs from this host, host model, or host type are dispatched. Once dispatched, jobs are no longer affected by the dispatch window.

### Default

Not defined (always open)

## EXIT\_RATE

### Description

Specifies a threshold for exited jobs. If the job exit rate is exceeded for 5 minutes or the period specified by `JOB_EXIT_RATE_DURATION` in `lsf.params`, LSF invokes `LSF_SERVERDIR/eadmin` to trigger a host exception.

`EXIT_RATE` for a specific host overrides a default `GLOBAL_EXIT_RATE` specified in `lsf.params`.

## Example

The following Host section defines a job exit rate of 20 jobs for all hosts, and an exit rate of 10 jobs on hostA.

```
Begin Host
HOST_NAME      MXJ      EXIT_RATE  # Keywords
Default        !          20
hostA          !          10
End Host
```

## Default

Not defined

## JL/U

## Description

Per-user job slot limit for the host. Maximum number of job slots that each user can use on this host.

## Example

```
HOST_NAME  JL/U hostA      2
```

## Default

Unlimited

## MIG

## Syntax

**MIG**=*minutes*

## Description

Enables automatic job migration and specifies the migration threshold for checkpointable or rerunnable jobs, in minutes.

LSF automatically migrates jobs that have been in the SSUSP state for more than the specified number of minutes. Specify a value of 0 to migrate jobs immediately upon suspension. The migration threshold applies to all jobs running on the host.

Job-level command line migration threshold overrides threshold configuration in application profile and queue. Application profile configuration overrides queue level configuration. When a host migration threshold is specified, and is lower than the value for the job, the queue, or the application, the host value is used.

Does not affect MultiCluster jobs that are forwarded to a remote cluster.

## Default

Not defined. LSF does not migrate checkpointable or rerunnable jobs automatically.

## MXJ

### Description

The number of job slots on the host.

With MultiCluster resource leasing model, this is the number of job slots on the host that are available to the local cluster.

Use “!” to make the number of job slots equal to the number of CPUs on a host.

For the reserved host name default, “!” makes the number of job slots equal to the number of CPUs on all hosts in the cluster not otherwise referenced in the section.

By default, the number of running and suspended jobs on a host cannot exceed the number of job slots. If preemptive scheduling is used, the suspended jobs are not counted as using a job slot.

On multiprocessor hosts, to fully use the CPU resource, make the number of job slots equal to or greater than the number of processors.

### Default

Unlimited

### *load\_index*

### Syntax

```
load_index loadSched[/loadStop]
```

Specify *i o, i t, l s, mem, pg, r 15s, r 1m, r 15m, swp, tmp, ut*, or a non-shared custom external load index as a column. Specify multiple columns to configure thresholds for multiple load indices.

### Description

Scheduling and suspending thresholds for dynamic load indices supported by LIM, including external load indices.

Each load index column must contain either the default entry or two numbers separated by a slash ‘/’, with no white space. The first number is the scheduling threshold for the load index; the second number is the suspending threshold.

Queue-level scheduling and suspending thresholds are defined in *lsb. queues*. If both files specify thresholds for an index, those that apply are the most restrictive ones.

### Example

```
HOST_NAME    mem    swp hostA    100/10    200/30
```

This example translates into a *loadSched* condition of

```
mem>=100 && swp>=200
```

and a *loadStop* condition of

```
mem < 10 || swp < 30
```

## Default

Not defined

## Example of a Host section

```

Begin Host
HOST_NAME  MXJ  JL/U  r1m      pg      DISPATCH_WINDOW
hostA      1    -    0.6/1.6  10/20   (5:19:00-1:8:30 20:00-8:30)
SUNSOL    1    -    0.5/2.5  -      23:00-8:00
default   2    1    0.6/1.6  20/40   ()
End Host

```

SUNSOL is a host type defined in `lsf.shared`. This example Host section configures one host and one host type explicitly and configures default values for all other load-sharing hosts.

HostA runs one batch job at a time. A job will only be started on hostA if the `r1m` index is below 0.6 and the `pg` index is below 10; the running job is stopped if the `r1m` index goes above 1.6 or the `pg` index goes above 20. HostA only accepts batch jobs from 19:00 on Friday evening until 8:30 Monday morning and overnight from 20:00 to 8:30 on all other days.

For hosts of type SUNSOL, the `pg` index does not have host-specific thresholds and such hosts are only available overnight from 23:00 to 8:00.

The entry with host name default applies to each of the other hosts in the cluster. Each host can run up to two jobs at the same time, with at most one job from each user. These hosts are available to run jobs at all times. Jobs may be started if the `r1m` index is below 0.6 and the `pg` index is below 20, and a job from the lowest priority queue is suspended if `r1m` goes above 1.6 or `pg` goes above 40.

## HostGroup section

### Description

Optional. Defines host groups.

The name of the host group can then be used in other host group, host partition, and queue definitions, as well as on the command line. Specifying the name of a host group has exactly the same effect as listing the names of all the hosts in the group.

### Structure

Host groups are specified in the same format as user groups in `lsb.users`.

The first line consists of two mandatory keywords, `GROUP_NAME` and `GROUP_MEMBER`, as well as an optional keywords, `CONDENSE` and `GROUP_ADMIN`. Subsequent lines name a group and list its membership.

The sum of all host groups, compute groups, and host partitions cannot be more than 1024.

## GROUP\_NAME

### Description

An alphanumeric string representing the name of the host group.

You cannot use the reserved name `all`, and group names must not conflict with host names.

## CONDENSE

### Description

Optional. Defines condensed host groups.

Condensed host groups are displayed in a condensed output format for the `bhosts` and `bjobs` commands.

If you configure a host to belong to more than one condensed host group, `bjobs` can display any of the host groups as execution host name.

### Valid Values

Y or N.

### Default

N (the specified host group is not condensed)

## GROUP\_MEMBER

### Description

A space-delimited list of host names or previously defined host group names, enclosed in one pair of parentheses.

You cannot use more than one pair of parentheses to define the list.

The names of hosts and host groups can appear on multiple lines because hosts can belong to multiple groups. The reserved name `all` specifies all hosts in the cluster. An exclamation mark (!) indicates an externally-defined host group, which the `egroup` executable retrieves.

### Pattern definition

You can use string literals and special characters when defining host group members. Each entry cannot contain any spaces, as the list itself is space delimited.

When a leased-in host joins the cluster, the host name is in the form of `host@cluster`. For these hosts, only the host part of the host name is subject to pattern definitions.

You can use the following special characters to specify host group members:

- Use a tilde (~) to exclude specified hosts or host groups from the list.
- Use an asterisk (\*) as a wildcard character to represent any number of characters.
- Use square brackets with a hyphen (`[integer1 - integer2]`) to define a range of non-negative integers at the end of a host name. The first integer must be less than the second integer.
- Use square brackets with commas (`[integer1, integer2...]`) to define individual non-negative integers at the end of a host name.
- Use square brackets with commas and hyphens (for example, `[integer1 - integer2, integer3, integer4 - integer5]`) to define different ranges of non-negative integers at the end of a host name.

### Restrictions

- You cannot use more than one set of square brackets in a single host group definition.

- The following example is *not* correct:  

```
... (hostA[1-10]B[1-20] hostC[101-120])
```
- The following example is correct:  

```
... (hostA[1-20] hostC[101-120])
```
- You cannot define subgroups that contain wildcards and special characters.

## GROUP\_ADMIN

### Description

Host group administrators have the ability to open or close the member hosts for the group they are administering.

the `GROUP_ADMIN` field is a space-delimited list of user names or previously defined user group names, enclosed in one pair of parentheses.

You cannot use more than one pair of parentheses to define the list.

The names of users and user groups can appear on multiple lines because users can belong to and administer multiple groups.

When host group administrators (who are not also cluster administrators) open or close a host, they must specify a comment with the `-C` option.

### Valid values

Any existing user or user group can be specified. A user group that specifies an external list is also allowed; however, in this location, you use the user group name that has been defined with `(!)` rather than `(!)` itself.

### Restrictions

- You cannot specify any wildcards or special characters (for example: \*, !, \$, #, &, ~).
- You cannot specify an external group (egroup).
- You cannot use the keyword `ALL` and you cannot administer any group that has `ALL` as its members.
- User names and user group names cannot have spaces.

## Example HostGroup sections

### Example 1

```
Begin HostGroup
GROUP_NAME  GROUP_MEMBER  GROUP_ADMIN
groupA      (hostA hostD) (user1 user10)
groupB      (hostF groupA hostK) ()
groupC      (!) ()
End HostGroup
```

This example defines three host groups:

- `groupA` includes `hostA` and `hostD` and can be administered by `user1` and `user10`.
- `groupB` includes `hostF` and `hostK`, along with all hosts in `groupA`. It has no administrators (only the cluster administrator can control the member hosts).

- The group membership of groupC is defined externally and retrieved by the egroup executable.

## Example 2

```

Begin HostGroup
GROUP_NAME  GROUP_MEMBER  GROUP_ADMIN
groupA      (all) ()
groupB      (groupA ~hostA ~hostB) (user11 user14)
groupC      (hostX hostY hostZ) ()
groupD      (groupC ~hostX) usergroupB
groupE      (all ~groupC ~hostB) ()
groupF      (hostF groupC hostK) ()
End HostGroup

```

This example defines the following host groups:

- groupA contains all hosts in the cluster and is administered by the cluster administrator.
- groupB contains all the hosts in the cluster except for hostA and hostB and is administered by user11 and user14.
- groupC contains only hostX, hostY, and hostZ and is administered by the cluster administrator.
- groupD contains the hosts in groupC except for hostX. Note that hostX must be a member of host group groupC to be excluded from groupD. usergroupB is the administrator for groupD.
- groupE contains all hosts in the cluster excluding the hosts in groupC and hostB and is administered by the cluster administrator.
- groupF contains hostF, hostK, and the 3 hosts in groupC and is administered by the cluster administrator.

## Example 3

```

Begin HostGroup
GROUP_NAME  CONDENSE  GROUP_MEMBER  GROUP_ADMIN
groupA      N          (all) ()
groupB      N          (hostA, hostB) (usergroupC user1)
groupC      Y          (all) ()
End HostGroup

```

This example defines the following host groups:

- groupA shows uncondensed output and contains all hosts in the cluster and is administered by the cluster administrator.
- groupB shows uncondensed output, and contains hostA and hostB. It is administered by all members of usergroupC and user1.
- groupC shows condensed output and contains all hosts in the cluster and is administered by the cluster administrator.

## Example 4

```

Begin HostGroup
GROUP_NAME CONDENSE GROUP_MEMBER GROUP_ADMIN
groupA      Y (host*) (user7)
groupB      N (*A) ()
groupC      N (hostB* ~hostB[1-50]) ()
groupD      Y (hostC[1-50] hostC[101-150]) (usergroupJ)
groupE      N (hostC[51-100] hostC[151-200]) ()
groupF      Y (hostD[1,3] hostD[5-10]) ()
groupG      N (hostD[11-50] ~hostD[15,20,25] hostD2) ()
End HostGroup

```

This example defines the following host groups:

- groupA shows condensed output, and contains all hosts starting with the string host. It is administered by user7.
- groupB shows uncondensed output, and contains all hosts ending with the string A, such as hostA and is administered by the cluster administrator.
- groupC shows uncondensed output, and contains all hosts starting with the string hostB except for the hosts from hostB1 to hostB50 and is administered by the cluster administrator.
- groupD shows condensed output, and contains all hosts from hostC1 to hostC50 and all hosts from hostC101 to hostC150 and is administered by the the members of usergroupJ.
- groupE shows uncondensed output, and contains all hosts from hostC51 to hostC100 and all hosts from hostC151 to hostC200 and is administered by the cluster administrator.
- groupF shows condensed output, and contains hostD1, hostD3, and all hosts from hostD5 to hostD10 and is administered by the cluster administrator.
- groupG shows uncondensed output, and contains all hosts from hostD11 to hostD50 except for hostD15, hostD20, and hostD25. groupG also includes hostD2. It is administered by the cluster administrator.

## HostPartition section

### Description

Optional. Used with host partition user-based fairshare scheduling. Defines a host partition, which defines a user-based fairshare policy at the host level.

Configure multiple sections to define multiple partitions.

The members of a host partition form a host group with the same name as the host partition.

---

#### Restriction:

You cannot use host partitions and host preference simultaneously.

---

## Limitations on queue configuration

- If you configure a host partition, you cannot configure fairshare at the queue level.
- If a queue uses a host that belongs to a host partition, it should not use any hosts that don't belong to that partition. All the hosts in the queue should belong to the same partition. Otherwise, you might notice unpredictable scheduling behavior:
  - Jobs in the queue sometimes may be dispatched to the host partition even though hosts not belonging to any host partition have a lighter load.
  - If some hosts belong to one host partition and some hosts belong to another, only the priorities of one host partition are used when dispatching a parallel job to hosts from more than one host partition.

## Shared resources and host partitions

- If a resource is shared among hosts included in host partitions and hosts that are not included in any host partition, jobs in queues that use the host partitions will always get the shared resource first, regardless of queue priority.
- If a resource is shared among host partitions, jobs in queues that use the host partitions listed first in the `HostPartiti on` section of `lsb. hosts` will always have priority to get the shared resource first. To allocate shared resources among host partitions, LSF considers host partitions in the order they are listed in `lsb. hosts`.

## Structure

Each host partition always consists of 3 lines, defining the name of the partition, the hosts included in the partition, and the user share assignments.

### HPART\_NAME

#### Syntax

**HPART\_NAME**=*partition\_name*

#### Description

Specifies the name of the partition. The name must be 59 characters or less.

### HOSTS

#### Syntax

**HOSTS**=[[~]*host\_name* / [[~]*host\_group* / all]...

#### Description

Specifies the hosts in the partition, in a space-separated list.

A host cannot belong to multiple partitions.

A host group cannot be empty.

Hosts that are not included in any host partition are controlled by the FCFS scheduling policy instead of the fairshare scheduling policy.

Optionally, use the reserved host name `all` to configure a single partition that applies to all hosts in a cluster.

Optionally, use the not operator (~) to exclude hosts or host groups from the list of hosts in the host partition.

## Examples

```
HOSTS=all ~hostK ~hostM
```

The partition includes all the hosts in the cluster, except for host K and host M.

```
HOSTS=groupA ~hostL
```

The partition includes all the hosts in host group groupA except for host L.

## USER\_SHARES

### Syntax

```
USER_SHARES=[user, number_shares]...
```

### Description

Specifies user share assignments

- Specify at least one user share assignment.
- Enclose each user share assignment in square brackets, as shown.
- Separate a list of multiple share assignments with a space between the square brackets.
- *user*—Specify users who are also configured to use the host partition. You can assign the shares:
  - To a single user (specify *user\_name*). To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name*).
  - To users in a group, individually (specify *group\_name@*) or collectively (specify *group\_name*). To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAME\group\_name*).
  - To users not included in any other share assignment, individually (specify the keyword *default*) or collectively (specify the keyword *others*).

By default, when resources are assigned collectively to a group, the group members compete for the resources according to FCFS scheduling. You can use hierarchical fairshare to further divide the shares among the group members.

When resources are assigned to members of a group individually, the share assignment is recursive. Members of the group and of all subgroups always compete for the resources according to FCFS scheduling, regardless of hierarchical fairshare policies.

- *number\_shares*
  - Specify a positive integer representing the number of shares of the cluster resources assigned to the user.
  - The number of shares assigned to each user is only meaningful when you compare it to the shares assigned to other users or to the total number of shares. The total number of shares is just the sum of all the shares assigned in each share assignment.

## Example of a HostPartition section

```
Begin HostPartition
HPART_NAME = Partition1 HOSTS = hostA hostB USER_SHARES = [groupA@, 3]
[groupB, 7] [default, 1]
End HostPartition
```

## ComputeUnit section

### Description

Optional. Defines compute units.

Once defined, the compute unit can be used in other compute unit and queue definitions, as well as in the command line. Specifying the name of a compute unit has the same effect as listing the names of all the hosts in the compute unit.

Compute units are similar to host groups, with the added feature of granularity allowing the construction of structures that mimic the network architecture. Job scheduling using compute unit resource requirements effectively spreads jobs over the cluster based on the configured compute units.

To enforce consistency, compute unit configuration has the following requirements:

- Hosts and host groups appear in the finest granularity compute unit type, and nowhere else.
- Hosts appear in only one compute unit of the finest granularity.
- All compute units of the same type have the same type of compute units (or hosts) as members.

### Structure

Compute units are specified in the same format as host groups in `lsb.hosts`.

The first line consists of three mandatory keywords, NAME, MEMBER, and TYPE, as well as an optional keywords CONDENSE and ADMIN. Subsequent lines name a compute unit and list its membership.

The sum of all host groups, compute groups, and host partitions cannot be more than 1024.

### NAME

#### Description

An alphanumeric string representing the name of the compute unit.

You cannot use the reserved names `all`, `allremote`, `others`, and `default`. Compute unit names must not conflict with host names, host partitions, or host group names.

### CONDENSE

#### Description

Optional. Defines condensed compute units.

Condensed compute units are displayed in a condensed output format for the `bhosts` and `bjobs` commands. The condensed compute unit format includes the slot usage for each compute unit.

## Valid Values

Y or N.

## Default

N (the specified host group is not condensed)

## MEMBER

### Description

A space-delimited list of host names or previously defined compute unit names, enclosed in one pair of parentheses.

You cannot use more than one pair of parentheses to define the list.

The names of hosts and host groups can appear only once, and only in a compute unit type of the finest granularity.

An exclamation mark (!) indicates an externally-defined host group, which the `egroup` executable retrieves.

### Pattern definition

You can use string literals and special characters when defining compute unit members. Each entry cannot contain any spaces, as the list itself is space delimited.

You can use the following special characters to specify host and host group compute unit members:

- Use a tilde (~) to exclude specified hosts or host groups from the list.
- Use an asterisk (\*) as a wildcard character to represent any number of characters.
- Use square brackets with a hyphen (`[integer1 - integer2]`) to define a range of non-negative integers at the end of a host name. The first integer must be less than the second integer.
- Use square brackets with commas (`[integer1, integer2...]`) to define individual non-negative integers at the end of a host name.
- Use square brackets with commas and hyphens (for example, `[integer1 - integer2, integer3, integer4 - integer5]`) to define different ranges of non-negative integers at the end of a host name.

### Restrictions

- You cannot use more than one set of square brackets in a single compute unit definition.
  - The following example is *not* correct:
 

```
... (encl A[ 1- 10]B[ 1- 20] encl C[ 101- 120])
```
  - The following example is correct:
 

```
... (encl A[ 1- 20] encl C[ 101- 120])
```
- Compute unit names cannot be used in compute units of the finest granularity.
- You cannot include host or host group names except in compute units of the finest granularity.
- You must not skip levels of granularity. For example:

If `lsb.params` contains `COMPUTE_UNIT_TYPES=enclosure rack cabinet` then a compute unit of type `cabinet` can contain compute units of type `rack`, but not of type `enclosure`.

- The keywords `all`, `allremote`, `all@cluster`, `other` and `default` cannot be used when defining compute units.

## TYPE

### Description

The type of the compute unit, as defined in the `COMPUTE_UNIT_TYPES` parameter of `lsb.params`.

## ADMIN

### Description

Host group administrators have the ability to open or close the member hosts for the compute unit they are administering.

the `ADMIN` field is a space-delimited list of user names or previously defined user group names, enclosed in one pair of parentheses.

You cannot use more than one pair of parentheses to define the list.

The names of users and user groups can appear on multiple lines because users can belong to and administer multiple compute units.

When host group administrators (who are not also cluster administrators) open or close a host, they must specify a comment with the `-C` option.

## Valid values

Any existing user or user group can be specified. A user group that specifies an external list is also allowed; however, in this location, you use the user group name that has been defined with `(!)` rather than `(!)` itself.

## Restrictions

- You cannot specify any wildcards or special characters (for example: `*`, `!`, `$`, `#`, `&`, `~`).
- You cannot specify an external group (egroup).
- You cannot use the keyword `ALL` and you cannot administer any group that has `ALL` as its members.
- User names and user group names cannot have spaces.

## Example ComputeUnit sections

### Example 1

(For the `lsb.params` entry  
`COMPUTE_UNIT_TYPES=enclosure rack cabinet`

```

)
Begin ComputeUnit
NAME    MEMBER          TYPE
encl 1  (host 1 host 2)  encl osure
encl 2  (host 3 host 4)  encl osure
encl 3  (host 5 host 6)  encl osure
encl 4  (host 7 host 8)  encl osure
rack1   (encl 1 encl 2)  rack
rack2   (encl 3 encl 4)  rack
cbnt 1  (rack1 rack2)   cabi net
End ComputeUnit

```

This example defines seven compute units:

- encl 1, encl 2, encl 3 and encl 4 are the finest granularity, and each contain two hosts.
- rack1 is of coarser granularity and contains two levels. At the enclosure level rack1 contains encl 1 and encl 2. At the lowest level rack1 contains host 1, host 2, host 3, and host 4.
- rack2 has the same structure as rack1, and contains encl 3 and encl 4.
- cbnt 1 contains two racks (rack1 and rack2), four enclosures (encl 1, encl 2, encl 3, and encl 4) and all eight hosts. Compute unit cbnt 1 is the coarsest granularity in this example.

## Example 2

(For the lsb.params entry COMPUTE\_UNIT\_TYPES=encl osure rack cabi net)

```

Begin ComputeUnit
NAME  CONDENSE  MEMBER                                TYPE      ADMIN
encl 1  Y        (hg123 ~hostA ~hostB)                enclosure (user11 user14)
encl 2  Y        (hg456)                                enclosure ()
encl 3  N        (hostA hostB)                          enclosure usergroupB
encl 4  N        (hgroupX ~hostB)                       enclosure ()
encl 5  Y        (hostC* ~hostC[ 101- 150])             enclosure usergroupJ
encl 6  N        (hostC[ 101- 150])                     enclosure ()
rack1   Y        (encl 1 encl 2 encl 3)                 rack      ()
rack2   N        (encl 4 encl 5)                         rack      usergroupJ
rack3   N        (encl 6)                               rack      ()
cbnt 1  Y        (rack1 rack2)                          cabi net  ()
cbnt 2  N        (rack3)                                cabi net  user14
End ComputeUnit

```

This example defines 11 compute units:

- All six enclosures (finest granularity) contain only hosts and host groups. All three racks contain only enclosures. Both cabinets (coarsest granularity) contain only racks.
- encl 1 contains all the hosts in host group hg123 except for host A and host B and is administered by user11 and user14. Note that host A and host B must be members of host group hg123 to be excluded from encl 1. encl 1 shows condensed output.

- encl 2 contains host group hg456 and is administered by the cluster administrator. encl 2 shows condensed output.
- encl 3 contains host A and host B. usergroupB is the administrator for encl 3. encl 3 shows uncondensed output.
- encl 4 contains host group hgroupX except for host B. Since each host can appear in only one enclosure and host B is already in encl 3, it cannot be in encl 4. encl 4 is administered by the cluster administrator. encl 4 shows uncondensed output.
- encl 5 contains all hosts starting with the string host C except for hosts host C101 to host C150, and is administered by usergroupJ. encl 5 shows condensed output.
- rack1 contains encl 1, encl 2, and encl 3. rack1 shows condensed output.
- rack2 contains encl 4, and encl 5. rack2 shows uncondensed output.
- rack3 contains encl 6. rack3 shows uncondensed output.
- cbnt1 contains rack1 and rack2. cbnt 1 shows condensed output.
- cbnt 2 contains rack3. Even though rack3 only contains encl6, cbnt 3 cannot contain encl 6 directly because that would mean skipping the level associated with compute unit type rack. cbnt 2 shows uncondensed output.

## Automatic time-based configuration

Variable configuration is used to automatically change LSF configuration based on time windows. You define automatic configuration changes in `lsb.hosts` by using if-else constructs and time expressions. After you change the files, reconfigure the cluster with the `admin reconfig` command.

The expressions are evaluated by LSF every 10 minutes based on `mbatchd` start time. When an expression evaluates true, LSF dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting `mbatchd`, providing continuous system availability.

## Example

In the following example, the `#if`, `#else`, `#endif` are not interpreted as comments by LSF but as if-else constructs.

```

Begin Host
HOST_NAME   r15s   r1m   pg
host1       3/5    3/5   12/20
#if time(5:16:30-1:8:30 20:00-8:30)
host2       3/5    3/5   12/20
#else
Ohost2      2/3    2/3   10/12
#endif
host3       3/5    3/5   12/20
End Host

```

# lsb.modules

The `lsb.modules` file contains configuration information for LSF scheduler and resource broker modules. The file contains only one section, named `PluginModule`.

This file is optional. If no scheduler or resource broker modules are configured, LSF uses the default scheduler plugin modules named `schmod_default` and `schmod_fcfs`.

The `lsb.modules` file is stored in the directory `LSB_CONFDIR/cluster_name/confdir`, where `LSB_CONFDIR` is defined in `lsf.conf`.

## Changing lsb.modules configuration

After making any changes to `lsb.modules`, run `badminton reconfig` to reconfigure `mbatchd`.

## PluginModule section

### Description

Defines the plugin modules for the LSF scheduler and LSF resource broker. If this section is not configured, LSF uses the default scheduler plugin modules named `schmod_default` and `schmod_fcfs`, which enable the LSF default scheduling features.

## Example PluginModule section

The following `PluginModule` section enables all scheduling policies provided by LSF:

```
Begin PluginModule
```

| SCH_PLUGIN                     | RB_PLUGIN       | SCH_DISABLE_PHASES |
|--------------------------------|-----------------|--------------------|
| <code>schmod_default</code>    | <code>()</code> | <code>()</code>    |
| <code>schmod_fairshare</code>  | <code>()</code> | <code>()</code>    |
| <code>schmod_fcfs</code>       | <code>()</code> | <code>()</code>    |
| <code>schmod_limit</code>      | <code>()</code> | <code>()</code>    |
| <code>schmod_parallel</code>   | <code>()</code> | <code>()</code>    |
| <code>schmod_reserve</code>    | <code>()</code> | <code>()</code>    |
| <code>schmod_preemption</code> | <code>()</code> | <code>()</code>    |
| <code>schmod_advrsv</code>     | <code>()</code> | <code>()</code>    |
| <code>schmod_mc</code>         | <code>()</code> | <code>()</code>    |
| <code>schmod_jobweight</code>  | <code>()</code> | <code>()</code>    |
| <code>schmod_cpuset</code>     | <code>()</code> | <code>()</code>    |
| <code>schmod_pset</code>       | <code>()</code> | <code>()</code>    |
| <code>schmod_ps</code>         | <code>()</code> | <code>()</code>    |
| <code>schmod_aps</code>        | <code>()</code> | <code>()</code>    |

```
End PluginModule
```

## PluginModule section structure

The first line consists of the following keywords:

- `SCH_PLUGIN`

- RB\_PLUGIN
- SCH\_DISABLE\_PHASES

They identify the scheduler plugins, resource broker plugins, and the scheduler phase to be disabled for the plugins that you wish to configure.

Each subsequent line describes the configuration information for one scheduler plugin module, resource broker plugin module, and scheduler phase, if any, to be disabled for the plugin. Each line must contain one entry for each keyword. Use empty parentheses ( ) or a dash (-) to specify the default value for an entry.

## SCH\_PLUGIN

### Description

Required. The SCH\_PLUGIN column specifies the shared module name for the LSF scheduler plugin. Each plugin requires a corresponding license. Scheduler plugins are called in the order they are listed in the PluginModule section.

By default, all shared modules for scheduler plugins are located in LSF\_LIBDIR. On UNIX, you can also specify a full path to the name of the scheduler plugin.

The following modules are supplied with LSF:

### schmod\_default

Enables the default LSF scheduler features.

Licensed by: LSF\_Manager

### schmod\_fcfs

Enables the first-come, first-served (FCFS) scheduler features. schmod\_fcfs can appear anywhere in the SCH\_PLUGIN list. By default, if schmod\_fcfs is not configured in lsb.modules, it is loaded automatically along with schmod\_default.

Source code (sch.mod.fcfs.c) for the schmod\_fcfs scheduler plugin module is installed in the directory

`LSF_TOP/7.0/misc/examples/external_plugin/`

Use the LSF scheduler plugin SDK to modify the FCFS scheduler module code to suit the job scheduling requirements of your site.

See *Platform LSF Programmer's Guide* for more detailed information about writing, building, and configuring your own custom scheduler plugins.

### schmod\_fairshare

Enables the LSF fairshare scheduling features.

### schmod\_limit

Enables the LSF resource allocation limit features.

Licensed by: LSF\_Manager

### schmod\_parallel

Enables scheduling of parallel jobs submitted with `bsub -n`.

## schmod\_reserve

Enables the LSF resource reservation features.

To enable processor reservation, backfill, and memory reservation for parallel jobs, you must configure both `schmod_parallel` and `schmod_reserve` in `lsb.modules`. If only `schmod_reserve` is configured, backfill and memory reservation are enabled only for sequential jobs, and processor reservation is not enabled.

## schmod\_preemption

Enables the LSF preemption scheduler features.

## schmod\_advrsv

Handles jobs that use advance reservations (`brsvadd`, `brsvs`, `brsvdel`, `bsub -U`)

## schmod\_cpuset

Handles jobs that use IRIX cpusets (`bsub -ext [sched] "CPuset[cpuset_options]"`)

The `schmod_cpuset` plugin name must be configured after the standard LSF plugin names in the `PluginModule` list.

## schmod\_mc

Enables MultiCluster job forwarding

Licensed by: LSF\_MultiCluster

## schmod\_ps

Enables resource ownership functionality of EGO-enabled SLA scheduling policies

## schmod\_pset

Enables scheduling policies required for jobs that use HP-UX processor sets (pset) allocations (`bsub -ext [sched] "PSET[topology]"`)

The `schmod_pset` plugin name must be configured after the standard LSF plugin names in the `PluginModule` list.

## schmod\_aps

Enables absolute priority scheduling (APS) policies configured by `APS_PRIORITY` in `lsb.queues`.

The `schmod_aps` plugin name must be configured after the `schmod_fairshare` plugin name in the `PluginModule` list, so that the APS value can override the fairshare job ordering decision.

Licensed by: LSF\_HPC

## schmod\_jobweight

An optional scheduler plugin module to enable Cross-Queue Job Weight scheduling policies. The `schmod_jobweight` plugin must be listed before `schmod_cpuset` and `schmod_rms`, and after all other scheduler plugin modules.

You should not use job weight scheduling together with fairshare scheduling or job preemption. To avoid scheduling conflicts, you should comment out `schmod_fairshare` and `schmod_preemption` in `lsb.modules`.

## Scheduler plugin SDK

Use the LSF scheduler plugin SDK to write customized scheduler modules that give you more flexibility and control over job scheduling. Enable your custom scheduling policies by configuring your modules under `SCH_PLUGIN` in the `PluginModules` section of `lsb.modules`.

The directory

```
LSF_TOP/7.0/misc/examples/external_plugin/
```

contains sample plugin code. See *Platform LSF Programmer's Guide* for more detailed information about writing, building, and configuring your own custom scheduler plugins.

## RB\_PLUGIN

### Description

`RB_PLUGIN` specifies the shared module name for resource broker plugins. Resource broker plugins collect and update job resource accounting information, and provide it to the scheduler.

Normally, for each scheduler plugin module, there is a corresponding resource broker plugin module to support it. However, the resource broker also supports multiple plugin modules for one scheduler plugin module.

For example, a fairshare policy may need more than one resource broker plugin module to support it if the policy has multiple configurations.

A scheduler plugin can have one, multiple, or none RB plugins corresponding to it.

### Example

| NAME                          | RB_PLUGIN                   |
|-------------------------------|-----------------------------|
| <code>schmod_default</code>   | <code>()</code>             |
| <code>schmod_fairshare</code> | <code>(rb_fairshare)</code> |

### Default

Undefined

## SCH\_DISABLE\_PHASES

### Description

`SCH_DISABLE_PHASES` specifies which scheduler phases, if any, to be disabled for the plugin. LSF scheduling has four phases:

1. **Preprocessing** — the scheduler checks the readiness of the job for scheduling and prepares a list of ready resource seekers. It also checks the start time of a job, and evaluates any job dependencies.
2. **Match/limit** — the scheduler evaluates the job resource requirements and prepares candidate hosts for jobs by matching jobs with resources. It also applies resource allocation limits. Jobs with all required resources matched go on to order/allocation phase. Not all

jobs are mapped to all potential available resources. Jobs without any matching resources will not go through the Order/Allocation Phase but can go through the Post-processing phase, where preemption may be applied to get resources the job needs to run.

3. Order/allocation — the scheduler sorts jobs with matched resources and allocates resources for each job, assigning job slot, memory, and other resources to the job. It also checks if the allocation satisfies all constraints defined in configuration, such as queue slot limit, deadline for the job, etc.
  1. In the order phase, the scheduler applies policies such as FCFS, Fairshare and Host-partition and consider job priorities within user groups and share groups. By default, job priority within a pool of jobs from the same user is based on how long the job has been pending.
  2. For resource intensive jobs (jobs requiring a lot of CPUs or a large amount of memory), resource reservation is performed so that these jobs are not starved.
  3. When all the currently available resources are allocated, jobs go on to post-processing.
4. Post-processing — the scheduler prepares jobs from the order/allocation phase for dispatch and applies preemption or backfill policies to obtain resources for the jobs that have completed pre-processing or match/limit phases, but did not have resources available to enter the next scheduling phase.

Each scheduler plugin module invokes one or more scheduler phase. The processing for a give phase can be disabled or skipped if:

The plugin module does not need to do any processing for that phase or the processing has already been done by a previous plugin module in the list.

The scheduler will not invoke phases marked by SCH\_DISABLE\_PHASES when scheduling jobs.

None of the plugins provided by LSF should require phases to be disabled, but your own custom plugin modules using the scheduler SDK may need to disable one or more scheduler phases.

## Example

In the following configuration, the `schmod_custom` plugin module disables the order allocation (3) and post-processing (4) phases:

| NAME                        | SCH_DISABLE_PHASES |
|-----------------------------|--------------------|
| <code>schmod_default</code> | ( )                |
| <code>schmod_custom</code>  | (3, 4)             |

## Default

Undefined

# lsb.params

The `lsb.params` file defines general parameters used by the LSF system. This file contains only one section, named Parameters. `mbatchd` uses `lsb.params` for initialization. The file is optional. If not present, the LSF-defined defaults are assumed.

Some of the parameters that can be defined in `lsb.params` control timing within the system. The default settings provide good throughput for long-running batch jobs while adding a minimum of processing overhead in the batch daemons.

This file is installed by default in `LSB_CONFDIR/cluster_name/configdir`.

## Changing lsb.params configuration

After making any changes to `lsb.params`, run `badm in reconfi g` to reconfigure `mbatchd`.

## Parameters section

This section and all the keywords in this section are optional. If keywords are not present, the default values are assumed.

## Parameters set at installation

The following parameter values are set at installation for the purpose of testing a new cluster:

```
Begin Parameters
DEFAULT_QUEUE = normal      #default job queue name
MBD_SLEEP_TIME = 20         #mbatchd scheduling interval (60 secs is default)
SBD_SLEEP_TIME = 15         #sbatchd scheduling interval (30 secs is default)
JOB_ACCEPT_INTERVAL = 1     #interval for any host to accept a job
                             #(default is 1 (one-fold of MBD_SLEEP_TIME))
End Parameters
```

With this configuration, jobs submitted to the LSF system will be started on server hosts quickly. If this configuration is not suitable for your production use, you should either remove the parameters to take the default values, or adjust them as needed.

For example, to avoid having jobs start when host load is high, increase `JOB_ACCEPT_INTERVAL` so that the job scheduling interval is longer to give hosts more time to adjust load indices after accepting jobs.

In production use, you should define `DEFAULT_QUEUE` to the normal queue, `MBD_SLEEP_TIME` to 60 seconds (the default), and `SBD_SLEEP_TIME` to 30 seconds (the default).

## ABS\_RUNLIMIT

### Syntax

```
ABS_RUNLIMIT=y | Y
```

## Description

If set, absolute (wall-clock) run time is used instead of normalized run time for all jobs submitted with the following values:

- Run time limit specified by the `-W` option of `bsub`
- `RUNLIMIT` queue-level parameter in `lsb.queues`
- `RUNLIMIT` application-level parameter in `lsb.applications`
- `RUNTIME` parameter in `lsb.applications`

The run time estimates and limits are not normalized by the host CPU factor.

## Default

N (run limit and run time estimate are normalized)

## ACCT\_ARCHIVE\_AGE

### Syntax

`ACCT_ARCHIVE_AGE=days`

## Description

Enables automatic archiving of LSF accounting log files, and specifies the archive interval. LSF archives the current log file if the length of time from its creation date exceeds the specified number of days.

## See also

- `ACCT_ARCHIVE_SIZE` also enables automatic archiving
- `ACCT_ARCHIVE_TIME` also enables automatic archiving
- `MAX_ACCT_ARCHIVE_FILE` enables automatic deletion of the archives

## Default

-1 (Not defined; no limit to the age of `lsb.acct`)

## ACCT\_ARCHIVE\_SIZE

### Syntax

`ACCT_ARCHIVE_SIZE=kilobytes`

## Description

Enables automatic archiving of LSF accounting log files, and specifies the archive threshold. LSF archives the current log file if its size exceeds the specified number of kilobytes.

## See also

- `ACCT_ARCHIVE_SIZE` also enables automatic archiving
- `ACCT_ARCHIVE_TIME` also enables automatic archiving
- `MAX_ACCT_ARCHIVE_FILE` enables automatic deletion of the archives

## Default

-1 (Not defined; no limit to the size of `lsb.acct`)

## ACCT\_ARCHIVE\_TIME

### Syntax

**ACCT\_ARCHIVE\_TIME**=*hh:mm*

### Description

Enables automatic archiving of LSF accounting log file `lsb.acct`, and specifies the time of day to archive the current log file.

### See also

- `ACCT_ARCHIVE_SIZE` also enables automatic archiving
- `ACCT_ARCHIVE_TIME` also enables automatic archiving
- `MAX_ACCT_ARCHIVE_FILE` enables automatic deletion of the archives

## Default

Not defined (no time set for archiving `lsb.acct`)

## CHUNK\_JOB\_DURATION

### Syntax

**CHUNK\_JOB\_DURATION**=*minutes*

### Description

Specifies a CPU limit, run limit, or estimated run time for jobs submitted to a chunk job queue to be chunked.

When `CHUNK_JOB_DURATION` is set, the CPU limit or run limit set at the queue level (`CPULIMIT` or `RUNLIMIT`), application level (`CPULIMIT` or `RUNLIMIT`), or job level (`-c` or `-W` `bsub` options), or the run time estimate set at the application level (`RUNTIME`) must be less than or equal to `CHUNK_JOB_DURATION` for jobs to be chunked.

If `CHUNK_JOB_DURATION` is set, jobs are *not* chunked if:

- No CPU limit, run time limit, or run time estimate is specified at any level, or
- A CPU limit, run time limit, or run time estimate is greater than the value of `CHUNK_JOB_DURATION`.

The value of `CHUNK_JOB_DURATION` is displayed by `bparams -l`.

## Examples

- `CHUNK_JOB_DURATION` is not defined:
  - Jobs with no CPU limit, run limit, or run time estimate are chunked
  - Jobs with a CPU limit, run limit, or run time estimate less than or equal to 30 are chunked

- Jobs with a CPU limit, run limit, or run time estimate greater than 30 are *not* chunked
- `CHUNK_JOB_DURATION=90`:
  - Jobs with no CPU limit, run limit, or run time estimate are *not* chunked
  - Jobs with a CPU limit, run limit, or run time estimate less than or equal to 90 are chunked
  - Jobs with a CPU limit, run limit, or run time estimate greater than 90 are *not* chunked

## Default

-1 (Not defined.)

## CLEAN\_PERIOD

### Syntax

**CLEAN\_PERIOD**=*seconds*

### Description

For non-repetitive jobs, the amount of time that job records for jobs that have finished or have been killed are kept in mbatchd core memory after they have finished.

Users can still see all jobs after they have finished using the `bj obs` command.

For jobs that finished more than `CLEAN_PERIOD` seconds ago, use the `bhi st` command.

## Default

3600 (1 hour)

## COMMITTED\_RUN\_TIME\_FACTOR

### Syntax

**COMMITTED\_RUN\_TIME\_FACTOR**=*number*

### Description

Used only with fairshare scheduling. Committed run time weighting factor.

In the calculation of a user's dynamic priority, this factor determines the relative importance of the committed run time in the calculation. If the `-W` option of `bsub` is not specified at job submission and a `RUNLIMIT` has not been set for the queue, the committed run time is not considered.

## Valid Values

Any positive number between 0.0 and 1.0

## Default

0.0

## COMPUTE\_UNIT\_TYPES

### Syntax

```
COMPUTE_UNIT_TYPES=type1 type2...
```

### Description

Used to define valid compute unit types for topological resource requirement allocation.

The order in which compute unit types appear specifies the containment relationship between types. Finer grained compute unit types appear first, followed by the coarser grained type that contains them, and so on.

At most one compute unit type in the list can be followed by an exclamation mark designating it as the default compute unit type. If no exclamation mark appears, the first compute unit type in the list is taken as the default type.

### Valid Values

Any space-separated list of alphanumeric strings.

### Default

Not defined

### Example

```
COMPUTE_UNIT_TYPES=cell enclosure! rack
```

Specifies three compute unit types, with the default type enclosure. Compute units of type rack contain type enclosure, and of type enclosure contain type cell.

## CONDENSE\_PENDING\_REASONS

### Syntax

```
CONDENSE_PENDING_REASONS=ALL | PARTIAL | N
```

### Description

Set to **ALL**, condenses all host-based pending reasons into one generic pending reason. This is equivalent to setting **CONDENSED\_PENDING\_REASON=Y**.

Set to **PARTIAL**, condenses all host-based pending reasons except shared resource pending reasons into one generic pending reason.

If enabled, you can request a full pending reason list by running the following command:  
**badmin diagnose *jobId***

---

#### Tip:

You must be LSF administrator or a queue administrator to run this command.

---

## Examples

- `CONDENSE_PENDING_REASONS=ALL` If a job has no other pending reason, `bj obs -p` or `bj obs -l` displays the following:  
Individual host based reasons
- `CONDENSE_PENDING_REASONS=N` The pending reasons are not suppressed. Host-based pending reasons are displayed.

## Default

N

## CPU\_TIME\_FACTOR

### Syntax

`CPU_TIME_FACTOR=number`

### Description

Used only with fairshare scheduling. CPU time weighting factor.

In the calculation of a user's dynamic share priority, this factor determines the relative importance of the cumulative CPU time used by a user's jobs.

## Default

0.7

## DEFAULT\_APPLICATION

### Syntax

`DEFAULT_APPLICATION=application_profile_name`

### Description

The name of the default application profile. The application profile must already be defined in `lsb.applications`.

When you submit a job to LSF without explicitly specifying an application profile, LSF associates the job with the specified application profile.

## Default

Not defined. When a user submits a job without explicitly specifying an application profile, and no default application profile is defined by this parameter, LSF does not associate the job with any application profile.

## DEFAULT\_HOST\_SPEC

### Syntax

`DEFAULT_HOST_SPEC=host_name | host_model`

## Description

The default CPU time normalization host for the cluster.

The CPU factor of the specified host or host model will be used to normalize the CPU time limit of all jobs in the cluster, unless the CPU time normalization host is specified at the queue or job level.

## Default

Not defined

## DEFAULT\_JOBGROUP

## Syntax

**DEFAULT\_JOBGROUP**=*job\_group\_name*

## Description

The name of the default job group.

When you submit a job to LSF without explicitly specifying a job group, LSF associates the job with the specified job group. The LSB\_DEFAULT\_JOBGROUP environment variable overrides the setting of DEFAULT\_JOBGROUP. The `bsub -g job_group_name` option overrides both LSB\_DEFAULT\_JOBGROUP and DEFAULT\_JOBGROUP.

Default job group specification supports macro substitution for project name (%p) and user name (%u). When you specify `bsub -P project_name`, the value of %p is the specified project name. If you do not specify a project name at job submission, %p is the project name defined by setting the environment variable LSB\_DEFAULTPROJECT, or the project name specified by DEFAULT\_PROJECT in `lsb.params`. the default project name is default.

For example, a default job group name specified by `DEFAULT_JOBGROUP=/canada/%p/%u` is expanded to the value for the LSF project name and the user name of the job submission user (for example, `/canada/projects/user1`).

Job group names must follow this format:

- Job group names must start with a slash character (/). For example, `DEFAULT_JOBGROUP=/A/B/C` is correct, but `DEFAULT_JOBGROUP=A/B/C` is not correct.
- Job group names cannot end with a slash character (/). For example, `DEFAULT_JOBGROUP=/A/` is not correct.
- Job group names cannot contain more than one slash character (/) in a row. For example, job group names like `DEFAULT_JOBGROUP=/A//B` or `DEFAULT_JOBGROUP=A///B` are not correct.
- Job group names cannot contain spaces. For example, `DEFAULT_JOBGROUP=/A/B C/D` is not correct.
- Project names and user names used for macro substitution with %p and %u cannot start or end with slash character (/).
- Project names and user names used for macro substitution with %p and %u cannot contain spaces or more than one slash character (/) in a row.
- Project names or user names containing slash character (/) will create separate job groups. For example, if the project name is `canada/projects`, `DEFAULT_JOBGROUP=%p` results in a job group hierarchy `/canada/projects`.

## Example

```
DEFAULT_JOBGROUP=/canada/projects
```

## Default

Not defined. When a user submits a job without explicitly specifying job group name, and the `LSB_DEFAULT_JOBGROUP` environment variable is not defined, LSF does not associate the job with any job group.

## DEFAULT\_PROJECT

### Syntax

```
DEFAULT_PROJECT=project_name
```

### Description

The name of the default project. Specify any string.

When you submit a job without specifying any project name, and the environment variable `LSB_DEFAULTPROJECT` is not set, LSF automatically assigns the job to this project.

## Default

```
default
```

## DEFAULT\_QUEUE

### Syntax

```
DEFAULT_QUEUE=queue_name ...
```

### Description

Space-separated list of candidate default queues (candidates must already be defined in `lsb.queues`).

When you submit a job to LSF without explicitly specifying a queue, and the environment variable `LSB_DEFAULTQUEUE` is not set, LSF puts the job in the first queue in this list that satisfies the job's specifications subject to other restrictions, such as requested hosts, queue status, etc.

## Default

This parameter is set at installation to `DEFAULT_QUEUE=normal`.

When a user submits a job to LSF without explicitly specifying a queue, and there are no candidate default queues defined (by this parameter or by the user's environment variable `LSB_DEFAULTQUEUE`), LSF automatically creates a new queue named `default`, using the default configuration, and submits the job to that queue.

## DEFAULT\_SLA\_VELOCITY

### Syntax

```
DEFAULT_SLA_VELOCITY=num_slots
```

## Description

For EGO-enabled SLA scheduling, the number of slots that the SLA should request for parallel jobs running in the SLA.

By default, an EGO-enabled SLA requests slots from EGO based on the number of jobs the SLA needs to run. If the jobs themselves require more than one slot, they will remain pending. To avoid this for parallel jobs, set `DEFAULT_SLA_VELOCITY` to the total number of slots that are expected to be used by parallel jobs.

## Default

1

## DETECT\_IDLE\_JOB\_AFTER

### Syntax

`DETECT_IDLE_JOB_AFTER=time_minutes`

### Description

The minimum job run time before `mbatchd` reports that the job is idle.

### Default

20 (`mbatchd` checks if the job is idle after 20 minutes of run time)

## DISABLE\_UACCT\_MAP

### Syntax

`DISABLE_UACCT_MAP=y | Y`

### Description

Specify `y` or `Y` to disable user-level account mapping.

### Default

N

## EADMIN\_TRIGGER\_DURATION

### Syntax

`EADMIN_TRIGGER_DURATION=minutes`

### Description

Defines how often `LSF_SERVERDIR/eadmin` is invoked once a job exception is detected. Used in conjunction with job exception handling parameters `JOB_IDLE`, `JOB_OVERRUN`, and `JOB_UNDERRUN` in `lsb_queues`.

---

**Tip:**

Tune EADMIN\_TRIGGER\_DURATION carefully. Shorter values may raise false alarms, longer values may not trigger exceptions frequently enough.

---

## Example

```
EADMIN_TRIGGER_DURATION=5
```

## Default

1 minute

## ENABLE\_DEFAULT\_EGO\_SLA

### Syntax

```
ENABLE_DEFAULT_EGO_SLA=service_class_name | consumer_name
```

### Description

The name of the default service class or EGO consumer name for EGO-enabled SLA scheduling. If the specified SLA does not exist in `lsb.serviceclasses`, LSF creates one with the specified consumer name, velocity of 1, priority of 1, and a time window that is always open.

If the name of the default SLA is not configured in `lsb.serviceclasses`, it must be the name of a valid EGO consumer.

ENABLE\_DEFAULT\_EGO\_SLA is required to turn on EGO-enabled SLA scheduling. All LSF resource management is delegated to Platform EGO, and all LSF hosts are under EGO control. When all jobs running in the default SLA finish, all allocated hosts are released to EGO after the default idle timeout of 120 seconds (configurable by MAX\_HOST\_IDLE\_TIME in `lsb.serviceclasses`).

When you submit a job to LSF without explicitly using the `-sla` option to specify a service class name, LSF puts the job in the default service class specified by *service\_class\_name*.

## Default

Not defined. When a user submits a job to LSF without explicitly specifying a service class, and there is no default service class defined by this parameter, LSF does not attach the job to any service class.

## ENABLE\_EVENT\_STREAM

### Syntax

```
ENABLE_EVENT_STREAM=Y | N
```

### Description

Used only with event streaming for system performance analysis tools, such as the Platform LSF reporting feature.

## Default

N (event streaming is not enabled)

## ENABLE\_EXIT\_RATE\_PER\_SLOT

### Syntax

ENABLE\_EXIT\_RATE\_PER\_SLOT=Y | N

### Description

Scales the actual exit rate thresholds on a host according to the number of slots on the host. For example, if EXIT\_RATE=2 in lsb. hosts or GLOBAL\_EXIT\_RATE=2 in lsb. params, and the host has 2 job slots, the job exit rate threshold will be 4.

## Default

N

## ENABLE\_HIST\_RUN\_TIME

### Syntax

ENABLE\_HIST\_RUN\_TIME=y | Y

### Description

Used only with fairshare scheduling. If set, enables the use of historical run time in the calculation of fairshare scheduling priority.

## Default

N

## ENABLE\_HOST\_INTERSECTION

### Syntax

ENABLE\_HOST\_INTERSECTION=Y | N

### Description

When enabled, allows job submission to any host that belongs to the intersection created when considering the queue the job was submitted to, any advance reservation hosts, or any hosts specified by bsub -m at the time of submission.

When disabled job submission with hosts specified can be accepted only if specified hosts are a subset of hosts defined in the queue.

The following commands are affected by ENABLE\_HOST\_INTERSECTION:

- bsub
- bmod
- bmg
- brestart

- `bswitch`

If no hosts exist in the intersection, the job is rejected.

## Default

N

## ENABLE\_USER\_RESUME

### Syntax

**ENABLE\_USER\_RESUME=Y | N**

### Description

Defines job resume permissions.

When this parameter is defined:

- If the value is Y, users can resume their own jobs that have been suspended by the administrator.
- If the value is N, jobs that are suspended by the administrator can only be resumed by the administrator or root; users do not have permission to resume a job suspended by another user or the administrator. Administrators can resume jobs suspended by users or administrators.

## Default

N (users cannot resume jobs suspended by administrator)

## ENFORCE\_ONE\_UG\_LIMITS

### Syntax

**ENFORCE\_ONE\_UG\_LIMITS=Y | N**

Upon job submission with the `-G` option and when user groups have overlapping members, defines whether only the specified user group's limits (or those of any parent group) are enforced or whether the most restrictive user group limits of any overlapping user/user group are enforced.

- If the value is Y, only the limits defined for the user group that you specify with `-G` during job submission apply to the job, even if there are overlapping members of groups.

If you have nested user groups, the limits of a user's group parent also apply.

View existing limits by running `blimits`.

- If the value is N and the user group has members that overlap with other user groups, the strictest possible limits (that you can view by running `blimits`) defined for any of the member user groups are enforced for the job.

## Default

N

## EVENT\_STREAM\_FILE

### Syntax

`EVENT_STREAM_FILE=file_path`

### Description

Determines the path to the event data stream file used by system performance analysis tools such as Platform LSF Reporting.

### Default

`LSF_TOP/work/cluster_name/logdir/stream/lsb.stream`

## EVENT\_UPDATE\_INTERVAL

### Syntax

`EVENT_UPDATE_INTERVAL=seconds`

### Description

Used with duplicate logging of event and accounting log files. `LSB_LOCALDIR` in `lsf.conf` must also be specified. Specifies how often to back up the data and synchronize the directories (`LSB_SHAREDIR` and `LSB_LOCALDIR`).

If you do not define this parameter, the directories are synchronized when data is logged to the files, or when `mbatchd` is started on the first LSF master host. If you define this parameter, `mbatchd` synchronizes the directories only at the specified time intervals.

Use this parameter if NFS traffic is too high and you want to reduce network traffic.

### Valid values

1 to `INFINIT_INT`

`INFINIT_INT` is defined in `lsf.h`

### Recommended values

Between 10 and 30 seconds, or longer depending on the amount of network traffic.

---

**Note:**

Avoid setting the value to exactly 30 seconds, because this will trigger the default behavior and cause `mbatchd` to synchronize the data every time an event is logged.

---

### Default

-1 (Not defined.)

### See also

`LSB_LOCALDIR` in `lsf.conf`

## EXIT\_RATE\_TYPE

### Syntax

**EXIT\_RATE\_TYPE**=[JOBEXIT | JOBEXIT\_NONLSF] [JOBINIT] [HPCINIT]

### Description

When host exception handling is configured (EXIT\_RATE in lsb. hosts or GLOBAL\_EXIT\_RATE in lsb. params), specifies the type of job exit to be handled.

#### **JOBEXIT**

Job exited after it was dispatched and started running.

#### **JOBEXIT\_NONLSF**

Job exited with exit reasons related to LSF and not related to a host problem (for example, user action or LSF policy). These jobs are not counted in the exit rate calculation for the host.

#### **JOBINIT**

Job exited during initialization because of an execution environment problem. The job did not actually start running.

#### **HPCINIT**

Job exited during initialization of a Platform LSF HPC because of an execution environment problem. The job did not actually start running.

### Default

JOBEXIT\_NONLSF

## FAIRSHARE\_ADJUSTMENT\_FACTOR

### Syntax

**FAIRSHARE\_ADJUSTMENT\_FACTOR**=*number*

### Description

Used only with fairshare scheduling. Fairshare adjustment plugin weighting factor.

In the calculation of a user's dynamic share priority, this factor determines the relative importance of the user-defined adjustment made in the fairshare plugin (libfairshareadjust.\*).

A positive float number both enables the fairshare plugin and acts as a weighting factor.

### Default

0 (user-defined adjustment made in the fairshare plugin not used)

## GLOBAL\_EXIT\_RATE

### Syntax

**GLOBAL\_EXIT\_RATE=number**

### Description

Specifies a cluster-wide threshold for exited jobs. If EXIT\_RATE is not specified for the host in `lsb.hosts`, GLOBAL\_EXIT\_RATE defines a default exit rate for all hosts in the cluster. Host-level EXIT\_RATE overrides the GLOBAL\_EXIT\_RATE value.

If the global job exit rate is exceeded for 5 minutes or the period specified by JOB\_EXIT\_RATE\_DURATION, LSF invokes LSF\_SERVERDIR/eadmin to trigger a host exception.

### Example

GLOBAL\_EXIT\_RATE=10 defines a job exit rate of 10 jobs for all hosts.

### Default

2147483647 (Unlimited threshold.)

## HIST\_HOURS

### Syntax

**HIST\_HOURS=hours**

### Description

Used only with fairshare scheduling. Determines a rate of decay for cumulative CPU time and historical run time.

To calculate dynamic user priority, LSF scales the actual CPU time using a decay factor, so that 1 hour of recently-used time is equivalent to 0.1 hours after the specified number of hours has elapsed.

To calculate dynamic user priority with historical run time, LSF scales the accumulated run time of finished jobs using the same decay factor, so that 1 hour of recently-used time is equivalent to 0.1 hours after the specified number of hours has elapsed.

When HIST\_HOURS=0, CPU time accumulated by running jobs is not decayed.

### Default

5

## JOB\_ACCEPT\_INTERVAL

### Syntax

**JOB\_ACCEPT\_INTERVAL=integer**

## Description

The number you specify is multiplied by the value of `lsb.params MBD_SLEEP_TIME` (60 seconds by default). The result of the calculation is the number of seconds to wait after dispatching a job to a host, before dispatching a second job to the same host.

If 0 (zero), a host may accept more than one job. By default, there is no limit to the total number of jobs that can run on a host, so if this parameter is set to 0, a very large number of jobs might be dispatched to a host all at once. This can overload your system to the point that it will be unable to create any more processes. It is not recommended to set this parameter to 0.

`JOB_ACCEPT_INTERVAL` set at the queue level (`lsb.queues`) overrides `JOB_ACCEPT_INTERVAL` set at the cluster level (`lsb.params`).

## Default

1

## JOB\_ATTA\_DIR

### Syntax

`JOB_ATTA_DIR=directory`

## Description

The shared directory in which `mbatchd` saves the attached data of messages posted with the `bpost` command.

Use `JOB_ATTA_DIR` if you use `bpost` and `bread` to transfer large data files between jobs and want to avoid using space in `LSB_SHAREDDIR`. By default, the `bread` command reads attachment data from the `JOB_ATTA_DIR` directory.

`JOB_ATTA_DIR` should be shared by all hosts in the cluster, so that any potential LSF master host can reach it. Like `LSB_SHAREDDIR`, the directory should be owned and writable by the primary LSF administrator. The directory must have at least 1 MB of free space.

The attached data will be stored under the directory in the format:

```
JOB_ATTA_DIR/timestamp.jobid.msgs/msg$msgid
```

On UNIX, specify an absolute path. For example:

```
JOB_ATTA_DIR=/opt/share/lsf_work
```

On Windows, specify a UNC path or a path with a drive letter. For example:

```
JOB_ATTA_DIR=\\HostA\temp\lsf_work
```

or

```
JOB_ATTA_DIR=D:\temp\lsf_work
```

After adding `JOB_ATTA_DIR` to `lsb.params`, use `badm in reconfi g` to reconfigure your cluster.

## Valid values

`JOB_ATTA_DIR` can be any valid UNIX or Windows path up to a maximum length of 256 characters.

## Default

Not defined

If `JOB_ATTA_DIR` is not specified, job message attachments are saved in `LSB_SHAREDINFO/`.

## JOB\_DEP\_LAST\_SUB

### Description

Used only with job dependency scheduling.

If set to 1, whenever dependency conditions use a job name that belongs to multiple jobs, LSF evaluates only the most recently submitted job.

Otherwise, all the jobs with the specified name must satisfy the dependency condition.

### Default

0

## JOB\_EXIT\_RATE\_DURATION

### Description

Defines how long LSF waits before checking the job exit rate for a host. Used in conjunction with `EXIT_RATE` in `lsb.hosts` for LSF host exception handling.

If the job exit rate is exceeded for the period specified by `JOB_EXIT_RATE_DURATION`, LSF invokes `LSF_SERVERDEFAULT/admin` to trigger a host exception.

### Tuning

---

**Tip:**

Tune `JOB_EXIT_RATE_DURATION` carefully. Shorter values may raise false alarms, longer values may not trigger exceptions frequently enough.

---

### Example

```
JOB_EXIT_RATE_DURATION=10
```

### Default

5 minutes

## JOB\_GROUP\_CLEAN

### Syntax

`JOB_GROUP_CLEAN=Y | N`

## Description

If `JOB_GROUP_CLEAN = Y`, implicitly created job groups that are empty and have no limits assigned to them are automatically deleted.

## Default

N (Implicitly created job groups are not automatically deleted unless they are deleted manually with `bgdel`.)

## JOB\_INCLUDE\_POSTPROC

### Syntax

`JOB_INCLUDE_POSTPROC=Y | N`

## Description

Specifies whether LSF includes the post-execution processing of the job as part of the job. When set to Y:

- Prevents a new job from starting on a host until post-execution processing is finished on that host
- Includes the CPU and run times of post-execution processing with the job CPU and run times
- `sbatchd` sends both job finish status (DONE or EXIT) and post-execution processing status (POST\_DONE or POST\_ERR) to `mbatchd` at the same time

In MultiCluster job forwarding model, the `JOB_INCLUDE_POSTPROC` value in the receiving cluster applies to the job.

MultiCluster job lease model, the `JOB_INCLUDE_POSTPROC` value applies to jobs running on remote leased hosts as if they were running on local hosts.

The variable `LSB_JOB_INCLUDE_POSTPROC` in the user environment overrides the value of `JOB_INCLUDE_POSTPROC` in an application profile in `lsb.appl icat i ons`.

`JOB_INCLUDE_POSTPROC` in an application profile in `lsb.appl icat i ons` overrides the value of `JOB_INCLUDE_POSTPROC` in `lsb.params`.

For SGI cpusets, if `JOB_INCLUDE_POSTPROC=Y`, LSF does not release the cpuset until post-execution processing has finished, even though post-execution processes are not attached to the cpuset.

## Default

N (Post-execution processing is not included as part of the job, and a new job can start on the execution host before post-execution processing finishes.)

## JOB\_POSITION\_CONTROL\_BY\_ADMIN

### Syntax

`JOB_POSITION_CONTROL_BY_ADMIN=Y | N`

## Description

Allows LSF administrators to control whether users can use `bt op` and `bbot` to move jobs to the top and bottom of queues. When `JOB_POSITION_CONTROL_BY_ADMIN=Y`, only the

lsb.params

LSF administrator (including any queue administrators) can use `bbot` and `bt op` to move jobs within a queue.

## Default

N

## See also

`bbot`, `bt op`

## JOB\_POSTPROC\_TIMEOUT

### Syntax

**JOB\_POSTPROC\_TIMEOUT**=*minutes*

### Description

Specifies a timeout in minutes for job post-execution processing. The specified timeout must be greater than zero.

If post-execution processing takes longer than the timeout, `sbat chd` reports that post-execution has failed (POST\_ERR status), and kills the entire process group of the job's post-execution processes on UNIX and Linux. On Windows, only the parent process of the post-execution command is killed when the timeout expires. The child processes of the post-execution command are not killed.

If `JOB_INCLUDE_POSTPROC=Y`, and `sbat chd` kills the post-execution processes because the timeout has been reached, the CPU time of the post-execution processing is set to 0, and the job's CPU time does not include the CPU time of post-execution processing.

`JOB_POSTPROC_TIMEOUT` defined in an application profile in `lsb.appl icat ions` overrides the value in `lsb.params`. `JOB_POSTPROC_TIMEOUT` cannot be defined in user environment.

In MultiCluster job forwarding model, the `JOB_POSTPROC_TIMEOUT` value in the receiving cluster applies to the job.

MultiCluster job lease model, the `JOB_POSTPROC_TIMEOUT` value applies to jobs running on remote leased hosts as if they were running on local hosts.

## Default

2147483647 (Unlimited; post-execution processing does not time out.)

## JOB\_PRIORITY\_OVER\_TIME

### Syntax

**JOB\_PRIORITY\_OVER\_TIME**=*increment#interval*

### Description

`JOB_PRIORITY_OVER_TIME` enables automatic job priority escalation when `MAX_USER_PRIORITY` is also defined.

## Valid Values

*increment*

Specifies the value used to increase job priority every *interval* minutes. Valid values are positive integers.

*interval*

Specifies the frequency, in minutes, to *increment* job priority. Valid values are positive integers.

## Default

-1 (Not defined.)

## Example

```
JOB_PRIORITY_OVER_TIME=3/20
```

Specifies that every 20 minute *interval increment* to job priority of pending jobs by 3.

## See also

MAX\_USER\_PRIORITY

## JOB\_RUNLIMIT\_RATIO

### Syntax

```
JOB_RUNLIMIT_RATIO=integer | 0
```

### Description

Specifies a ratio between a job run limit and the runtime estimate specified by `bsub -We` or `bmod -We`, `-We+`, `-Wep`. The ratio does not apply to the `RUNTIME` parameter in `lsb.appl icat ions`.

This ratio can be set to 0 and no restrictions are applied to the runtime estimate.

`JOB_RUNLIMIT_RATIO` prevents abuse of the runtime estimate. The value of this parameter is the ratio of run limit divided by the runtime estimate.

By default, the ratio value is 0. Only administrators can set or change this ratio. If the ratio changes, it only applies to newly submitted jobs. The changed value does not retroactively reapply to already submitted jobs.

If the ratio value is greater than 0:

- If the users specify a runtime estimate only (`bsub -We`), the job-level run limit will automatically be set to  $runtime\_ratio * runtime\_estimate$ . Jobs running longer than this run limit are killed by LSF. If the job-level run limit is greater than the hard run limit in the queue, the job is rejected.
- If the users specify a runtime estimate (`-We`) and job run limit (`-W`) at job submission, and the run limit is greater than  $runtime\_ratio * runtime\_estimate$ , the job is rejected.
- If the users modify the run limit to be greater than  $runtime\_ratio$ , they must increase the runtime estimate first (`bmod -We`). Then they can increase the default run limit.
- LSF remembers the run limit is set with `bsub -W` or convert from  $runtime\_ratio * runtime\_estimate$ . When users modify the run limit with `bmod -Wn`, the run limit is

automatically be set to  $runtime\_ratio * runtime\_estimate$ . If the run limit is set from  $runtime\_ratio$ , LSF rejects the run limit modification.

- If users modify the runtime estimate with `bmod -We` and the run limit is set by the user, the run limit is  $\text{MIN}(new\_estimate * new\_ratio, run\_limit)$ . If the run limit is set by  $runtime\_ratio$ , the run limit is set to  $new\_estimate * new\_ratio$ .
- If users modify the runtime estimate by using `bmod -Wen` and the run limit is set by the user, it is not changed. If the run limit is set by  $runtime\_ratio$ , it is set to unlimited.

In MultiCluster job forwarding model, `JOB_RUNLIMIT_RATIO` values in both the sending and receiving clusters apply to the job. The run limit in the receiving cluster cannot be greater than the value of  $runtime * \text{JOB\_RUNLIMIT\_RATIO}$  in the receiving cluster. Some examples:

- Run limit (for example with `bsub -We`) is 10, `JOB_RUNLIMIT_RATIO=5` in the sending cluster, `JOB_RUNLIMIT_RATIO=0` in the receiving cluster—run limit=50, and the job will run
- Run limit (for example with `bsub -We`) is 10, `JOB_RUNLIMIT_RATIO=5` in the sending cluster, `JOB_RUNLIMIT_RATIO=3` in the receiving cluster—run limit=50, and the job will pend
- Run limit (for example with `bsub -We`) is 10, `JOB_RUNLIMIT_RATIO=5` in the sending cluster, `JOB_RUNLIMIT_RATIO=6` in the receiving cluster—run limit=50, and the job will run
- Run limit (for example with `bsub -We`) is 10, `JOB_RUNLIMIT_RATIO=0` in the sending cluster, `JOB_RUNLIMIT_RATIO=5` in the receiving cluster—run limit=50, and the job will run

MultiCluster job lease model, the `JOB_RUNLIMIT_RATIO` value applies to jobs running on remote leased hosts as if they were running on local hosts.

## Default

0

## JOB\_SCHEDULING\_INTERVAL

### Syntax

`JOB_SCHEDULING_INTERVAL=milliseconds`

### Description

Time interval at which `mbatchd` sends jobs for scheduling to the scheduling daemon `mbschd` along with any collected load information.

If set to 0, there is no interval between job scheduling sessions.

### Valid Value

Number of seconds greater than or equal to zero (0).

### Default

5000 milliseconds

## JOB\_SPOOL\_DIR

### Syntax

**JOB\_SPOOL\_DIR=dir**

### Description

Specifies the directory for buffering batch standard output and standard error for a job.

When JOB\_SPOOL\_DIR is defined, the standard output and standard error for the job is buffered in the specified directory.

Files are copied from the submission host to a temporary file in the directory specified by the JOB\_SPOOL\_DIR on the execution host. LSF removes these files when the job completes.

If JOB\_SPOOL\_DIR is not accessible or does not exist, files are spooled to the default job output directory \$HOME/.lsbatch.

For `bsub -is` and `bsub -Zs`, JOB\_SPOOL\_DIR must be readable and writable by the job submission user, and it must be shared by the master host and the submission host. If the specified directory is not accessible or does not exist, and JOB\_SPOOL\_DIR is specified, `bsub -is` cannot write to the default directory `LSB_SHAREDIR/cluster_name/l sf_i ndr`, and `bsub -Zs` cannot write to the default directory `LSB_SHAREDIR/cluster_name/l sf_cmddr`, and the job will fail.

As LSF runs jobs, it creates temporary directories and files under JOB\_SPOOL\_DIR. By default, LSF removes these directories and files after the job is finished. See `bsub` for information about job submission options that specify the disposition of these files.

On UNIX, specify an absolute path. For example:

```
JOB_SPOOL_DIR=/home/share/l sf_spool
```

On Windows, specify a UNC path or a path with a drive letter. For example:

```
JOB_SPOOL_DIR=\\HostA\share\spool dir
```

or

```
JOB_SPOOL_DIR=D: \share\spool dir
```

In a mixed UNIX/Windows cluster, specify one path for the UNIX platform and one for the Windows platform. Separate the two paths by a pipe character (|):

```
JOB_SPOOL_DIR=/usr/share/l sf_spool | \\HostA\share\spool dir
```

### Valid value

JOB\_SPOOL\_DIR can be any valid path.

The entire path including JOB\_SPOOL\_DIR can up to 4094 characters on UNIX and Linux or up to 255 characters for Windows. This maximum path length includes:

- All directory and file paths attached to the JOB\_SPOOL\_DIR path
- Temporary directories and files that the LSF system creates as jobs run.

The path you specify for JOB\_SPOOL\_DIR should be as short as possible to avoid exceeding this limit.

### Default

Not defined

Batch job output (standard output and standard error) is sent to the `.lsbatch` directory on the execution host:

- On UNIX: `$HOME/.lsbatch`
- On Windows: `%windir%\lsbatch\%user_id%`

If `%HOME%` is specified in the user environment, uses that directory instead of `%windir%` for spooled output.

## JOB\_TERMINATE\_INTERVAL

### Syntax

**JOB\_TERMINATE\_INTERVAL**=*seconds*

### Description

UNIX only.

Specifies the time interval in seconds between sending SIGINT, SIGTERM, and SIGKILL when terminating a job. When a job is terminated, the job is sent SIGINT, SIGTERM, and SIGKILL in sequence with a sleep time of `JOB_TERMINATE_INTERVAL` between sending the signals. This allows the job to clean up if necessary.

### Default

10 (seconds)

## LOCAL\_MAX\_PREEEXEC\_RETRY

### Syntax

**LOCAL\_MAX\_PREEEXEC\_RETRY**=*integer*

### Description

The maximum number of times to attempt the pre-execution command of a job on the local cluster.

### Valid values

`0 < LOCAL_MAX_PREEEXEC_RETRY < INFINIT_INT`  
`INFINIT_INT` is defined in `lsf.h`.

### Default

2147483647 (Unlimited number of preexec retry times.)

## LSB\_STOP\_ASKING\_LICENSES\_TO\_LS

### Syntax

**LSB\_STOP\_ASKING\_LICENSES\_TO\_LS**=*n | N | y | Y*

## Description

Used in conjunction with LSF License Scheduler, optimizes the licenses available to pending jobs. Setting this parameter to `y` stops `mbatchd` from requesting a license from the License Scheduler daemon when a job cannot run—even with a license—because of other pending reasons. For example, if `jobA` pends because of a license shortage, and, while `jobA` waits for a license, other jobs fill all available slots, `mbatchd` stops requesting a license for `jobA`. This prevents `jobA` from obtaining a license that it cannot use, which makes more licenses available for other jobs. Once the slots required by `jobA` become available, `mbatchd` requests a license for `jobA`. If no license is available, `jobA` pends until it gets a license.

## Default

N. A job that was initially pending due to a license requirement and is now pending for another reason continues to request a license.

## LSB\_SYNC\_HOST\_STAT\_LIM

### Syntax

`LSB_SYNC_HOST_STAT_LIM=y | Y`

## Description

Improves the speed with which `mbatchd` obtains host status, and therefore the speed with which LSF reschedules rerunnable jobs: the sooner LSF knows that a host has become unavailable, the sooner LSF reschedules any rerunnable jobs executing on that host. Useful for a large cluster.

When you define this parameter, `mbatchd` periodically obtains the host status from the master LIM, and then verifies the status by polling each `sbatchd` at an interval defined by the parameters `MBD_SLEEP_TIME` and `LSB_MAX_PROBE_SBD`.

## Default

N. `mbatchd` obtains and reports host status, without contacting the master LIM, by polling each `sbatchd` at an interval defined by the parameters `MBD_SLEEP_TIME` and `LSB_MAX_PROBE_SBD`.

## See also

`MBD_SLEEP_TIME`

`LSB_MAX_PROBE_SBD` in `lsf.conf`

## MAX\_ACCT\_ARCHIVE\_FILE

### Syntax

`MAX_ACCT_ARCHIVE_FILE=integer`

## Description

Enables automatic deletion of archived LSF accounting log files and specifies the archive limit.

## Compatibility

ACCT\_ARCHIVE\_SIZE or ACCT\_ARCHIVE\_AGE should also be defined.

## Example

```
MAX_ACCT_ARCHIVE_FILE=10
```

LSF maintains the current lsb. acct and up to 10 archives. Every time the old lsb. acct. 9 becomes lsb. acct. 10, the old lsb. acct. 10 gets deleted.

## See also

- ACCT\_ARCHIVE\_AGE also enables automatic archiving
- ACCT\_ARCHIVE\_SIZE also enables automatic archiving
- ACCT\_ARCHIVE\_TIME also enables automatic archiving

## Default

-1 (Not defined. No deletion of lsb. acct. *n* files).

## MAX\_CONCURRENT\_JOB\_QUERY

### Syntax

```
MAX_CONCURRENT_JOB_QUERY=integer
```

### Description

Defines how many concurrent job queries mbatchd can handle.

- If mbatchd is using multithreading, a dedicated query port is defined by the parameter LSB\_QUERY\_PORT in lsf.conf. When mbatchd has a dedicated query port, the value of MAX\_CONCURRENT\_JOB\_QUERY sets the maximum number of job queries for each child mbatchd that is forked by mbatchd. This means that the total number of job queries can be more than the number specified by MAX\_CONCURRENT\_JOB\_QUERY.
- If mbatchd is not using multithreading, the value of MAX\_CONCURRENT\_JOB\_QUERY sets the maximum total number of job queries.

### Valid values

1-100

### Default

2147483647 (Unlimited concurrent job queries.)

### See also

LSB\_QUERY\_PORT in lsf.conf

## MAX\_EVENT\_STREAM\_FILE\_NUMBER

### Syntax

```
MAX_EVENT_STREAM_FILE_NUMBER=integer
```

## Description

Determines the maximum number of different `lsb.stream.utc` files that `mbatchd` uses. If the number of `lsb.stream.utc` files reaches this number, `mbatchd` logs and error message to the `mbd.log` file and stops writing events to the `lsb.stream` file.

## Default

10

## MAX\_EVENT\_STREAM\_SIZE

## Syntax

**MAX\_EVENT\_STREAM\_SIZE**=*integer*

## Description

Determines the maximum size in MB of the `lsb.stream` file used by system performance analysis tools such as Platform LSF Reporting. For LSF Reporting, the recommended size is 2000 MB.

When the `MAX_EVENT_STREAM_SIZE` size is reached, LSF logs a special event `EVENT_END_OF_STREAM`, closes the stream and moves it to `lsb.stream.0` and a new stream is opened.

All applications that read the file once the event `EVENT_END_OF_STREAM` is logged should close the file and reopen it.

## Recommended value

2000 MB

## Default

1024 MB

## MAX\_INFO\_DIRS

## Syntax

**MAX\_INFO\_DIRS**=*num\_subdirs*

## Description

The number of subdirectories under the `LSB_SHAREDIR/cluster_name/logdir/info` directory.

When `MAX_INFO_DIRS` is enabled, `mbatchd` creates the specified number of subdirectories in the `info` directory. These subdirectories are given an integer as its name, starting with 0 for the first subdirectory. `mbatchd` writes the job files of all new submitted jobs into these subdirectories using the following formula to choose the subdirectory in which to store the job file:

```
subdirectory = jobId % MAX_INFO_DIRS
```

This formula ensures an even distribution of job files across the subdirectories.

---

**Important:**

If you are using local duplicate event logging, you must run `badadmin mbdrestart` after changing `MAX_INFO_DIRS` for the changes to take effect.

---

## Valid values

0-1024

## Default

0 (no subdirectories under the `info` directory; `mbatchd` writes all jobfiles to the `info` directory)

## Example

```
MAX_INFO_DIRS=10
```

`mbatchd` creates ten subdirectories from `LSB_SHAREDIR/cluster_name/logdir/info/0` to `LSB_SHAREDIR/cluster_name/logdir/info/9`.

## MAX\_JOB\_ARRAY\_SIZE

### Syntax

```
MAX_JOB_ARRAY_SIZE=integer
```

### Description

Specifies the maximum number of jobs in a job array that can be created by a user for a single job submission. The maximum number of jobs in a job array cannot exceed this value.

A large job array allows a user to submit a large number of jobs to the system with a single job submission.

### Valid values

Specify a positive integer between 1 and 2147483646

### Default

1000

## MAX\_JOB\_ATTACHEMENT\_SIZE

### Syntax

```
MAX_JOB_ATTACHEMENT_SIZE=integer | 0
```

Specify any number less than 20000.

### Description

Maximum attached data size, in KB, that can be transferred to a job.

Maximum size for data attached to a job with the `bpost` command. Useful if you use `bpost` and `bread` to transfer large data files between jobs and you want to limit the usage in the current working directory.

0 indicates that jobs cannot accept attached data files.

## Default

2147483647 (Unlimited; LSF does not set a maximum size of job attachments.)

## MAX\_JOB\_MSG\_NUM

### Syntax

**MAX\_JOB\_MSG\_NUM**=*integer* | 0

### Description

Maximum number of message slots for each job. Maximum number of messages that can be posted to a job with the `bpost` command.

0 indicates that jobs cannot accept external messages.

## Default

128

## MAX\_JOB\_NUM

### Syntax

**MAX\_JOB\_NUM**=*integer*

### Description

The maximum number of finished jobs whose events are to be stored in the `l sb. event s` log file.

Once the limit is reached, `mbatchd` starts a new event log file. The old event log file is saved as `l sb. event s. n`, with subsequent sequence number suffixes incremented by 1 each time a new log file is started. Event logging continues in the new `l sb. event s` file.

## Default

1000

## MAX\_JOB\_PREEMPT

### Syntax

**MAX\_JOB\_PREEMPT**=*integer*

### Description

The maximum number of times a job can be preempted. Applies to queue-level jobs only.

## Valid values

$0 < \text{MAX\_JOB\_PREEMPT} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in l sf . h.

## Default

2147483647 (Unlimited number of preemption times.)

## MAX\_JOB\_REQUEUE

### Syntax

**MAX\_JOB\_REQUEUE**=*integer*

### Description

The maximum number of times to requeue a job automatically.

## Valid values

$0 < \text{MAX\_JOB\_REQUEUE} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in l sf . h.

## Default

2147483647 (Unlimited number of requeue times.)

## MAX\_JOBID

### Syntax

**MAX\_JOBID**=*integer*

### Description

The job ID limit. The job ID limit is the highest job ID that LSF will ever assign, and also the maximum number of jobs in the system.

By default, LSF assigns job IDs up to 6 digits. This means that no more than 999999 jobs can be in the system at once.

Specify any integer from 999999 to 2147483646 (for practical purposes, you can use any 10-digit integer less than this value).

You cannot lower the job ID limit, but you can raise it to 10 digits. This allows longer term job accounting and analysis, and means you can have more jobs in the system, and the job ID numbers will roll over less often.

LSF assigns job IDs in sequence. When the job ID limit is reached, the count rolls over, so the next job submitted gets job ID "1". If the original job 1 remains in the system, LSF skips that number and assigns job ID "2", or the next available job ID. If you have so many jobs in the system that the low job IDs are still in use when the maximum job ID is assigned, jobs with sequential numbers could have totally different submission times.

## Example

```
MAX_JOBID=12500000
```

## Default

```
999999
```

## MAX\_JOBINFO\_QUERY\_PERIOD

### Syntax

```
MAX_JOBINFO_QUERY_PERIOD=integer
```

### Description

Maximum time for job information query commands (for example, with `bj obs`) to wait.

When the time arrives, the query command processes exit, and all associated threads are terminated.

If the parameter is not defined, query command processes will wait for all threads to finish.

Specify a multiple of `MBD_REFRESH_TIME`.

### Valid values

Any positive integer greater than or equal to one (1)

### Default

```
2147483647 (Unlimited wait time.)
```

### See also

`LSB_BLOCK_JOBINFO_TIMEOUT` in `lsf.conf`

## MAX\_PEND\_JOBS

### Syntax

```
MAX_PEND_JOBS=integer
```

### Description

The maximum number of pending jobs in the system.

This is the hard system-wide pending job threshold. No user or user group can exceed this limit unless the job is forwarded from a remote cluster.

If the user or user group submitting the job has reached the pending job threshold as specified by `MAX_PEND_JOBS`, LSF will reject any further job submission requests sent by that user or user group. The system will continue to send the job submission requests with the interval specified by `SUB_TRY_INTERVAL` in `lsb.params` until it has made a number of attempts equal to the `LSB_NTRIES` environment variable. If `LSB_NTRIES` is not defined and LSF rejects the job submission request, the system will continue to send the job submission requests indefinitely as the default behavior.

lsb.params

## Default

2147483647 (Unlimited number of pending jobs.)

## See also

SUB\_TRY\_INTERVAL

## MAX\_PREEEXEC\_RETRY

### Syntax

**MAX\_PREEEXEC\_RETRY**=*integer*

### Description

MultiCluster job forwarding model only. The maximum number of times to attempt the pre-execution command of a job from a remote cluster.

If the job's pre-execution command fails all attempts, the job is returned to the submission cluster.

### Valid values

$0 < \text{MAX\_PREEEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in lsf.h.

### Default

5

## MAX\_SBD\_FAIL

### Syntax

**MAX\_SBD\_FAIL**=*integer*

### Description

The maximum number of retries for reaching a non-responding slave batch daemon, sbatchd.

The interval between retries is defined by MBD\_SLEEP\_TIME. If mbatchd fails to reach a host and has retried MAX\_SBD\_FAIL times, the host is considered unreachable.

If you define LSB\_SYNC\_HOST\_STAT\_LIM=Y, mbatchd obtains the host status from the master LIM before it polls sbatchd. When the master LIM reports that a host is unavailable (LIM is down) or unreachable (sbatchd is down) MAX\_SBD\_FAIL number of times, mbatchd reports the host status as unavailable or unreachable.

When a host becomes unavailable, mbatchd assumes that all jobs running on that host have exited and that all rerunnable jobs (jobs submitted with the bsub -r option) are scheduled to be rerun on another host.

## Default

3

## MAX\_USER\_PRIORITY

### Syntax

**MAX\_USER\_PRIORITY**=*integer*

### Description

Enables user-assigned job priority and specifies the maximum job priority a user can assign to a job.

LSF and queue administrators can assign a job priority higher than the specified value for jobs they own.

### Compatibility

User-assigned job priority changes the behavior of `bt op` and `bbot`.

### Example

```
MAX_USER_PRIORITY=100
```

Specifies that 100 is the maximum job priority that can be specified by a user.

## Default

-1 (Not defined.)

## See also

- `bsub`, `bmod`, `bt op`, `bbot`
- `JOB_PRIORITY_OVER_TIME`

## MBD\_EGO\_CONNECT\_TIMEOUT

### Syntax

**MBD\_EGO\_CONNECT\_TIMEOUT**=*seconds*

### Description

For EGO-enabled SLA scheduling, timeout parameter for network I/O connection with EGO `venkd`.

## Default

0 seconds

## MBD\_EGO\_READ\_TIMEOUT

### Syntax

**MBD\_EGO\_READ\_TIMEOUT**=*seconds*

## Description

For EGO-enabled SLA scheduling, timeout parameter for network I/O read from EGO vemkd after connection with EGO.

## Default

0 seconds

## MBD\_EGO\_TIME2LIVE

## Syntax

**MBD\_EGO\_TIME2LIVE=*minutes***

## Description

For EGO-enabled SLA scheduling, specifies how long EGO should keep information about host allocations in case mbatchd restarts,

## Default

0 minutes

## MBD\_QUERY\_CPUS

## Syntax

**MBD\_QUERY\_CPUS=*cpu\_list***

*cpu\_list* defines the list of master host CPUs on which the mbatchd child query processes can run. Format the list as a white-space delimited list of CPU numbers.

For example, if you specify

**MBD\_QUERY\_CPUS=1 2 3**

the mbatchd child query processes will run only on CPU numbers 1, 2, and 3 on the master host.

## Description

This parameter allows you to specify the master host CPUs on which mbatchd child query processes can run (hard CPU affinity). This improves mbatchd scheduling and dispatch performance by binding query processes to specific CPUs so that higher priority mbatchd processes can run more efficiently.

When you define this parameter, LSF runs mbatchd child query processes *only* on the specified CPUs. The operating system can assign other processes to run on the same CPU; however, if utilization of the bound CPU is lower than utilization of the unbound CPUs.

## Important

1. You can specify CPU affinity only for master hosts that use one of the following operating systems:
  - Linux 2.6 or higher
  - Solaris 8 or higher

2. If failover to a master host candidate occurs, LSF maintains the hard CPU affinity, provided that the master host candidate has the same CPU configuration as the original master host. If the configuration differs, LSF ignores the CPU list and reverts to default behavior.

## Related parameters

To improve scheduling and dispatch performance of all LSF daemons, you should use `MBD_QUERY_CPUS` together with `EGO_DAEMONS_CPUS` (in `ego.conf`), which controls LIM CPU allocation, and `LSF_DAEMONS_CPUS`, which binds `mbatchd` and `mbschd` daemon processes to specific CPUs so that higher priority daemon processes can run more efficiently. To get best performance, CPU allocation for all four daemons should be assigned their own CPUs. For example, on a 4 CPU SMP host, the following configuration will give the best performance:

```
EGO_DAEMONS_CPUS=0 LSF_DAEMONS_CPUS=1: 2 MBD_QUERY_CPUS=3
```

## Default

Not defined

## See also

`LSF_DAEMONS_CPUS` in `lsf.conf`

## MBD\_REFRESH\_TIME

### Syntax

**MBD\_REFRESH\_TIME=seconds** [*min\_refresh\_time*]

where *min\_refresh\_time* defines the minimum time (in seconds) that the child `mbatchd` will stay to handle queries. The valid range is 0 - 300.

### Description

Time interval, in seconds, when `mbatchd` will fork a new child `mbatchd` to service query requests to keep information sent back to clients updated. A child `mbatchd` processes query requests creating threads.

`MBD_REFRESH_TIME` applies only to UNIX platforms that support thread programming.

To enable `MBD_REFRESH_TIME` you must specify `LSB_QUERY_PORT` in `lsf.conf`. The child `mbatchd` listens to the port number specified by `LSB_QUERY_PORT` and creates threads to service requests until the job changes status, a new job is submitted, or

`MBD_REFRESH_TIME` has expired.

- If `MBD_REFRESH_TIME` is < *min\_refresh\_time*, the child `mbatchd` exits at `MBD_REFRESH_TIME` even if the job changes status or a new job is submitted before `MBD_REFRESH_TIME` expires.
- If `MBD_REFRESH_TIME` > *min\_refresh\_time* the child `mbatchd` exits at *min\_refresh\_time* if a job changes status or a new job is submitted before the *min\_refresh\_time*, or a job exits after the *min\_refresh\_time* when a job changes status or a new job is submitted.
- If `MBD_REFRESH_TIME` > *min\_refresh\_time* and no job changes status or a new job is submitted, the child `mbatchd` exits at `MBD_REFRESH_TIME`

The value of this parameter must be between 0 and 300. Any values specified out of this range are ignored, and the system default value is applied.

The `bj obs` command may not display up-to-date information if two consecutive query commands are issued before a child `mbatchd` expires because child `mbatchd` job information is not updated. If you use the `bj obs` command and do not get up-to-date information, you may need to decrease the value of this parameter. Note, however, that the lower the value of this parameter, the more you negatively affect performance.

The number of concurrent requests is limited by the number of concurrent threads that a process can have. This number varies by platform:

- Sun Solaris, 2500 threads per process
- AIX, 512 threads per process
- Digital, 256 threads per process
- HP-UX, 64 threads per process

## Default

5 seconds if `min_refresh_time` is not defined or if `MBD_REFRESH_TIME` is defined value is less than 5; 300 seconds if the defined value is more than 300

`min_refresh_time` default is 10 seconds

## See also

`LSB_QUERY_PORT` in `lsf.conf`

## MBD\_SLEEP\_TIME

### Syntax

**MBD\_SLEEP\_TIME=seconds**

### Description

Used in conjunction with the parameters `SLOT_RESERVE`, `MAX_SBD_FAIL`, and `JOB_ACCEPT_INTERVAL`.

Amount of time in seconds used for calculating parameter values.

### Default

If not defined, 60 seconds. `MBD_SLEEP_TIME` is set at installation to 20 seconds.

## MBD\_USE\_EGO\_MXJ

### Syntax

**MBD\_USE\_EGO\_MXJ=Y | N**

### Description

By default, when EGO-enabled SLA scheduling is configured, EGO allocates an entire host to LSF, which uses its own `MXJ` definition to determine how many slots are available on the host. LSF gets its host allocation from EGO, and runs as many jobs as the LSF configured `MXJ` for that host dictates.

`MBD_USE_EGO_MXJ` forces LSF to use the job slot maximum configured in the EGO consumer. This allows partial sharing of hosts (for example, a large SMP computer) among

different consumers or workload managers. When `MBD_USE_EGO_MXJ` is set, LSF schedules jobs based on the number of slots allocated from EGO. For example, if host A has 4 processors, but EGO allocates 2 slots to an EGO-enabled SLA consumer. LSF can schedule a maximum of 2 jobs from that SLA on host A.

---

**Important:**

If you set `MBD_USE_EGO_MXJ=Y`, you can configure only one service class, including the default SLA.

---

## Default

N (mbatchd uses the LSF MXJ)

## MC\_PENDING\_REASON\_PKG\_SIZE

### Syntax

`MC_PENDING_REASON_PKG_SIZE=kilobytes | 0`

### Description

MultiCluster job forwarding model only. Pending reason update package size, in KB. Defines the maximum amount of pending reason data this cluster will send to submission clusters in one cycle.

Specify the keyword 0 (zero) to disable the limit and allow any amount of data in one package.

## Default

512

## MC\_PENDING\_REASON\_UPDATE\_INTERVAL

### Syntax

`MC_PENDING_REASON_UPDATE_INTERVAL=seconds | 0`

### Description

MultiCluster job forwarding model only. Pending reason update interval, in seconds. Defines how often this cluster will update submission clusters about the status of pending MultiCluster jobs.

Specify the keyword 0 (zero) to disable pending reason updating between clusters.

## Default

300

## MC\_RECLAIM\_DELAY

### Syntax

`MC_RECLAIM_DELAY=minutes`

## Description

MultiCluster resource leasing model only. The reclaim interval (how often to reconfigure shared leases) in minutes.

Shared leases are defined by Type=shared in the lsb.resources HostExport section.

## Default

10 (minutes)

## MC\_RUSAGE\_UPDATE\_INTERVAL

### Syntax

**MC\_RUSAGE\_UPDATE\_INTERVAL**=*seconds*

## Description

MultiCluster only. Enables resource use updating for MultiCluster jobs running on hosts in the cluster and specifies how often to send updated information to the submission or consumer cluster.

## Default

300

## MIN\_SWITCH\_PERIOD

### Syntax

**MIN\_SWITCH\_PERIOD**=*seconds*

## Description

The minimum period in seconds between event log switches.

Works together with MAX\_JOB\_NUM to control how frequently mbatchd switches the file. mbatchd checks if MAX\_JOB\_NUM has been reached every MIN\_SWITCH\_PERIOD seconds. If mbatchd finds that MAX\_JOB\_NUM has been reached, it switches the events file.

To significantly improve the performance of mbatchd for large clusters, set this parameter to a value equal to or greater than 600. This causes mbatchd to fork a child process that handles event switching, thereby reducing the load on mbatchd. mbatchd terminates the child process and appends delta events to new events after the MIN\_SWITCH\_PERIOD has elapsed.

## Default

0

No minimum period. Log switch frequency is not restricted.

## See also

MAX\_PEND\_JOBS

## NEWJOB\_REFRESH

### Syntax

**NEWJOB\_REFRESH=Y | N**

### Description

Enables a child `mbat chd` to get up to date information about new jobs from the parent `mbat chd`. When set to Y, job queries with `bj obs` display new jobs submitted after the child `mbat chd` was created.

If you have enabled multithreaded `mbatchd` support, the `bj obs` command may not display up-to-date information if two consecutive query commands are issued before a child `mbat chd` expires because child `mbat chd` job information is not updated. Use `NEWJOB_REFRESH=Y` to enable the parent `mbat chd` to push new job information to a child `mbat chd`.

When `NEWJOB_REFRESH=Y`, as users submit new jobs, the parent `mbat chd` pushes the new job event to the child `mbat chd`. The parent `mbat chd` transfers the following kinds of new jobs to the child `mbat chd`:

- Newly submitted jobs
- Restarted jobs
- Remote lease model jobs from the submission cluster
- Remote forwarded jobs from the submission cluster

When `NEWJOB_REFRESH=Y`, you should set `MBD_REFRESH_TIME` to a value greater than 10 seconds.

### Required parameters

`LSB_QUERY_PORT` must be enabled in `lsf.conf`.

### Restrictions

The parent `mbat chd` only pushes the new job event to a child `mbat chd`. The child `mbat chd` is not aware of status changes of existing jobs. The child `mbat chd` will not reflect the results of job control commands (`bmod`, `bmi g`, `bswi t ch`, `bt op`, `bbot`, `brequeue`, `bst op`, `brresume`, and so on) invoked after the child `mbat chd` is created.

### Default

N (Not defined. New jobs are not pushed to the child `mbat chd`.)

### See also

`MBD_REFRESH_TIME`

## NO\_PREEMPT\_FINISH\_TIME

### Syntax

**NO\_PREEMPT\_FINISH\_TIME=*minutes* | *percentage***

## Description

Prevents preemption of jobs that will finish within the specified number of minutes or the specified percentage of the estimated run time or run limit.

Specifies that jobs due to finish within the specified number of minutes or percentage of job duration should not be preempted, where *minutes* is wall-clock time, not normalized time. Percentage must be greater than 0 or less than 100% (between 1% and 99%).

For example, if the job run limit is 60 minutes and NO\_PREEMPT\_FINISH\_TIME=10%, the job cannot be preempted after it running 54 minutes or longer.

If you specify percentage for NO\_PREEMPT\_RUN\_TIME, requires a run time (bsub -W or RUNTIME in lsb. applications), or run limit to be specified for the job (bsub -W, or RUNLIMIT in lsb. queues, or RUNLIMIT in lsb. applications)

## Default

-1 (Not defined.)

## NO\_PREEMPT\_RUN\_TIME

## Syntax

**NO\_PREEMPT\_RUN\_TIME**=*minutes* | *percentage*

## Description

Prevents preemption of jobs that have been running for the specified number of minutes or the specified percentage of the estimated run time or run limit.

Specifies that jobs that have been running for the specified number of minutes or longer should not be preempted, where *minutes* is wall-clock time, not normalized time. Percentage must be greater than 0 or less than 100% (between 1% and 99%).

For example, if the job run limit is 60 minutes and NO\_PREEMPT\_RUN\_TIME=50%, the job cannot be preempted after it running 30 minutes or longer.

If you specify percentage for NO\_PREEMPT\_RUN\_TIME, requires a run time (bsub -W or RUNTIME in lsb. applications), or run limit to be specified for the job (bsub -W, or RUNLIMIT in lsb. queues, or RUNLIMIT in lsb. applications)

## Default

-1 (Not defined.)

## NQS\_QUEUES\_FLAGS

## Syntax

**NQS\_QUEUES\_FLAGS**=*integer*

## Description

For Cray NQS compatibility only. Used by LSF to get the NQS queue information.

If the NQS version on a Cray is NQS 1.1, 80.42 or NQS 71.3, this parameter does not need to be defined.

For other versions of NQS on Cray, define both `NQS_QUEUES_FLAGS` and `NQS_REQUESTS_FLAGS`.

To determine the value of this parameter, run the `NQS qstat` command. The value of `Npk_int [1]` in the output is the value you need for this parameter. Refer to the NQS chapter in *Administering Platform LSF* for more details.

## Default

2147483647 (Not defined.)

## NQS\_REQUESTS\_FLAGS

### Syntax

**NQS\_REQUESTS\_FLAGS**=*integer*

### Description

For Cray NQS compatibility only.

If the NQS version on a Cray is NQS 80.42 or NQS 71.3, this parameter does not need to be defined.

If the version is NQS 1.1 on a Cray, set this parameter to 251918848. This is the is the `qstat` flag that LSF uses to retrieve requests on Cray in long format.

For other versions of NQS on a Cray, run the `NQS qstat` command. The value of `Npk_int [1]` in the output is the value you need for this parameter. Refer to the NQS chapter in *Administering Platform LSF* for more details.

## Default

2147483647 (Not defined.)

## PARALLEL\_SCHED\_BY\_SLOT

### Syntax

**PARALLEL\_SCHED\_BY\_SLOT**=*y* | *Y*

### Description

If defined, LSF schedules jobs based on the number of slots assigned to the hosts instead of the number of CPUs. These slots can be defined by `host in lsb. hosts` or by `slot limit in lsb. resources`.

All slot-related messages still show the word “processors”, but actually refer to “slots” instead. Similarly, all scheduling activities also use slots instead of processors.

## Default

N (Disabled.)

## See also

- `JL/U` and `MXJ` in `lsb. hosts`

- SLOTS and SLOTS\_PER\_PROCESSOR in lsb.resources

## PEND\_REASON\_MAX\_JOBS

### Syntax

**PEND\_REASON\_MAX\_JOBS**=*integer*

### Description

Number of jobs for each user per queue for which pending reasons are calculated by the scheduling daemon mbschd. Pending reasons are calculated at a time period set by PENDING\_REASON\_UPDATE\_INTERVAL.

### Default

20 jobs

## PEND\_REASON\_UPDATE\_INTERVAL

### Syntax

**PEND\_REASON\_UPDATE\_INTERVAL**=*seconds*

### Description

Time interval that defines how often pending reasons are calculated by the scheduling daemon mbschd.

### Default

30 seconds

## PG\_SUSP\_IT

### Syntax

**PG\_SUSP\_IT**=*seconds*

### Description

The time interval that a host should be interactively idle (it > 0) before jobs suspended because of a threshold on the pg load index can be resumed.

This parameter is used to prevent the case in which a batch job is suspended and resumed too often as it raises the paging rate while running and lowers it while suspended. If you are not concerned with the interference with interactive jobs caused by paging, the value of this parameter may be set to 0.

### Default

180 seconds

# PREEMPT\_FOR

## Syntax

```
PREEMPT_FOR=[GROUP_JLP] [GROUP_MAX] [HOST_JLU] [LEAST_RUN_TIME]
[MINI_JOB] [USER_JLP]
```

## Description

If preemptive scheduling is enabled, this parameter is used to disregard suspended jobs when determining if a job slot limit is exceeded, to preempt jobs with the shortest running time, and to optimize preemption of parallel jobs.

Specify one or more of the following keywords. Use spaces to separate multiple keywords.

### GROUP\_JLP

Counts only running jobs when evaluating if a user group is approaching its per-processor job slot limit (SLOTS\_PER\_PROCESSOR, USERS, and PER\_HOST=all in the `lsb.resources` file). Suspended jobs are ignored when this keyword is used.

### GROUP\_MAX

Counts only running jobs when evaluating if a user group is approaching its total job slot limit (SLOTS, PER\_USER=all, and HOSTS in the `lsb.resources` file). Suspended jobs are ignored when this keyword is used. When preemptive scheduling is enabled, suspended jobs never count against the total job slot limit for individual users.

### HOST\_JLU

Counts only running jobs when evaluating if a user or user group is approaching its per-host job slot limit (SLOTS and USERS in the `lsb.resources` file). Suspended jobs are ignored when this keyword is used.

### LEAST\_RUN\_TIME

Preempts the job that has been running for the shortest time. Run time is wall-clock time, not normalized run time.

### MINI\_JOB

Optimizes the preemption of parallel jobs by preempting only enough parallel jobs to start the high-priority parallel job.

### OPTIMAL\_MINI\_JOB

Optimizes preemption of parallel jobs by preempting only low-priority parallel jobs using the least number of slots to allow the high-priority parallel job to start.

User limits and user group limits can interfere with preemption optimization of OPTIMAL\_MINI\_JOB. You should not configure OPTIMAL\_MINI\_JOB if you have user or user group limits configured.

You should configure PARALLEL\_SCHED\_BY\_SLOT=Y when using OPTIMAL\_MINI\_JOB.

### USER\_JLP

Counts only running jobs when evaluating if a user is approaching their per-processor job slot limit (SLOTS\_PER\_PROCESSOR, USERS, and PER\_HOST=all in the `lsb.resources` file). Suspended jobs are ignored when this keyword is used. Ignores suspended jobs when calculating the user-processor job slot limit for individual users. When preemptive scheduling is enabled, suspended jobs never count against the total job slot limit for individual users.

## Default

0 (The parameter is not defined.)

If preemptive scheduling is enabled, more lower-priority parallel jobs may be preempted than necessary to start a high-priority parallel job. Both running and suspended jobs are counted when calculating the number of job slots in use, except for the following limits:

- The total job slot limit for hosts, specified at the host level
- Total job slot limit for individual users, specified at the user level—by default, suspended jobs still count against the limit for user groups

## PREEMPT\_JOBTYPE

### Syntax

**PREEMPT\_JOBTYPE**=[EXCLUSIVE] [BACKFILL]

### Description

If preemptive scheduling is enabled, this parameter enables preemption of exclusive and backfill jobs.

Specify one or both of the following keywords. Separate keywords with a space.

#### EXCLUSIVE

Enables preemption of and preemption by exclusive jobs.

LSB\_DISABLE\_LIMLOCK\_EXCL=Y in `lsf.conf` must also be defined.

#### BACKFILL

Enables preemption of backfill jobs. Jobs from higher priority queues can preempt jobs from backfill queues that are either backfilling reserved job slots or running as normal jobs.

## Default

Not defined. Exclusive and backfill jobs are only preempted if the exclusive low priority job is running on a different host than the one used by the preemptive high priority job.

## PREEMPTABLE\_RESOURCES

### Syntax

**PREEMPTABLE\_RESOURCES**=*resource\_name* ...

## Description

Enables license preemption when preemptive scheduling is enabled (has no effect if `PREEMPTIVE` is not also specified) and specifies the licenses that will be preemption resources. Specify shared numeric resources, static or decreasing, that LSF is configured to release (`RELEASE=Y` in `lsf . shared`, which is the default).

You must also configure LSF preemption actions to make the preempted application releases its licenses. To kill preempted jobs instead of suspending them, set `TERMINATE_WHEN=PREEMPT` in `lsb. queues`, or set `JOB_CONTROLS` in `lsb. queues` and specify `brequeue` as the `SUSPEND` action.

## Default

Not defined (if preemptive scheduling is configured, LSF preempts on job slots only)

## PREEMPTION\_WAIT\_TIME

### Syntax

**PREEMPTION\_WAIT\_TIME=seconds**

## Description

Platform LSF License Scheduler only. You must also specify `PREEMPTABLE_RESOURCES` in `lsb. params`).

The amount of time LSF waits, after preempting jobs, for preemption resources to become available. Specify at least 300 seconds.

If LSF does not get the resources after this time, LSF might preempt more jobs.

## Default

300 (seconds)

## PRIVILEGED\_USER\_FORCE\_BKILL

### Syntax

**PRIVILEGED\_USER\_FORCE\_BKILL=y | Y**

## Description

If Y, only root or the LSF administrator can successfully run `bkill -r`. For any other users, `-r` is ignored. If not defined, any user can run `bkill -r`.

## Default

Not defined.

## REMOTE\_MAX\_PREEEXEC\_RETRY

### Syntax

**REMOTE\_MAX\_PREEEXEC\_RETRY=integer**

## Description

The maximum number of times to attempt the pre-execution command of a job on the remote cluster.

## Valid values

$0 < \text{REMOTE\_MAX\_PREEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in lsf.h.

## Default

5

## RESOURCE\_RESERVE\_PER\_SLOT

### Syntax

**RESOURCE\_RESERVE\_PER\_SLOT=y | Y**

### Description

If Y, mbatchd reserves resources based on job slots instead of per-host.

By default, mbatchd only reserves static resources for parallel jobs on a per-host basis. For example, by default, the command:

```
bsub -n 4 -R "rusage[mem=500]" -q reservation my_job
```

requires the job to reserve 500 MB on each host where the job runs.

Some parallel jobs need to reserve resources based on job slots, rather than by host. In this example, if per-slot reservation is enabled by RESOURCE\_RESERVE\_PER\_SLOT, the job my\_job must reserve 500 MB of memory for each job slot ( $4 \times 500 = 2$  GB) on the host in order to run.

If RESOURCE\_RESERVE\_PER\_SLOT is set, the following command reserves the resource static\_resource on all 4 job slots instead of only 1 on the host where the job runs:

```
bsub -n 4 -R "static_resource > 0 rusage[static_resource=1]" my_job
```

## Default

N (Not defined; reserve resources per-host.)

## RUN\_JOB\_FACTOR

### Syntax

**RUN\_JOB\_FACTOR=number**

### Description

Used only with fairshare scheduling. Job slots weighting factor.

In the calculation of a user's dynamic share priority, this factor determines the relative importance of the number of job slots reserved and in use by a user.

## Default

3.0

## RUN\_TIME\_FACTOR

### Syntax

**RUN\_TIME\_FACTOR**=*number*

### Description

Used only with fairshare scheduling. Run time weighting factor.

In the calculation of a user's dynamic share priority, this factor determines the relative importance of the total run time of a user's running jobs.

## Default

0.7

## SBD\_SLEEP\_TIME

### Syntax

**SBD\_SLEEP\_TIME**=*seconds*

### Description

The interval at which LSF checks the load conditions of each host, to decide whether jobs on the host must be suspended or resumed.

The job-level resource usage information is updated at a maximum frequency of every SBD\_SLEEP\_TIME seconds.

The update is done only if the value for the CPU time, resident memory usage, or virtual memory usage has changed by more than 10 percent from the previous update or if a new process or process group has been created.

## Default

SBD\_SLEEP\_TIME is set at installation to 15 seconds. If not defined, 30 seconds.

## SCHED\_METRIC\_ENABLE

### Syntax

**SCHED\_METRIC\_ENABLE**=Y | N

### Description

Enable scheduler performance metric collection.

Use `badmi n perfmon stop` and `badmi n perfmon start` to dynamically control performance metric collection.

lsb.params

The update is done only if the value for the CPU time, resident memory usage, or virtual memory usage has changed by more than 10 percent from the previous update or if a new process or process group has been created.

## Default

N

## SCHED\_METRIC\_SAMPLE\_PERIOD

### Syntax

**SCHED\_METRIC\_SAMPLE\_PERIOD=seconds**

### Description

Set a default performance metric sampling period in seconds.

Cannot be less than 60 seconds.

Use `badmi n perfmon setperiod` to dynamically change performance metric sampling period.

## Default

60 seconds

## SLA\_TIMER

### Syntax

**SLA\_TIMER=seconds**

### Description

For EGO-enabled SLA scheduling. Controls how often each service class is evaluated and a network message is sent to EGO communicating host demand.

### Valid values

Positive integer between 2 and 21474847

## Default

0 (Not defined.)

## SUB\_TRY\_INTERVAL

### Syntax

**SUB\_TRY\_INTERVAL=integer**

### Description

The number of seconds for the requesting client to wait before resubmitting a job. This is sent by `mbatchd` to the client.

## Default

60 seconds

## See also

MAX\_PEND\_JOBS

## SYSTEM\_MAPPING\_ACCOUNT

### Syntax

**SYSTEM\_MAPPING\_ACCOUNT**=*user\_account*

### Description

Enables Windows workgroup account mapping, which allows LSF administrators to map all Windows workgroup users to a single Windows system account, eliminating the need to create multiple users and passwords in LSF. Users can submit and run jobs using their local user names and passwords, and LSF runs the jobs using the mapped system account name and password. With Windows workgroup account mapping, all users have the same permissions because all users map to the same system account.

To specify the user account, include the domain name in uppercase letters (*DOMAIN\_NAME \user\_name*).

Define this parameter for LSF Windows Workgroup installations only.

## Default

Not defined

## USE\_SUSP\_SLOTS

### Syntax

**USE\_SUSP\_SLOTS**=Y | N

### Description

If **USE\_SUSP\_SLOTS**=Y, allows jobs from a low priority queue to use slots held by suspended jobs in a high priority queue, which has a preemption relation with the low priority queue.

Set **USE\_SUSP\_SLOTS**=N to prevent low priority jobs from using slots held by suspended jobs in a high priority queue, which has a preemption relation with the low priority queue.

## Default

Y

## Automatic time-based configuration

Variable configuration is used to automatically change LSF configuration based on time windows. You define automatic configuration changes in `lsb.params` by using if-else constructs and time expressions. After you change the files, reconfigure the cluster with the `badmi n reconfi g` command.

The expressions are evaluated by LSF every 10 minutes based on mbatchd start time. When an expression evaluates true, LSF dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting mbatchd, providing continuous system availability.

## Example

```
# if 18:30-19:30 is your short job express period, but
# you want all jobs going to the short queue by default
# and be subject to the thresholds of that queue

# for all other hours, normal is the default queue

#if time(18:30-19:30)
DEFAULT_QUEUE=short
#else
DEFAULT_QUEUE=normal
#endif
```

# lsb.queues

The `lsb.queues` file defines batch queues. Numerous controls are available at the queue level to allow cluster administrators to customize site policies.

This file is optional; if no queues are configured, LSF creates a queue named `default`, with all parameters set to default values.

This file is installed by default in `LSB_CONFDIR/cluster_name/confidir`.

## Changing lsb.queues configuration

After making any changes to `lsb.queues`, run `badmi n reconfi g` to reconfigure `mbatchd`.

Some parameters such as `run window` and `run time limit` do not take effect immediately for running jobs unless you run `mbatchd restart` or `sbatchd restart` on the job execution host.

## lsb.queues structure

Each queue definition begins with the line `Begin Queue` and ends with the line `End Queue`. The queue name must be specified; all other parameters are optional.

## Parameters

- ADMINISTRATORS
- APS\_PRIORITY
- BACKFILL
- CHKPNT
- CHUNK\_JOB\_SIZE
- CORELIMIT
- CPULIMIT
- DATALIMIT
- DEFAULT\_EXTSCHED
- DEFAULT\_HOST\_SPEC
- DESCRIPTION
- DISPATCH\_ORDER
- DISPATCH\_WINDOW
- EXCLUSIVE
- FAIRSHARE
- FAIRSHARE\_QUEUES
- FILELIMIT
- HJOB\_LIMIT
- HOSTS
- IGNORE\_DEADLINE
- IMPT\_JOBKLG
- INTERACTIVE
- INTERRUPTIBLE\_BACKFILL
- JOB\_ACCEPT\_INTERVAL
- JOB\_ACTION\_WARNING\_TIME
- JOB\_CONTROLS

## lsb.queues

- JOB\_IDLE
- JOB\_OVERRUN
- JOB\_STARTER
- JOB\_UNDERRUN
- JOB\_WARNING\_ACTION
- load\_index
- LOCAL\_MAX\_PREEEXEC\_RETRY
- MANDATORY\_EXTSCHED
- MAX\_JOB\_PREEMPT
- MAX\_JOB\_REQUEUE
- MAX\_PREEEXEC\_RETRY
- MAX\_RSCHED\_TIME
- MEMLIMIT
- MIG
- NEW\_JOB\_SCHED\_DELAY
- NICE
- NQS\_QUEUES
- PJOB\_LIMIT
- POST\_EXEC
- PRE\_EXEC
- PREEMPTION
- PRIORITY
- PROCESSLIMIT
- PROCLIMIT
- QJOB\_LIMIT
- QUEUE\_GROUP
- QUEUE\_NAME
- RCVJOBS\_FROM
- REMOTE\_MAX\_PREEEXEC\_RETRY
- REQUEUE\_EXIT\_VALUES
- RERUNNABLE
- RESOURCE\_RESERVE
- RES\_REQ
- RESUME\_COND
- RUN\_WINDOW
- RUNLIMIT
- SLOT\_POOL
- SLOT\_RESERVE
- SLOT\_SHARE
- SNDJOBS\_TO
- STACKLIMIT
- STOP\_COND
- SWAPLIMIT
- THREADLIMIT
- UJOB\_LIMIT
- USE\_PAM\_CREDS

- USERS

## ADMINISTRATORS

### Syntax

**ADMINISTRATORS**=*user\_name* | *user\_group* ...

### Description

List of queue administrators. To specify a Windows user account or user group, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name* or *DOMAIN\_NAME\user\_group*).

Queue administrators can perform operations on any user's job in the queue, as well as on the queue itself.

### Default

Not defined. You must be a cluster administrator to operate on this queue.

## APS\_PRIORITY

### Syntax

**APS\_PRIORITY**=**WEIGHT**[[*factor*, *value*] [*subfactor*, *value*]......] **LIMIT**[[*factor*, *value*] [*subfactor*, *value*]......] **GRACE\_PERIOD**[[*factor*, *value*] [*subfactor*, *value*]......]

### Description

Specifies calculation factors for absolute priority scheduling (APS). Pending jobs in the queue are ordered according to the calculated APS value.

If weight of a subfactor is defined, but the weight of parent factor is not defined, the parent factor weight is set as 1.

The WEIGHT and LIMIT factors are floating-point values. Specify a *value* for GRACE\_PERIOD in seconds (*values*), minutes (*valuem*), or hours (*valueh*).

The default unit for grace period is hours.

For example, the following sets a grace period of 10 hours for the MEM factor, 10 minutes for the JPRIORITY factor, 10 seconds for the QPRIORITY factor, and 10 hours (default) for the RSRC factor:

```
GRACE_PERIOD[ [MEM, 10h] [JPRIORITY, 10m] [QPRIORITY, 10s] [RSRC, 10] ]
```

You cannot specify zero (0) for the WEIGHT, LIMIT, and GRACE\_PERIOD of any factor or subfactor.

APS queues cannot configure cross-queue fairshare (FAIRSHARE\_QUEUES). The QUEUE\_GROUP parameter replaces FAIRSHARE\_QUEUES, which is obsolete in LSF 7.0.

Suspended (bst op) jobs and migrated jobs (bmi g) are always scheduled before pending jobs. For migrated jobs, LSF keeps the existing job priority information.

If LSB\_REQUEUE\_TO\_BOTTOM and LSB\_MIG2PEND are configured in `lsf.conf`, the migrated jobs keep their APS information. When LSB\_REQUEUE\_TO\_BOTTOM and LSB\_MIG2PEND are configured, the migrated jobs need to compete with other pending jobs

based on the APS value. If you want to reset the APS value, the you should use `brequeue`, not `bmi g`.

## Default

Not defined

## BACKFILL

### Syntax

**BACKFILL=Y | N**

### Description

If Y, enables backfill scheduling for the queue.

A possible conflict exists if BACKFILL and PREEMPTION are specified together. If `PREEMPT_JOBTYPE = BACKFILL` is set in the `lsb.params` file, a backfill queue can be preemptable. Otherwise a backfill queue cannot be preemptable. If BACKFILL is enabled do not also specify `PREEMPTION = PREEMPTABLE`.

BACKFILL is required for interruptible backfill queues (`INTERRUPTIBLE_BACKFILL=seconds`).

## Default

Not defined. No backfilling.

## CHKPNT

### Syntax

**CHKPNT=chkpnt\_dir [chkpnt\_period]**

### Description

Enables automatic checkpointing for the queue. All jobs submitted to the queue are checkpointable.

The checkpoint directory is the directory where the checkpoint files are created. Specify an absolute path or a path relative to CWD, do not use environment variables.

Specify the optional checkpoint period in minutes.

Only running members of a chunk job can be checkpointed.

If checkpoint-related configuration is specified in both the queue and an application profile, the application profile setting overrides queue level configuration.

If checkpoint-related configuration is specified in the queue, application profile, and at job level:

- Application-level and job-level parameters are merged. If the same parameter is defined at both job-level and in the application profile, the job-level value overrides the application profile value.
- The merged result of job-level and application profile settings override queue-level configuration.

To enable checkpointing of MultiCluster jobs, define a checkpoint directory in both the send-jobs and receive-jobs queues (CHKPNT in `lsb.queues`), or in an application profile (CHKPNT\_DIR, CHKPNT\_PERIOD, CHKPNT\_INITPERIOD, CHKPNT\_METHOD in `lsb.applications`) of both submission cluster and execution cluster. LSF uses the directory specified in the execution cluster.

To make a MultiCluster job checkpointable, both submission and execution queues must enable checkpointing, and the application profile or queue setting on the execution cluster determines the checkpoint directory. Checkpointing is not supported if a job runs on a leased host.

The file path of the checkpoint directory can contain up to 4000 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory and file name.

## Default

Not defined

## CHUNK\_JOB\_SIZE

## Syntax

**CHUNK\_JOB\_SIZE=integer**

## Description

Chunk jobs only. Enables job chunking and specifies the maximum number of jobs allowed to be dispatched together in a chunk. Specify a positive integer greater than 1.

The ideal candidates for job chunking are jobs that have the same host and resource requirements and typically take 1 to 2 minutes to run.

Job chunking can have the following advantages:

- Reduces communication between sbatchd and mbatchd and reduces scheduling overhead in mbschd.
- Increases job throughput in mbatchd and CPU utilization on the execution hosts.

However, throughput can deteriorate if the chunk job size is too big. Performance may decrease on queues with CHUNK\_JOB\_SIZE greater than 30. You should evaluate the chunk job size on your own systems for best performance.

With MultiCluster job forwarding model, this parameter does not affect MultiCluster jobs that are forwarded to a remote cluster.

## Compatibility

This parameter is ignored in the following kinds of queues and applications:

- Interactive (INTERACTIVE=ONLY parameter)
- CPU limit greater than 30 minutes (CPULIMIT parameter)
- Run limit greater than 30 minutes (RUNLIMIT parameter)
- Runtime estimate greater than 30 minutes (RUNTIME parameter in `lsb.applications` only)

If CHUNK\_JOB\_DURATION is set in `lsb.params`, chunk jobs are accepted regardless of the value of CPULIMIT, RUNLIMIT or RUNTIME.

## Example

The following configures a queue named `chunk`, which dispatches up to 4 jobs in a chunk:

```

Begin Queue
QUEUE_NAME      = chunk
PRIORITY        = 50
CHUNK_JOB_SIZE  = 4
End Queue

```

## Default

Not defined

## CORELIMIT

### Syntax

**CORELIMIT**=*integer*

### Description

The per-process (hard) core file size limit (in KB) for all of the processes belonging to a job from this queue (see `getrlimit(2)`).

## Default

Unlimited

## CPULIMIT

### Syntax

**CPULIMIT**=[*default\_limit*] *maximum\_limit*

where *default\_limit* and *maximum\_limit* are:

[*hour*:]*minute*[/*host\_name* | /*host\_model*]

### Description

Maximum normalized CPU time and optionally, the default normalized CPU time allowed for all processes of a job running in this queue. The name of a host or host model specifies the CPU time normalization host to use.

Limits the total CPU time the job can use. This parameter is useful for preventing runaway jobs or jobs that use up too many resources.

When the total CPU time for the whole job has reached the limit, a SIGXCPU signal is sent to all processes belonging to the job. If the job has no signal handler for SIGXCPU, the job is killed immediately. If the SIGXCPU signal is handled, blocked, or ignored by the application, then after the grace period expires, LSF sends SIGINT, SIGTERM, and SIGKILL to the job to kill it.

If a job dynamically spawns processes, the CPU time used by these processes is accumulated over the life of the job.

Processes that exist for fewer than 30 seconds may be ignored.

By default, if a default CPU limit is specified, jobs submitted to the queue without a job-level CPU limit are killed when the default CPU limit is reached.

If you specify only one limit, it is the maximum, or hard, CPU limit. If you specify two limits, the first one is the default, or soft, CPU limit, and the second one is the maximum CPU limit. The number of minutes may be greater than 59. Therefore, three and a half hours can be specified either as 3:30 or 210.

If no host or host model is given with the CPU time, LSF uses the default CPU time normalization host defined at the queue level (DEFAULT\_HOST\_SPEC in `lsb.queues`) if it has been configured, otherwise uses the default CPU time normalization host defined at the cluster level (DEFAULT\_HOST\_SPEC in `lsb.params`) if it has been configured, otherwise uses the host with the largest CPU factor (the fastest host in the cluster).

On Windows, a job that runs under a CPU time limit may exceed that limit by up to SBD\_SLEEP\_TIME. This is because sbatchd periodically checks if the limit has been exceeded.

On UNIX systems, the CPU limit can be enforced by the operating system at the process level.

You can define whether the CPU limit is a per-process limit enforced by the OS or a per-job limit enforced by LSF with LSB\_JOB\_CPULIMIT in `lsf.conf`.

Jobs submitted to a chunk job queue are not chunked if CPULIMIT is greater than 30 minutes.

## Default

Unlimited

## DATALIMIT

### Syntax

**DATALIMIT**=[*default\_limit*] *maximum\_limit*

### Description

The per-process data segment size limit (in KB) for all of the processes belonging to a job from this queue (see `getrlimit(2)`).

By default, if a default data limit is specified, jobs submitted to the queue without a job-level data limit are killed when the default data limit is reached.

If you specify only one limit, it is the maximum, or hard, data limit. If you specify two limits, the first one is the default, or soft, data limit, and the second one is the maximum data limit

## Default

Unlimited

## DEFAULT\_EXTSCHED

### Syntax

**DEFAULT\_EXTSCHED**=*external\_scheduler\_options*

### Description

Specifies default external scheduling options for the queue.

-extsched options on the bsub command are merged with DEFAULT\_EXTSCHEDED options, and -extsched options override any conflicting queue-level options set by DEFAULT\_EXTSCHEDED.

## Default

Not defined

## DEFAULT\_HOST\_SPEC

### Syntax

**DEFAULT\_HOST\_SPEC**=*host\_name / host\_model*

### Description

The default CPU time normalization host for the queue.

The CPU factor of the specified host or host model is used to normalize the CPU time limit of all jobs in the queue, unless the CPU time normalization host is specified at the job level.

## Default

Not defined. The queue uses the DEFAULT\_HOST\_SPEC defined in lsb.params. If DEFAULT\_HOST\_SPEC is not defined in either file, LSF uses the fastest host in the cluster.

## DESCRIPTION

### Syntax

**DESCRIPTION**=*text*

### Description

Description of the job queue displayed by bqueues -l.

This description should clearly describe the service features of this queue, to help users select the proper queue for each job.

The text can include any characters, including white space. The text can be extended to multiple lines by ending the preceding line with a backslash (\). The maximum length for the text is 512 characters.

## DISPATCH\_ORDER

### Syntax

**DISPATCH\_ORDER**=**QUEUE**

### Description

Defines an *ordered* cross-queue fairshare set. DISPATCH\_ORDER indicates that jobs are dispatched according to the order of queue priorities first, then user fairshare priority.

By default, a user has the same priority across the master and slave queues. If the same user submits several jobs to these queues, user priority is calculated by taking into account all the jobs the user has submitted across the master-slave set.

If DISPATCH\_ORDER=QUEUE is set in the master queue, jobs are dispatched according to queue priorities first, then user priority. Jobs from users with lower fairshare priorities who have pending jobs in higher priority queues are dispatched before jobs in lower priority queues. This avoids having users with higher fairshare priority getting jobs dispatched from low-priority queues.

Jobs in queues having the same priority are dispatched according to user priority.

Queues that are not part of the cross-queue fairshare can have any priority; they are not limited to fall outside of the priority range of cross-queue fairshare queues.

## Default

Not defined

## DISPATCH\_WINDOW

### Syntax

**DISPATCH\_WINDOW**=*time\_window* ...

### Description

The time windows in which jobs from this queue are dispatched. Once dispatched, jobs are no longer affected by the dispatch window.

## Default

Not defined. Dispatch window is always open.

## EXCLUSIVE

### Syntax

**EXCLUSIVE**=Y | N | CU[*cu\_type*]

### Description

If Y, specifies an exclusive queue.

If CU, CU[], or CU[*cu\_type*], specifies an exclusive queue as well as a queue exclusive to compute units of type *cu\_type* (as defined in lsb.params). If no type is specified, the default compute unit type is used.

Jobs submitted to an exclusive queue with `bsub -x` are only dispatched to a host that has no other LSF jobs running. Jobs submitted to a compute unit exclusive queue with `bsub -R "cu [excl]"` only run on a compute unit that has no other jobs running.

For hosts shared under the MultiCluster resource leasing model, jobs are not dispatched to a host that has LSF jobs running, even if the jobs are from another cluster.

## Default

N

# FAIRSHARE

## Syntax

**FAIRSHARE=USER\_SHARES***[[user, number\_shares] ...]*

- Specify at least one user share assignment.
- Enclose the list in square brackets, as shown.
- Enclose each user share assignment in square brackets, as shown.
- *user*: Specify users who are also configured to use queue. You can assign the shares to:
  - A single user (specify *user\_name*). To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name*).
  - Users in a group, individually (specify *group\_name@*) or collectively (specify *group\_name*). To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAMEgroup\_name*).
  - Users not included in any other share assignment, individually (specify the keyword *default*) or collectively (specify the keyword *others*)
    - By default, when resources are assigned collectively to a group, the group members compete for the resources on a first-come, first-served (FCFS) basis. You can use hierarchical fairshare to further divide the shares among the group members.
    - When resources are assigned to members of a group individually, the share assignment is recursive. Members of the group and of all subgroups always compete for the resources according to FCFS scheduling, regardless of hierarchical fairshare policies.
- *number\_shares*
  - Specify a positive integer representing the number of shares of the cluster resources assigned to the user.
  - The number of shares assigned to each user is only meaningful when you compare it to the shares assigned to other users or to the total number of shares. The total number of shares is just the sum of all the shares assigned in each share assignment.

## Description

Enables queue-level user-based fairshare and specifies share assignments. Only users with share assignments can submit jobs to the queue.

## Compatibility

Do not configure hosts in a cluster to use fairshare at both queue and host levels. However, you can configure user-based fairshare and queue-based fairshare together.

## Default

Not defined. No fairshare.

# FAIRSHARE\_QUEUES

## Syntax

**FAIRSHARE\_QUEUES**=*queue\_name**[queue\_name ...]*

## Description

Defines cross-queue fairshare. When this parameter is defined:

- The queue in which this parameter is defined becomes the “*master queue*”.
- Queues listed with this parameter are “*slave queues*” and inherit the fairshare policy of the master queue.
- A user has the same priority across the master and slave queues. If the same user submits several jobs to these queues, user priority is calculated by taking into account all the jobs the user has submitted across the master-slave set.

## Notes

- By default, the PRIORITY range defined for queues in cross-queue fairshare cannot be used with any other queues. For example, you have 4 queues: queue1, queue2, queue3, queue4. You configure cross-queue fairshare for queue1, queue2, queue3 and assign priorities of 30, 40, 50 respectively.
- By default, the priority of queue4 (which is not part of the cross-queue fairshare) cannot fall between the priority range of the cross-queue fairshare queues (30-50). It can be any number up to 29 or higher than 50. It does not matter if queue4 is a fairshare queue or FCFS queue. If DISPATCH\_ORDER=QUEUE is set in the master queue, the priority of queue4 (which is not part of the cross-queue fairshare) can be any number, including a priority falling between the priority range of the cross-queue fairshare queues (30-50).
- FAIRSHARE must be defined in the master queue. If it is also defined in the queues listed in FAIRSHARE\_QUEUES, it is ignored.
- Cross-queue fairshare can be defined more than once within lsb. queues. You can define several sets of master-slave queues. However, a queue cannot belong to more than one master-slave set. For example, you can define:
  - In queue normal : FAIRSHARE\_QUEUES=short license
  - In queue priority: FAIRSHARE\_QUEUES=night owners

### Restriction:

You cannot, however, define night, owners, or priority as slaves in the queue normal; or normal, short and license as slaves in the priority queue; or short, license, night, owners as master queues of their own.

- Cross-queue fairshare cannot be used with host partition fairshare. It is part of queue-level fairshare.
- Cross-queue fairshare cannot be used with absolute priority scheduling.

## Default

Not defined

## FILELIMIT

## Syntax

**FILELIMIT**=*integer*

## Description

The per-process (hard) file size limit (in KB) for all of the processes belonging to a job from this queue (see `getrlimit(2)`).

## Default

Unlimited

## HJOB\_LIMIT

## Syntax

**HJOB\_LIMIT**=*integer*

## Description

Per-host job slot limit.

Maximum number of job slots that this queue can use on any host. This limit is configured per host, regardless of the number of processors it may have.

This may be useful if the queue dispatches jobs that require a node-locked license. If there is only one node-locked license per host then the system should not dispatch more than one job to the host even if it is a multiprocessor host.

## Example

The following runs a maximum of one job on each of host A, host B, and host C:

```

Begin Queue
...
HJOB_LIMIT = 1
HOSTS=hostA hostB hostC
...
End Queue

```

## Default

Unlimited

## HOSTS

## Syntax

**HOSTS**=*host\_list* | **none**

- *host\_list* is a space-separated list of the following items:
  - *host\_name*[@*cluster\_name*][[!] | +*pref\_level*]
  - *host\_partition*[+*pref\_level*]
  - *host\_group*[[!] | +*pref\_level*]
  - *compute\_unit*[[!] | +*pref\_level*]
  - [~]*host\_name*
  - [~]*host\_group*
  - [~]*compute\_unit*

- The list can include the following items only once:
  - `all@cluster_name`
  - `others[+pref_level]`
  - `all`
  - `allremote`
- The `none` keyword is only used with the MultiCluster job forwarding model, to specify a remote-only queue.

## Description

A space-separated list of hosts on which jobs from this queue can be run.

If compute units, host groups, or host partitions are included in the list, the job can run on any host in the unit, group, or partition. All the members of the host list should either belong to a single host partition or not belong to any host partition. Otherwise, job scheduling may be affected.

Some items can be followed by a plus sign (+) and a positive number to indicate the preference for dispatching a job to that host. A higher number indicates a higher preference. If a host preference is not given, it is assumed to be 0. If there are multiple candidate hosts, LSF dispatches the job to the host with the highest preference; hosts at the same level of preference are ordered by load.

If compute units, host groups, or host partitions are assigned a preference, each host in the unit, group, or partition has the same preference.

Use the keyword `others` to include all hosts not explicitly listed.

Use the keyword `all` to include all hosts not explicitly excluded.

Use the keyword `all@cluster_name hostgroup_name` or `allremote hostgroup_name` to include lease in hosts.

Use the not operator (~) to exclude hosts from the all specification in the queue. This is useful if you have a large cluster but only want to exclude a few hosts from the queue definition.

The not operator can only be used with the `all` keyword. It is *not* valid with the keywords `others` and `none`.

The not operator (~) can be used to exclude host groups.

For parallel jobs, specify first execution host candidates when you want to ensure that a host has the required resources or runtime environment to handle processes that run on the first execution host.

To specify one or more hosts, host groups, or compute units as first execution host candidates, add the exclamation point (!) symbol after the name.

Follow these guidelines when you specify first execution host candidates:

- If you specify a compute unit or host group, you must first define the unit or group in the file `lsb.hosts`.
- Do not specify a dynamic host group as a first execution host.
- Do not specify "all," "allremote," or "others," or a host partition as a first execution host.
- Do not specify a preference (+) for a host identified by (!) as a first execution host candidate.
- For each parallel job, specify enough regular hosts to satisfy the CPU requirement for the job. Once LSF selects a first execution host for the current job, the other first execution host candidates

- Become unavailable to the current job
- Remain available to other jobs as either regular or first execution hosts
- You cannot specify first execution host candidates when you use the brun command.

---

**Restriction:**

If you have enabled EGO, host groups and compute units are not honored.

---

With MultiCluster resource leasing model, use the format *host\_name@cluster\_name* to specify a borrowed host. LSF does not validate the names of remote hosts. The keyword *others* indicates all local hosts not explicitly listed. The keyword *all* indicates all local hosts not explicitly excluded. Use the keyword *allremote* to specify all hosts borrowed from all remote clusters. Use *al l@cluster\_name* to specify the group of all hosts borrowed from one remote cluster. You cannot specify a host group or partition that includes remote resources, unless it uses the keyword *allremote* to include all remote hosts. You cannot specify a compute unit that includes remote resources.

With MultiCluster resource leasing model, the not operator (~) can be used to exclude local hosts or host groups. You cannot use the not operator (~) with remote hosts.

---

**Restriction:**

Hosts that participate in queue-based fairshare cannot be in a host partition.

---

## Behavior with host intersection

Host preferences specified by `bsub -m` combine intelligently with the queue specification and advance reservation hosts. The jobs run on the hosts that are both specified at job submission and belong to the queue or have advance reservation.

### Example 1

```
HOSTS=hostA+1 hostB hostC+1 hostD+3
```

This example defines three levels of preferences: run jobs on `hostD` as much as possible, otherwise run on either `hostA` or `hostC` if possible, otherwise run on `hostB`. Jobs should not run on `hostB` unless all other hosts are too busy to accept more jobs.

### Example 2

```
HOSTS=hostD+1 others
```

Run jobs on `hostD` as much as possible, otherwise run jobs on the least-loaded host available.

With MultiCluster resource leasing model, this queue does not use borrowed hosts.

### Example 3

```
HOSTS=all ~hostA
```

Run jobs on all hosts in the cluster, except for `hostA`.

With MultiCluster resource leasing model, this queue does not use borrowed hosts.

## Example 4

```
HOSTS=Group1 ~hostA hostB hostC
```

Run jobs on hostB, hostC, and all hosts in Group1 except for hostA.

With MultiCluster resource leasing model, this queue uses borrowed hosts if Group1 uses the keyword allremote.

## Example 5

```
HOSTS=hostA! hostB+ hostC hostgroup1!
```

Runs parallel jobs using either hostA or a host defined in hostgroup1 as the first execution host. If the first execution host cannot run the entire job due to resource requirements, runs the rest of the job on hostB. If hostB is too busy to accept the job, or if hostB does not have enough resources to run the entire job, runs the rest of the job on hostC.

## Example 6

```
HOSTS=computeunit1! hostB hostC
```

Runs parallel jobs using a host in computeunit1 as the first execution host. If the first execution host cannot run the entire job due to resource requirements, runs the rest of the job on other hosts in computeunit1 followed by hostB and finally hostC.

## Example 7

```
HOSTS=hostgroup1! computeunitA computeunitB computeunitC
```

Runs parallel jobs using a host in hostgroup1 as the first execution host. If additional hosts are required, runs the rest of the job on other hosts in the same compute unit as the first execution host, followed by hosts in the remaining compute units in the order they are defined in the lsb.hosts ComputeUnit section.

## Default

all (the queue can use all hosts in the cluster, and every host has equal preference)

With MultiCluster resource leasing model, this queue can use all local hosts, but no borrowed hosts.

## IGNORE\_DEADLINE

### Syntax

```
IGNORE_DEADLINE=Y
```

### Description

If Y, disables deadline constraint scheduling (starts all jobs regardless of deadline constraints).

## IMPT\_JOBKLG

### Syntax

```
IMPT_JOBKLG=integer | infinite
```

## Description

MultiCluster job forwarding model only. Specifies the MultiCluster pending job limit for a receive-jobs queue. This represents the maximum number of MultiCluster jobs that can be pending in the queue; once the limit has been reached, the queue stops accepting jobs from remote clusters.

Use the keyword `infinite` to make the queue accept an unlimited number of pending MultiCluster jobs.

## Default

50

## INTERACTIVE

## Syntax

**INTERACTIVE=**YES | NO | ONLY

## Description

YES causes the queue to accept both interactive and non-interactive batch jobs, NO causes the queue to reject interactive batch jobs, and ONLY causes the queue to accept interactive batch jobs and reject non-interactive batch jobs.

Interactive batch jobs are submitted via `bsub -I`.

## Default

YES. The queue accepts both interactive and non-interactive jobs.

## INTERRUPTIBLE\_BACKFILL

## Syntax

**INTERRUPTIBLE\_BACKFILL=***seconds*

## Description

Configures interruptible backfill scheduling policy, which allows reserved job slots to be used by low priority small jobs that are terminated when the higher priority large jobs are about to start.

There can only be one interruptible backfill queue. It should be the lowest priority queue in the cluster.

Specify the minimum number of seconds for the job to be considered for backfilling. This minimal time slice depends on the specific job properties; it must be longer than at least one useful iteration of the job. Multiple queues may be created if a site has jobs of distinctively different classes.

An interruptible backfill job:

- Starts as a regular job and is killed when it exceeds the queue runtime limit, or
- Is started for backfill whenever there is a backfill time slice longer than the specified minimal time, and killed before the slot-reservation job is about to start

The queue RUNLIMIT corresponds to a maximum time slice for backfill, and should be configured so that the wait period for the new jobs submitted to the queue is acceptable to users. 10 minutes of runtime is a common value.

You should configure REQUEUE\_EXIT\_VALUES for interruptible backfill queues.

BACKFILL and RUNLIMIT must be configured in the queue. The queue is disabled if BACKFILL and RUNLIMIT are not configured.

## Assumptions and limitations:

- The interruptible backfill job holds the slot-reserving job start until its calculated start time, in the same way as a regular backfill job. The interruptible backfill job are not preempted in any way other than being killed when its time come.
- While the queue is checked for the consistency of interruptible backfill, backfill and runtime specifications, the requeue exit value clause is not verified, nor executed automatically. Configure requeue exit values according to your site policies.
- The interruptible backfill job must be able to do at least one unit of useful calculations and save its data within the minimal time slice, and be able to continue its calculations after it has been restarted
- Interruptible backfill paradigm does not explicitly prohibit running parallel jobs, distributed across multiple nodes; however, the chance of success of such job is close to zero.

## Default

Not defined. No interruptible backfilling.

## JOB\_ACCEPT\_INTERVAL

### Syntax

**JOB\_ACCEPT\_INTERVAL**=*integer*

### Description

The number you specify is multiplied by the value of l sb. params MBD\_SLEEP\_TIME (60 seconds by default). The result of the calculation is the number of seconds to wait after dispatching a job to a host, before dispatching a second job to the same host.

If 0 (zero), a host may accept more than one job in each dispatch turn. By default, there is no limit to the total number of jobs that can run on a host, so if this parameter is set to 0, a very large number of jobs might be dispatched to a host all at once. This can overload your system to the point that it is unable to create any more processes. It is not recommended to set this parameter to 0.

JOB\_ACCEPT\_INTERVAL set at the queue level (l sb. queues) overrides JOB\_ACCEPT\_INTERVAL set at the cluster level (l sb. params).

## Default

Not defined. The queue uses JOB\_ACCEPT\_INTERVAL defined in l sb. params, which has a default value of 1.

## JOB\_ACTION\_WARNING\_TIME

### Syntax

**JOB\_ACTION\_WARNING\_TIME**=[*hour*:]*minute*

### Description

Specifies the amount of time before a job control action occurs that a job warning action is to be taken. For example, 2 minutes before the job reaches runtime limit or termination deadline, or the queue's run window is closed, an URG signal is sent to the job.

Job action warning time is not normalized.

A job action warning time must be specified with a job warning action in order for job warning to take effect.

The warning time specified by the `bsub -wt` option overrides `JOB_ACTION_WARNING_TIME` in the queue. `JOB_ACTION_WARNING_TIME` is used as the default when no command line option is specified.

### Example

`JOB_ACTION_WARNING_TIME=2`

### Default

Not defined

## JOB\_CONTROLS

### Syntax

**JOB\_CONTROLS**=**SUSPEND**[*signal* | *command*] **CHKPNT** **RESUME**[*signal* | *command*]  
**TERMINATE**[*signal* | *command*] **CHKPNT**

- *signal* is a UNIX signal name (for example, SIGTSTP or SIGTERM). The specified signal is sent to the job. The same set of signals is not supported on all UNIX systems. To display a list of the symbolic names of the signals (without the SIG prefix) supported on your system, use the `kill -l` command.
- *command* specifies a `/bin/sh` command line to be invoked.

---

#### Restriction:

Do not quote the command line inside an action definition. Do not specify a signal followed by an action that triggers the same signal. For example, do not specify

`JOB_CONTROLS=TERMINATE[ bkill ]` or

`JOB_CONTROLS=TERMINATE[ bqueue ]`. This causes a deadlock between the signal and the action.

- **CHKPNT** is a special action, which causes the system to checkpoint the job. Only valid for **SUSPEND** and **TERMINATE** actions:
  - If the **SUSPEND** action is **CHKPNT**, the job is checkpointed and then stopped by sending the SIGSTOP signal to the job automatically.

- If the TERMINATE action is CHKPNT, then the job is checkpointed and killed automatically.

## Description

Changes the behavior of the SUSPEND, RESUME, and TERMINATE actions in LSF.

- The contents of the configuration line for the action are run with `/bin/sh -c` so you can use shell features in the command.
- The standard input, output, and error of the command are redirected to the NULL device, so you cannot tell directly whether the command runs correctly. The default null device on UNIX is `/dev/null`.
- The command is run as the user of the job.
- All environment variables set for the job are also set for the command action. The following additional environment variables are set:
  - LSB\_JOBPGIDS: a list of current process group IDs of the job
  - LSB\_JOBPI DS: a list of current process IDs of the job
- For the SUSPEND action command, the following environment variables are also set:
  - LSB\_SUSP\_REASONS : an integer representing a bitmap of suspending reasons as defined in `lsbat ch. h`. The suspending reason can allow the command to take different actions based on the reason for suspending the job.
  - LSB\_SUSP\_SUBREASONS : an integer representing the load index that caused the job to be suspended. When the suspending reason SUSP\_LOAD\_REASON (suspended by load) is set in LSB\_SUSP\_REASONS, LSB\_SUSP\_SUBREASONS set to one of the load index values defined in `lsf . h`. Use LSB\_SUSP\_REASONS and LSB\_SUSP\_SUBREASONS together in your custom job control to determine the exact load threshold that caused a job to be suspended.
- If an additional action is necessary for the SUSPEND command, that action should also send the appropriate signal to the application. Otherwise, a job can continue to run even after being suspended by LSF. For example, `JOB_CONTROLS=SUSPEND[ kill SLSB_JOBPI DS: command]`
- If you set preemption with the signal SIGTSTP you use Platform License Scheduler, define `LIC_SCHED_PREEMPT_STOP=Y` in `lsf . conf` for License Scheduler preemption to work.

## Default

On UNIX, by default, SUSPEND sends SIGTSTP for parallel or interactive jobs and SIGSTOP for other jobs. RESUME sends SIGCONT. TERMINATE sends SIGINT, SIGTERM and SIGKILL in that order.

On Windows, actions equivalent to the UNIX signals have been implemented to do the default job control actions. Job control messages replace the SIGINT and SIGTERM signals, but only customized applications are able to process them. Termination is implemented by the `TerminateProcess()` system call.

## JOB\_IDLE

### Syntax

**JOB\_IDLE=***number*

## Description

Specifies a threshold for idle job exception handling. The value should be a number between 0.0 and 1.0 representing CPU time/runtime. If the job idle factor is less than the specified threshold, LSF invokes `LSF_SERVERDIR/eadmin` to trigger the action for a job idle exception.

The minimum job run time before `mbatchd` reports that the job is idle is defined as `DETECT_IDLE_JOB_AFTER` in `lsb.params`.

## Valid Values

Any positive number between 0.0 and 1.0

## Example

```
JOB_IDLE=0.10
```

A job idle exception is triggered for jobs with an idle value (CPU time/runtime) less than 0.10.

## Default

Not defined. No job idle exceptions are detected.

## JOB\_OVERRUN

### Syntax

```
JOB_OVERRUN=run_time
```

## Description

Specifies a threshold for job overrun exception handling. If a job runs longer than the specified run time, LSF invokes `LSF_SERVERDIR/eadmin` to trigger the action for a job overrun exception.

## Example

```
JOB_OVERRUN=5
```

A job overrun exception is triggered for jobs running longer than 5 minutes.

## Default

Not defined. No job overrun exceptions are detected.

## JOB\_STARTER

### Syntax

```
JOB_STARTER=starter [starter] ["%USRCMD"] [starter]
```

## Description

Creates a specific environment for submitted jobs prior to execution.

*starter* is any executable that can be used to start the job (i.e., can accept the job as an input argument). Optionally, additional strings can be specified.

By default, the user commands run after the job starter. A special string, %USRCMD, can be used to represent the position of the user's job in the job starter command line. The %USRCMD string and any additional commands must be enclosed in quotation marks (" ").

## Example

```
JOB_STARTER=csh -c "%USRCMD; sleep 10"
```

In this case, if a user submits a job

```
% bsub myj ob arguments
```

the command that actually runs is:

```
% csh -c "myj ob arguments; sleep 10"
```

## Default

Not defined. No job starter is used.

## JOB\_UNDERRUN

### Syntax

```
JOB_UNDERRUN=run_time
```

### Description

Specifies a threshold for job underrun exception handling. If a job exits before the specified number of minutes, LSF invokes LSF\_SERVERDIR/eadmin to trigger the action for a job underrun exception.

### Example

```
JOB_UNDERRUN=2
```

A job underrun exception is triggered for jobs running less than 2 minutes.

## Default

Not defined. No job underrun exceptions are detected.

## JOB\_WARNING\_ACTION

### Syntax

```
JOB_WARNING_ACTION=signal
```

### Description

Specifies the job action to be taken before a job control action occurs. For example, 2 minutes before the job reaches runtime limit or termination deadline, or the queue's run window is closed, an URG signal is sent to the job.

A job warning action must be specified with a job action warning time in order for job warning to take effect.

If JOB\_WARNING\_ACTION is specified, LSF sends the warning action to the job before the actual control action is taken. This allows the job time to save its result before being terminated by the job control action.

The warning action specified by the `bsub -wa` option overrides `JOB_WARNING_ACTION` in the queue. `JOB_WARNING_ACTION` is used as the default when no command line option is specified.

## Example

```
JOB_WARNING_ACTION=URG
```

## Default

Not defined

## *load\_index*

## Syntax

```
load_index=loadSched[loadStop]
```

Specify `io`, `it`, `ls`, `mem`, `pg`, `r15s`, `r1m`, `r15m`, `swp`, `tmp`, `ut`, or a non-shared custom external load index. Specify multiple lines to configure thresholds for multiple load indices.

Specify `io`, `it`, `ls`, `mem`, `pg`, `r15s`, `r1m`, `r15m`, `swp`, `tmp`, `ut`, or a non-shared custom external load index as a column. Specify multiple columns to configure thresholds for multiple load indices.

## Description

Scheduling and suspending thresholds for the specified dynamic load index.

The `loadSched` condition must be satisfied before a job is dispatched to the host. If a `RESUME_COND` is not specified, the `loadSched` condition must also be satisfied before a suspended job can be resumed.

If the `loadStop` condition is satisfied, a job on the host is suspended.

The `loadSched` and `loadStop` thresholds permit the specification of conditions using simple AND/OR logic. Any load index that does not have a configured threshold has no effect on job scheduling.

LSF does not suspend a job if the job is the only batch job running on the host and the machine is interactively idle (`it > 0`).

The `r15s`, `r1m`, and `r15m` CPU run queue length conditions are compared to the effective queue length as reported by `lsload -E`, which is normalized for multiprocessor hosts. Thresholds for these parameters should be set at appropriate levels for single processor hosts.

## Example

```
MEM=100/10
```

```
SWAP=200/30
```

These two lines translate into a `loadSched` condition of

```
mem>=100 && swap>=200
```

and a `loadStop` condition of

```
mem < 10 || swap < 30
```

## Default

Not defined

## LOCAL\_MAX\_PREEEXEC\_RETRY

### Syntax

**LOCAL\_MAX\_PREEEXEC\_RETRY**=*integer*

### Description

The maximum number of times to attempt the pre-execution command of a job on the local cluster.

### Valid values

0 < MAX\_PREEEXEC\_RETRY < INFINIT\_INT  
INFINIT\_INT is defined in lsf.h.

## Default

Not defined. The number of preexec retry times is unlimited

## MANDATORY\_EXTSCHEDED

### Syntax

**MANDATORY\_EXTSCHEDED**=*external\_scheduler\_options*

### Description

Specifies mandatory external scheduling options for the queue.

-extsched options on the bsub command are merged with MANDATORY\_EXTSCHEDED options, and MANDATORY\_EXTSCHEDED options override any conflicting job-level options set by -extsched.

## Default

Not defined

## MAX\_JOB\_PREEMPT

### Syntax

**MAX\_JOB\_PREEMPT**=*integer*

### Description

The maximum number of times a job can be preempted. Applies to queue-level jobs only.

### Valid values

0 < MAX\_JOB\_PREEMPT < INFINIT\_INT  
INFINIT\_INT is defined in lsf.h.

## Default

Not defined. The number of preemption times is unlimited.

## MAX\_JOB\_REQUEUE

### Syntax

**MAX\_JOB\_REQUEUE=*integer***

### Description

The maximum number of times to requeue a job automatically.

### Valid values

$0 < \text{MAX\_JOB\_REQUEUE} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in lsf.h.

## Default

Not defined. The number of requeue times is unlimited

## MAX\_PREEEXEC\_RETRY

### Syntax

**MAX\_PREEEXEC\_RETRY=*integer***

### Description

MultiCluster job forwarding model only. The maximum number of times to attempt the pre-execution command of a job from a remote cluster.

If the job's pre-execution command fails all attempts, the job is returned to the submission cluster.

### Valid values

$0 < \text{MAX\_PREEEXEC\_RETRY} < \text{INFINIT\_INT}$

INFINIT\_INT is defined in lsf.h.

## Default

5

## MAX\_RSCHED\_TIME

### Syntax

**MAX\_RSCHED\_TIME=*integer* | *infinite***

## Description

MultiCluster job forwarding model only. Determines how long a MultiCluster job stays pending in the execution cluster before returning to the submission cluster. The remote timeout limit in seconds is:

```
MAX_RSCHED_TIME * MBD_SLEEP_TIME=timeout
```

Specify `infinite` to disable remote timeout (jobs always get dispatched in the correct FCFS order because MultiCluster jobs never get rescheduled, but MultiCluster jobs can be pending in the receive-jobs queue forever instead of being rescheduled to a better queue).

---

### Note:

apply to the queue in the submission cluster (only). This parameter is ignored by the receiving queue.

---

Remote timeout limit never affects advance reservation jobs

Jobs that use an advance reservation always behave as if remote timeout is disabled.

## Default

20 (20 minutes by default)

## MEMLIMIT

## Syntax

```
MEMLIMIT=[default_limit] maximum_limit
```

## Description

The per-process (hard) process resident set size limit (in KB) for all of the processes belonging to a job from this queue (see `getrlimit(2)`).

Sets the maximum amount of physical memory (resident set size, RSS) that may be allocated to a process.

By default, if a default memory limit is specified, jobs submitted to the queue without a job-level memory limit are killed when the default memory limit is reached.

If you specify only one limit, it is the maximum, or hard, memory limit. If you specify two limits, the first one is the default, or soft, memory limit, and the second one is the maximum memory limit.

LSF has two methods of enforcing memory usage:

- OS Memory Limit Enforcement
- LSF Memory Limit Enforcement

## OS memory limit enforcement

OS memory limit enforcement is the default MEMLIMIT behavior and does not require further configuration. OS enforcement usually allows the process to eventually run to completion. LSF passes MEMLIMIT to the OS that uses it as a guide for the system scheduler and memory allocator. The system may allocate more memory to a process if there is a surplus. When memory is low, the system takes memory from and lowers the scheduling priority (renice) of a process that has exceeded its declared MEMLIMIT. Only available on systems that support RLIMIT\_RSS for `setrlimit()`.

Not supported on:

- Sun Solaris 2.x
- Windows

## LSF memory limit enforcement

To enable LSF memory limit enforcement, set `LSB_MEMLIMIT_ENFORCE` in `lsf.conf` to `y`. LSF memory limit enforcement explicitly sends a signal to kill a running process once it has allocated memory past `MEMLIMIT`.

You can also enable LSF memory limit enforcement by setting `LSB_JOB_MEMLIMIT` in `lsf.conf` to `y`. The difference between `LSB_JOB_MEMLIMIT` set to `y` and `LSB_MEMLIMIT_ENFORCE` set to `y` is that with `LSB_JOB_MEMLIMIT`, only the per-job memory limit enforced by LSF is enabled. The per-process memory limit enforced by the OS is disabled. With `LSB_MEMLIMIT_ENFORCE` set to `y`, both the per-job memory limit enforced by LSF and the per-process memory limit enforced by the OS are enabled.

Available for all systems on which LSF collects total memory usage.

## Example

The following configuration defines a queue with a memory limit of 5000 KB:

```
Begin Queue
QUEUE_NAME = default
DESCRIPTION = Queue with memory limit of 5000 kbytes
MEMLIMIT = 5000
End Queue
```

## Default

Unlimited

## MIG

## Syntax

**MIG**=*minutes*

## Description

Enables automatic job migration and specifies the migration threshold for checkpointable or rerunnable jobs, in minutes.

LSF automatically migrates jobs that have been in the `SSUSP` state for more than the specified number of minutes. Specify a value of 0 to migrate jobs immediately upon suspension. The migration threshold applies to all jobs running on the host.

Job-level command line migration threshold overrides threshold configuration in application profile and queue. Application profile configuration overrides queue level configuration.

When a host migration threshold is specified, and is lower than the value for the job, the queue, or the application, the host value is used..

Members of a chunk job can be migrated. Chunk jobs in `WAIT` state are removed from the job chunk and put into `PEND` state.

Does not affect MultiCluster jobs that are forwarded to a remote cluster.

## Default

Not defined. LSF does not migrate checkpointable or rerunnable jobs automatically.

## NEW\_JOB\_SCHED\_DELAY

### Syntax

**NEW\_JOB\_SCHED\_DELAY**=*seconds*

### Description

The number of seconds that a new job waits, before being scheduled. A value of zero (0) means the job is scheduled without any delay.

## Default

2 seconds

## NICE

### Syntax

**NICE**=*integer*

### Description

Adjusts the UNIX scheduling priority at which jobs from this queue execute.

The default value of 0 (zero) maintains the default scheduling priority for UNIX interactive jobs. This value adjusts the run-time priorities for batch jobs on a queue-by-queue basis, to control their effect on other batch or interactive jobs. See the `nicel(1)` manual page for more details.

On Windows, this value is mapped to Windows process priority classes as follows:

- `nicel` ≥ 0 corresponds to a priority class of IDLE
- `nicel` < 0 corresponds to a priority class of NORMAL

Platform LSF on Windows does not support HIGH or REAL-TIME priority classes.

## Default

0 (zero)

## NQS\_QUEUES

### Syntax

**NQS\_QUEUES**=*NQS\_queue\_name@NQS\_host\_name ...*

### Description

Makes the queue an NQS forward queue.

*NQS\_host\_name* is an NQS host name that can be the official host name or an alias name known to the LSF master host.

*NQS\_queue\_name* is the name of an NQS destination queue on this host. NQS destination queues are considered for job routing in the order in which they are listed here. If a queue

accepts the job, it is routed to that queue. If no queue accepts the job, it remains pending in the NQS forward queue.

`lsb.nqsmaps` must be present for the LSF system to route jobs in this queue to NQS systems.

You must configure `LSB_MAX_NQS_QUEUES` in `lsf.conf` to specify the maximum number of NQS queues allowed in the LSF cluster. This is required for LSF to work with NQS.

Since many features of LSF are not supported by NQS, the following queue configuration parameters are ignored for NQS forward queues: `PJOB_LIMIT`, `POLICIES`, `RUN_WINDOW`, `DISPATCH_WINDOW`, `RUNLIMIT`, `HOSTS`, `MIG`. The application-level `RUNTIME` parameter in `lsb.applications` is also ignored. In addition, scheduling load threshold parameters are ignored because NQS does not provide load information about hosts.

## Default

Not defined

## PJOB\_LIMIT

### Syntax

**PJOB\_LIMIT**=*float*

### Description

Per-processor job slot limit for the queue.

Maximum number of job slots that this queue can use on any processor. This limit is configured per processor, so that multiprocessor hosts automatically run more jobs.

## Default

Unlimited

## POST\_EXEC

### Syntax

**POST\_EXEC**=*command*

### Description

Enables post-execution processing at the queue level. The `POST_EXEC` command runs on the execution host after the job finishes. Post-execution commands can be configured at the application and queue levels. Application-level post-execution commands run *before* queue-level post-execution commands.

The `POST_EXEC` command uses the same environment variable values as the job, and, by default, runs under the user account of the user who submits the job. To run post-execution commands under a different user account (such as `root` for privileged operations), configure the parameter `LSB_PRE_POST_EXEC_USER` in `lsf.sudoers`.

When a job exits with one of the queue's `REQUEUE_EXIT_VALUES`, LSF requeues the job and sets the environment variable `LSB_JOBPEND`. The post-execution command runs after the requeued job finishes.

When the post-execution command is run, the environment variable `LSB_JOBEXIT_STAT` is set to the exit status of the job. If the execution environment for the job cannot be set up, `LSB_JOBEXIT_STAT` is set to 0 (zero).

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

For UNIX:

- The pre- and post-execution commands run in the `/tmp` directory under `/bin/sh -c`, which allows the use of shell features in the commands. The following example shows valid configuration lines:

```
PRE_EXEC= /usr/share/lsf/misc/testq_pre >> /tmp/pre.out
```

```
POST_EXEC= /usr/share/lsf/misc/testq_post | grep -v "Hey!"
```

- LSF sets the `PATH` environment variable to

```
PATH='/bin /usr/bin /sbin /usr/sbin'
```

- The `stdin`, `stdout`, and `stderr` are set to `/dev/null`
- To allow UNIX users to define their own post-execution commands, an LSF administrator specifies the environment variable `$USER_POSTEXEC` as the `POST_EXEC` command. A user then defines the post-execution command:

```
setenv USER_POSTEXEC /path_name
```

---

#### Note:

The path name for the post-execution command must be an absolute path. Do not define `POST_EXEC=$USER_POSTEXEC` when `LSB_PRE_POST_EXEC_USER=root`.

---

For Windows:

- The pre- and post-execution commands run under `cmd.exe /c`
- The standard input, standard output, and standard error are set to `NULL`
- The `PATH` is determined by the setup of the LSF Service

---

#### Note:

For post-execution commands that execute on a Windows Server 2003, x64 Edition platform, users must have read and execute privileges for `cmd.exe`.

---

## Default

Not defined. No post-execution commands are associated with the queue.

## PRE\_EXEC

## Syntax

**PRE\_EXEC**=*command*

## Description

Enables pre-execution processing at the queue level. The `PRE_EXEC` command runs on the execution host before the job starts. If the `PRE_EXEC` command exits with a non-zero exit code, LSF requeues the job to the front of the queue.

Pre-execution commands can be configured at the queue, application, and job levels and run in the following order:

1. The queue-level command
2. The application-level or job-level command. If you specify a command at both the application and job levels, the job-level command overrides the application-level command; the application-level command is ignored.

The `PRE_EXEC` command uses the same environment variable values as the job, and runs under the user account of the user who submits the job. To run pre-execution commands under a different user account (such as `root` for privileged operations), configure the parameter `LSB_PRE_POST_EXEC_USER` in `lsf.sudoers`.

The command path can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows, including the directory, file name, and expanded values for `%J` (*job\_ID*) and `%I` (*index\_ID*).

For UNIX:

- The pre- and post-execution commands run in the `/tmp` directory under `/bin/sh -c`, which allows the use of shell features in the commands. The following example shows valid configuration lines:  

```
PRE_EXEC= /usr/share/lsf/misc/testq_pre >> /tmp/pre.out
POST_EXEC= /usr/share/lsf/misc/testq_post | grep -v "Hey!"
```
- LSF sets the `PATH` environment variable to  

```
PATH='/bin /usr/bin /sbin /usr/sbin'
```
- The `stdin`, `stdout`, and `stderr` are set to `/dev/null`

For Windows:

- The pre- and post-execution commands run under `cmd.exe /c`
- The standard input, standard output, and standard error are set to `NULL`
- The `PATH` is determined by the setup of the LSF Service

---

#### Note:

For pre-execution commands that execute on a Windows Server 2003, x64 Edition platform, users must have read and execute privileges for `cmd.exe`.

---

## Default

Not defined. No pre-execution commands are associated with the queue.

## PREEMPTION

### Syntax

```
PREEMPTION=PREEMPTIVE[[low_queue_name[+pref_level]...]]
PREEMPTION=PREEMPTABLE[[hi_queue_name...]] PREEMPTION=PREEMPTIVE
[[low_queue_name[+pref_level]...]] PREEMPTABLE[[hi_queue_name...]]
```

## Description

### PREEMPTIVE

Enables preemptive scheduling and defines this queue as preemptive. Jobs in this queue preempt jobs from the specified lower-priority queues or from all lower-priority queues if the parameter is specified with no queue names. PREEMPTIVE can be combined with PREEMPTABLE to specify that jobs in this queue can preempt jobs in lower-priority queues, and can be preempted by jobs in higher-priority queues.

### PREEMPTABLE

Enables preemptive scheduling and defines this queue as preemptable. Jobs in this queue can be preempted by jobs from specified higher-priority queues, or from all higher-priority queues, even if the higher-priority queues are not preemptive. PREEMPTIVE can be combined with PREEMPTABLE to specify that jobs in this queue can be preempted by jobs in higher-priority queues, and can preempt jobs in lower-priority queues.

#### *low\_queue\_name*

Specifies the names of lower-priority queues that can be preempted.

To specify multiple queues, separate the queue names with a space, and enclose the list in a single set of square brackets.

#### *+pref\_level*

Specifies to preempt this queue before preempting other queues. When multiple queues are indicated with a preference level, an order of preference is indicated: queues with higher relative preference levels are preempted before queues with lower relative preference levels set.

#### *hi\_queue\_name*

Specifies the names of higher-priority queues that can preempt jobs in this queue.

To specify multiple queues, separate the queue names with a space and enclose the list in a single set of square brackets.

## Example: configure selective, ordered preemption across queues

The following example defines four queues, as follows:

- high
  - Has the highest relative priority of 99
  - Jobs from this queue can preempt jobs from all other queues
- medium
  - Has the second-highest relative priority at 10
  - Jobs from this queue can preempt jobs from `normal` and `low` queues, beginning with jobs from `low`, as indicated by the preference (+1)
- normal
  - Has the second-lowest relative priority, at 5
  - Jobs from this queue can preempt jobs from `low`, and can be preempted by jobs from both `high` and `medium` queues

- **low**
  - Has the lowest relative priority, which is also the default priority, at 1
  - Jobs from this queue can be preempted by jobs from all preemptive queues, even though it does not have the **PREEMPTABLE** keyword set

```

Begin Queue
QUEUE_NAME=high
PREEMPTION=PREEMPTIVE
PRIORITY=99
End Queue

Begin Queue
QUEUE_NAME=medium
PREEMPTION=PREEMPTIVE[normal low+1]
PRIORITY=10
End Queue

Begin Queue
QUEUE_NAME=normal
PREEMPTION=PREEMPTIVE[low]
PREEMPTABLE[high medium]
PRIORITY=5
End Queue

Begin Queue
QUEUE_NAME=low
PRIORITY=1
End Queue

```

## PRIORITY

### Syntax

**PRIORITY**=*integer*

### Description

Specifies the relative queue priority for dispatching jobs. A higher value indicates a higher job-dispatching priority, relative to other queues.

LSF schedules jobs from one queue at a time, starting with the highest-priority queue. If multiple queues have the same priority, LSF schedules all the jobs from these queues in first-come, first-served order.

LSF queue priority is independent of the UNIX scheduler priority system for time-sharing processes. In LSF, the NICE parameter is used to set the UNIX time-sharing priority for batch jobs.

integer

Specify a number greater than or equal to 1, where 1 is the lowest priority.

## Default

1

## PROCESSLIMIT

### Syntax

**PROCESSLIMIT**=[*default\_limit*] *maximum\_limit*

### Description

Limits the number of concurrent processes that can be part of a job.

By default, if a default process limit is specified, jobs submitted to the queue without a job-level process limit are killed when the default process limit is reached.

If you specify only one limit, it is the maximum, or hard, process limit. If you specify two limits, the first one is the default, or soft, process limit, and the second one is the maximum process limit.

## Default

Unlimited

## PROCLIMIT

### Syntax

**PROCLIMIT**=[*minimum\_limit* [*default\_limit*]] *maximum\_limit*

### Description

Maximum number of slots that can be allocated to a job. For parallel jobs, the maximum number of processors that can be allocated to the job.

Job-level processor limits (`bsub -n`) override queue-level PROCLIMIT. Job-level limits must fall within the maximum and minimum limits of the application profile and the queue. Application-level PROCLIMIT in `lsb.appl icat ions` overrides queue-level specification.

Optionally specifies the minimum and default number of job slots.

All limits must be positive numbers greater than or equal to 1 that satisfy the following relationship:

$1 \leq \textit{minimum} \leq \textit{default} \leq \textit{maximum}$

You can specify up to three limits in the PROCLIMIT parameter:

Jobs that request fewer slots than the minimum PROCLIMIT or more slots than the maximum PROCLIMIT cannot use the queue and are rejected. If the job requests minimum and maximum job slots, the maximum slots requested cannot be less than the minimum PROCLIMIT, and the minimum slots requested cannot be more than the maximum PROCLIMIT.

## Default

Unlimited, the default number of slots is 1

## QJOB\_LIMIT

### Syntax

**QJOB\_LIMIT**=*integer*

### Description

Job slot limit for the queue. Total number of job slots that this queue can use.

## Default

Unlimited

## QUEUE\_GROUP

### Syntax

**QUEUE\_GROUP**=*queue1, queue2 ...*

### Description

Configures absolute priority scheduling (APS) across multiple queues.

When APS is enabled in the queue with APS\_PRIORITY, the FAIRSHARE\_QUEUES parameter is ignored. The QUEUE\_GROUP parameter replaces FAIRSHARE\_QUEUES, which is obsolete in LSF 7.0.

## Default

Not defined

## QUEUE\_NAME

### Syntax

**QUEUE\_NAME**=*string*

### Description

*Required.* Name of the queue.

Specify any ASCII string up to 59 characters long. You can use letters, digits, underscores (\_) or dashes (-). You cannot use blank spaces. You cannot specify the reserved name default.

## Default

You must specify this parameter to define a queue. The default queue automatically created by LSF is named default.

## RCVJOBS\_FROM

### Syntax

```
RCVJOBS_FROM=cluster_name ... | allclusters
```

### Description

MultiCluster only. Defines a MultiCluster receive-jobs queue.

Specify cluster names, separated by a space. The administrator of each remote cluster determines which queues in that cluster forward jobs to the local cluster.

Use the keyword `allclusters` to specify any remote cluster.

### Example

```
RCVJOBS_FROM=cluster2 cluster4 cluster6
```

This queue accepts remote jobs from clusters 2, 4, and 6.

## REMOTE\_MAX\_PREEEXEC\_RETRY

### Syntax

```
REMOTE_MAX_PREEEXEC_RETRY=integer
```

### Description

The maximum number of times to attempt the pre-execution command of a job on the remote cluster.

### Valid values

$0 < \text{MAX\_PREEEXEC\_RETRY} < \text{INFINIT\_INT}$

`INFINIT_INT` is defined in `lsf.h`.

### Default

5

## REQUEUE\_EXIT\_VALUES

### Syntax

```
REQUEUE_EXIT_VALUES=[exit_code ...] [EXCLUDE(exit_code ...)]
```

### Description

Enables automatic job requeue and sets the `LSB_EXIT_REQUEUE` environment variable. Use spaces to separate multiple exit codes. Application-level exit values override queue-level values. Job-level exit values (`bsub -Q`) override application-level and queue-level values.

*exit\_code* has the following form:

```
"[all] [~number ...] | [number ...]"
```

The reserved keyword `all` specifies all exit codes. Exit codes are typically between 0 and 255. Use a tilde (~) to exclude specified exit codes from the list.

Jobs are requeued to the head of the queue. The output from the failed run is not saved, and the user is not notified by LSF.

Define an exit code as `EXCLUDE(exit_code)` to enable exclusive job requeue. Exclusive job requeue does not work for parallel jobs.

For MultiCluster jobs forwarded to a remote execution cluster, the exit values specified in the submission cluster with the `EXCLUSIVE` keyword are treated as if they were non-exclusive.

You can also requeue a job if the job is terminated by a signal.

If a job is killed by a signal, the exit value is  $128 + \text{signal\_value}$ . The sum of 128 and the signal value can be used as the exit code in the parameter `REQUEUE_EXIT_VALUES`.

For example, if you want a job to rerun if it is killed with a signal 9 (SIGKILL), the exit value would be  $128 + 9 = 137$ . You can configure the following requeue exit value to allow a job to be requeue if it was kill by signal 9:

```
REQUEUE_EXIT_VALUES=137
```

If `mbatchd` is restarted, it does not remember the previous hosts from which the job exited with an exclusive requeue exit code. In this situation, it is possible for a job to be dispatched to hosts on which the job has previously exited with an exclusive exit code.

You should configure `REQUEUE_EXIT_VALUES` for interruptible backfill queues (`INTERRUPTIBLE_BACKFILL=seconds`).

## Example

```
REQUEUE_EXIT_VALUES=30 EXCLUDE(20)
```

means that jobs with exit code 30 are requeued, jobs with exit code 20 are requeued exclusively, and jobs with any other exit code are not requeued.

## Default

Not defined. Jobs are not requeued.

## RERUNNABLE

### Syntax

```
RERUNNABLE=yes | no
```

### Description

If yes, enables automatic job rerun (restart).

Rerun is disabled when `RERUNNABLE` is set to no. The yes and no arguments are not case sensitive.

For MultiCluster jobs, the setting in the submission queue is used, and the setting in the execution queue is ignored.

Members of a chunk job can be rerunnable. If the execution host becomes unavailable, rerunnable chunk job members are removed from the job chunk and dispatched to a different execution host.

## Default

no

## RESOURCE\_RESERVE

### Syntax

```
RESOURCE_RESERVE=MAX_RESERVE_TIME[integer]
```

### Description

Enables processor reservation and memory reservation for pending jobs for the queue. Specifies the number of dispatch turns (MAX\_RESERVE\_TIME) over which a job can reserve job slots and memory.

Overrides the SLOT\_RESERVE parameter. If both RESOURCE\_RESERVE and SLOT\_RESERVE are defined in the same queue, an error is displayed when the cluster is reconfigured, and SLOT\_RESERVE is ignored. Job slot reservation for parallel jobs is enabled by RESOURCE\_RESERVE if the LSF scheduler plugin module names for both resource reservation and parallel batch jobs (schmod\_parallel and schmod\_reserve) are configured in the lsb.modules file: The schmod\_parallel name *must* come before schmod\_reserve in lsb.modules.

If a job has not accumulated enough memory or job slots to start by the time MAX\_RESERVE\_TIME expires, it releases all its reserved job slots or memory so that other pending jobs can run. After the reservation time expires, the job cannot reserve memory or slots for one scheduling session, so other jobs have a chance to be dispatched. After one scheduling session, the job can reserve available memory and job slots again for another period specified by MAX\_RESERVE\_TIME.

If BACKFILL is configured in a queue, and a run limit is specified with -W on bsub or with RUNLIMIT in the queue, backfill jobs can use the accumulated memory reserved by the other jobs in the queue, as long as the backfill job can finish before the predicted start time of the jobs with the reservation.

Unlike slot reservation, which only applies to parallel jobs, memory reservation and backfill on memory apply to sequential and parallel jobs.

### Example

```
RESOURCE_RESERVE=MAX_RESERVE_TIME[5]
```

This example specifies that jobs have up to 5 dispatch turns to reserve sufficient job slots or memory (equal to 5 minutes, by default).

## Default

Not defined. No job slots or memory is reserved.

## RES\_REQ

### Syntax

```
RES_REQ=res_req
```

## Description

Resource requirements used to determine eligible hosts. Specify a resource requirement string as usual. The resource requirement string lets you specify conditions in a more flexible manner than using the load thresholds. Resource requirement strings can be simple (applying to the entire job) or compound (applying to the specified number of slots).

When a compound resource requirement is set for a queue, it will be ignored unless it is the only resource requirement specified (no resource requirements are set at the job-level or application-level).

When a simple resource requirement is set for a queue and a compound resource requirement is set at the job-level or application-level, the queue-level requirements merge as they do for simple resource requirements. However, any job-based resources defined in the queue only apply to the first term of the merged compound resource requirements.

When `LSF_STRICT_RESREQ=Y` is configured in `lsf.conf`, resource requirement strings in select sections must conform to a more strict syntax. The strict resource requirement syntax only applies to the select section. It does not apply to the other resource requirement sections (order, rusage, same, span, or cu). When `LSF_STRICT_RESREQ=Y` in `lsf.conf`, LSF rejects resource requirement strings where an rusage section contains a non-consumable resource.

For simple resource requirements, the select sections from all levels must be satisfied and the same sections from all levels are combined. cu, order, and span sections at the job-level overwrite those at the application-level which overwrite those at the queue-level. Multiple rusage definitions are merged, with the job-level rusage taking precedence over the application-level, and application-level taking precedence over the queue-level.

The simple resource requirement rusage section can specify additional requests. To do this, use the OR (|) operator to separate additional rusage strings.

---

### Note:

Compound resource requirements do not support use of the || operator within rusage sections, multiple -R options, or the cu section.

---

For example:

Queue-level RES\_REQ: `RES_REQ=rusage[mem=200:lic=1] ...`

For the job submission:

`bsub -R' rusage[mem=100]' ...`

the resulting requirement for the job is

`rusage[mem=100:lic=1]`

where `mem=100` specified by the job overrides `mem=200` specified by the queue. However, `lic=1` from queue is kept, since job does not specify it.

Queue-level RES\_REQ: `RES_REQ=rusage[mem=200: duration=20: decay=1] ...`

For a job submission with no decay or duration:

`bsub -R' rusage[mem=100]' ...`

the resulting requirement for the job is:

`rusage[mem=100: duration=20: decay=1]`

Queue-level duration and decay are merged with the job-level specification, and `mem=100` for the job overrides `mem=200` specified by the queue. However, `duration=20` and `decay=1` from queue are kept, since job does not specify them.

The `order` section defined at the queue level is ignored if any resource requirements are specified at the job level (if the job-level resource requirements do not include the `order` section, the default `order, r15s:pg`, is used instead of the queue-level resource requirement).

If `RES_REQ` is defined at the queue level and there are no load thresholds defined, the pending reasons for each individual load index are not displayed by `bj obs`.

The `span` section defined at the queue level is ignored if the `span` section is also defined at the job level or in an application profile.

---

#### Note:

Define `span[hosts=-1]` in the application profile or `bsub -R resource requirement string` to override the `span` section setting in the queue.

---

Resource requirements determined by the queue no longer apply to a running job after running `badmi n reconfi g`. For example, if you change the `RES_REQ` parameter in a queue and reconfigure the cluster, the previous queue-level resource requirements for running jobs are lost.

## Default

`select[type==local] order[r15s:pg]`. If this parameter is defined and a host model or Boolean resource is specified, the default type is any.

## RESUME\_COND

### Syntax

**RESUME\_COND**=*res\_req*

Use the `select` section of the resource requirement string to specify load thresholds. All other sections are ignored.

### Description

LSF automatically resumes a suspended (SSUSP) job in this queue if the load on the host satisfies the specified conditions.

If `RESUME_COND` is not defined, then the `loadSched` thresholds are used to control resuming of jobs. The `loadSched` thresholds are ignored, when resuming jobs, if `RESUME_COND` is defined.

## RUN\_WINDOW

### Syntax

**RUN\_WINDOW**=*time\_window ...*

## Description

Time periods during which jobs in the queue are allowed to run.

When the window closes, LSF suspends jobs running in the queue and stops dispatching jobs from the queue. When the window reopens, LSF resumes the suspended jobs and begins dispatching additional jobs.

## Default

Not defined. Queue is always active.

## RUNLIMIT

### Syntax

**RUNLIMIT**=[*default\_limit*] *maximum\_limit*

where *default\_limit* and *maximum\_limit* are:

[*hour*:]*minute*[/*host\_name* | /*host\_model*]

## Description

The maximum run limit and optionally the default run limit. The name of a host or host model specifies the runtime normalization host to use.

By default, jobs that are in the RUN state for longer than the specified maximum run limit are killed by LSF. You can optionally provide your own termination job action to override this default.

Jobs submitted with a job-level run limit (bsub -W) that is less than the maximum run limit are killed when their job-level run limit is reached. Jobs submitted with a run limit greater than the maximum run limit are rejected by the queue.

If a default run limit is specified, jobs submitted to the queue without a job-level run limit are killed when the default run limit is reached. The default run limit is used with backfill scheduling of parallel jobs.

---

### Note:

If you want to provide an estimated run time for scheduling purposes without killing jobs that exceed the estimate, define the RUNTIME parameter in an application profile instead of a run limit (see lsb. applications for details).

---

If you specify only one limit, it is the maximum, or hard, run limit. If you specify two limits, the first one is the default, or soft, run limit, and the second one is the maximum run limit. The number of minutes may be greater than 59. Therefore, three and a half hours can be specified either as 3:30, or 210.

The run limit is in the form of [hour:]minute. The minutes can be specified as a number greater than 59. For example, three and a half hours can either be specified as 3:30, or 210.

The run limit you specify is the normalized run time. This is done so that the job does approximately the same amount of processing, even if it is sent to host with a faster or slower CPU. Whenever a normalized run time is given, the actual time on the execution host is the

specified time multiplied by the CPU factor of the normalization host then divided by the CPU factor of the execution host.

If `ABS_RUNLIMIT=Y` is defined in `lsb.params`, the runtime limit is not normalized by the host CPU factor. Absolute wall-clock run time is used for all jobs submitted to a queue with a run limit configured.

Optionally, you can supply a host name or a host model name defined in LSF. You must insert `'/'` between the run limit and the host name or model name. (See `lsinfo(1)` to get host model information.)

If no host or host model is given, LSF uses the default runtime normalization host defined at the queue level (`DEFAULT_HOST_SPEC` in `lsb.queues`) if it has been configured; otherwise, LSF uses the default CPU time normalization host defined at the cluster level (`DEFAULT_HOST_SPEC` in `lsb.params`) if it has been configured; otherwise, the host with the largest CPU factor (the fastest host in the cluster).

For MultiCluster jobs, if no other CPU time normalization host is defined and information about the submission host is not available, LSF uses the host with the largest CPU factor (the fastest host in the cluster).

Jobs submitted to a chunk job queue are not chunked if `RUNLIMIT` is greater than 30 minutes. `RUNLIMIT` is required for queues configured with `INTERRUPTIBLE_BACKFILL`.

## Default

Unlimited

## SLOT\_POOL

### Syntax

`SLOT_POOL=pool_name`

### Description

Name of the pool of job slots the queue belongs to for queue-based fairshare. A queue can only belong to one pool. All queues in the pool must share the same set of hosts.

### Valid value

Specify any ASCII string up to 60 characters long. You can use letters, digits, underscores (`_`) or dashes (`-`). You cannot use blank spaces.

## Default

Not defined. No job slots are reserved.

## SLOT\_RESERVE

### Syntax

`SLOT_RESERVE=MAX_RESERVE_TIME[integer]`

## Description

Enables processor reservation for the queue and specifies the reservation time. Specify the keyword `MAX_RESERVE_TIME` and, in square brackets, the number of `MBD_SLEEP_TIME` cycles over which a job can reserve job slots. `MBD_SLEEP_TIME` is defined in `lsb.params`; the default value is 60 seconds.

If a job has not accumulated enough job slots to start before the reservation expires, it releases all its reserved job slots so that other jobs can run. Then, the job cannot reserve slots for one scheduling session, so other jobs have a chance to be dispatched. After one scheduling session, the job can reserve job slots again for another period specified by `SLOT_RESERVE`.

`SLOT_RESERVE` is overridden by the `RESOURCE_RESERVE` parameter.

If both `RESOURCE_RESERVE` and `SLOT_RESERVE` are defined in the same queue, job slot reservation and memory reservation are enabled and an error is displayed when the cluster is reconfigured. `SLOT_RESERVE` is ignored.

Job slot reservation for parallel jobs is enabled by `RESOURCE_RESERVE` if the LSF scheduler plugin module names for both resource reservation and parallel batch jobs (`schmod_parallel` and `schmod_reserve`) are configured in the `lsb.modules` file: The `schmod_parallel` name *must* come before `schmod_reserve` in `lsb.modules`.

If `BACKFILL` is configured in a queue, and a run limit is specified at the job level (`bsub -W`), application level (`RUNLIMIT` in `lsb.applications`), or queue level (`RUNLIMIT` in `lsb.queues`), or if an estimated run time is specified at the application level (`RUNTIME` in `lsb.applications`), backfill parallel jobs can use job slots reserved by the other jobs, as long as the backfill job can finish before the predicted start time of the jobs with the reservation.

Unlike memory reservation, which applies both to sequential and parallel jobs, slot reservation applies only to parallel jobs.

## Example

```
SLOT_RESERVE=MAX_RESERVE_TIME[ 5]
```

This example specifies that parallel jobs have up to 5 cycles of `MBD_SLEEP_TIME` (5 minutes, by default) to reserve sufficient job slots to start.

## Default

Not defined. No job slots are reserved.

## SLOT\_SHARE

### Syntax

```
SLOT_SHARE=integer
```

### Description

Share of job slots for queue-based fairshare. Represents the percentage of running jobs (job slots) in use from the queue. `SLOT_SHARE` must be greater than zero (0) and less than or equal to 100.

The sum of `SLOT_SHARE` for all queues in the pool does not need to be 100%. It can be more or less, depending on your needs.

## Default

Not defined

## SNDJOBS\_TO

### Syntax

**SNDJOBS\_TO**=*queue\_name@cluster\_name ...*

### Description

Defines a MultiCluster send-jobs queue.

Specify remote queue names, in the form *queue\_name@cluster\_name*, separated by a space.

This parameter is ignored if `lsb.queues.HOSTS` specifies remote (borrowed) resources.

### Example

```
SNDJOBS_TO=queue2@cluster2 queue3@cluster2 queue3@cluster3
```

## STACKLIMIT

### Syntax

**STACKLIMIT**=*integer*

### Description

The per-process (hard) stack segment size limit (in KB) for all of the processes belonging to a job from this queue (see `getrlimit(2)`).

## Default

Unlimited

## STOP\_COND

### Syntax

**STOP\_COND**=*res\_req*

Use the `select` section of the resource requirement string to specify load thresholds. All other sections are ignored.

### Description

LSF automatically suspends a running job in this queue if the load on the host satisfies the specified conditions.

- LSF does not suspend the only job running on the host if the machine is interactively idle (`it > 0`).
- LSF does not suspend a forced job (`brun -f`).
- LSF does not suspend a job because of paging rate if the machine is interactively idle.

If `STOP_COND` is specified in the queue and there are no load thresholds, the suspending reasons for each individual load index is not displayed by `bj obs`.

## Example

```
STOP_COND= select [ ((!cs && it < 5) || (cs && mem < 15 && swp < 50)) ]
```

In this example, assume “cs” is a Boolean resource indicating that the host is a computer server. The stop condition for jobs running on computer servers is based on the availability of swap memory. The stop condition for jobs running on other kinds of hosts is based on the idle time.

## SWAPLIMIT

### Syntax

**SWAPLIMIT**=*integer*

### Description

The amount of total virtual memory limit (in KB) for a job from this queue.

This limit applies to the whole job, no matter how many processes the job may contain.

The action taken when a job exceeds its SWAPLIMIT or PROCESSLIMIT is to send SIGQUIT, SIGINT, SIGTERM, and SIGKILL in sequence. For CPULIMIT, SIGXCPU is sent before SIGINT, SIGTERM, and SIGKILL.

### Default

Unlimited

## TERMINATE\_WHEN

### Syntax

**TERMINATE\_WHEN**=[LOAD] [PREEMPT] [WINDOW]

### Description

Configures the queue to invoke the TERMINATE action instead of the SUSPEND action in the specified circumstance.

- **LOAD**: kills jobs when the load exceeds the suspending thresholds.
- **PREEMPT**: kills jobs that are being preempted.
- **WINDOW**: kills jobs if the run window closes.

If the TERMINATE\_WHEN job control action is applied to a chunk job, sbatchd kills the chunk job element that is running and puts the rest of the waiting elements into pending state to be rescheduled later.

## Example

Set `TERMINATE_WHEN` to `WINDOW` to define a night queue that kills jobs if the run window closes:

```
Begin Queue
NAME           = ni ght
RUN_WINDOW     = 20: 00- 08: 00
TERMINATE_WHEN = WI NDO W
JOB_CONTROLS   = TERMI NATE[kill -KILL $LS_JOBPGIDS; mail - s "job $LSB_JOBID
killed by queue run window" $USER < /dev/null ]
End Queue
```

## THREADLIMIT

### Syntax

**THREADLIMIT**=[*default\_limit*] *maximum\_limit*

### Description

Limits the number of concurrent threads that can be part of a job. Exceeding the limit causes the job to terminate. The system sends the following signals in sequence to all processes belongs to the job: SIGINT, SIGTERM, and SIGKILL.

By default, if a default thread limit is specified, jobs submitted to the queue without a job-level thread limit are killed when the default thread limit is reached.

If you specify only one limit, it is the maximum, or hard, thread limit. If you specify two limits, the first one is the default, or soft, thread limit, and the second one is the maximum thread limit.

Both the default and the maximum limits must be positive integers. The default limit must be less than the maximum limit. The default limit is ignored if it is greater than the maximum limit.

### Examples

```
THREADLI MI T=6
```

No default thread limit is specified. The value 6 is the default and maximum thread limit.

```
THREADLI MI T=6 8
```

The first value (6) is the default thread limit. The second value (8) is the maximum thread limit.

### Default

Unlimited

## UJOB\_LIMIT

### Syntax

**UJOB\_LIMIT**=*integer*

## Description

Per-user job slot limit for the queue. Maximum number of job slots that each user can use in this queue.

## Default

Unlimited

## USE\_PAM\_CREDS

## Syntax

**USE\_PAM\_CREDS=y | n**

## Description

If **USE\_PAM\_CREDS=y**, applies PAM limits to a queue when its job is dispatched to a Linux host using PAM. PAM limits are system resource limits defined in `limits.conf`.

When **USE\_PAM\_CREDS** is enabled, PAM limits override others. For example, the PAM limit is used even if queue-level soft limit is less than PAM limit. However, it still cannot exceed queue's hard limit.

If the execution host does not have PAM configured and this parameter is enabled, the job fails.

For parallel jobs, only takes effect on the first execution host.

**USE\_PAM\_CREDS** only applies on the following platforms:

- linux2.6-glibc2.3-ia64
- linux2.6-glibc2.3-ia64-slurm
- linux2.6-glibc2.3-ppc64
- linux2.6-glibc2.3-sn-ipf
- linux2.6-glibc2.3-x86
- linux2.6-glibc2.3-x86\_64
- linux2.6-glibc2.3-x86\_64-slurm

Overrides **MEMLIMIT\_TYPE=Process**.

Overridden (for CPU limit only) by **LSB\_JOB\_CPULIMIT=y**.

Overridden (for memory limits only) by **LSB\_JOB\_MEMLIMIT=y**.

## Default

n

## USERS

## Syntax

**USERS=all** [*~user\_name...*] [*~user\_group...*] | [*user\_name...*] [*user\_group* [*~user\_group...*] ...]

## Description

A space-separated list of user names or user groups that can submit jobs to the queue. LSF cluster administrators are automatically included in the list of users. LSF cluster administrators can submit jobs to this queue, or switch (b*swi t ch*) any user's jobs into this queue.

If user groups are specified, each user in the group can submit jobs to this queue. If FAIRSHARE is also defined in this queue, only users defined by both parameters can submit jobs, so LSF administrators cannot use the queue if they are not included in the share assignments.

User names must be valid login names. To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME**user\_name*).

User group names can be LSF user groups or UNIX and Windows user groups. To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAME* \i*user\_group*).

Use the keyword *all* to specify all users or user groups in a cluster.

Use the not operator (~) to exclude users from the *all* specification or from user groups. This is useful if you have a large number of users but only want to exclude a few users or groups from the queue definition.

The not operator (~) can only be used with the *all* keyword or to exclude users from user groups.

---

### Caution:

The not operator does not exclude LSF administrators from the queue definition.

---

## Default

*all* (all users can submit jobs to the queue)

## Examples

- `USERS=user1 user2`
- `USERS=all ~user1 ~user2`
- `USERS=all ~ugroup1`
- `USERS=groupA ~user3 ~user4`

## Automatic time-based configuration

Variable configuration is used to automatically change LSF configuration based on time windows. You define automatic configuration changes in *lsb.queues* by using if-else constructs and time expressions. After you change the files, reconfigure the cluster with the `lsadmin reconfig` command.

The expressions are evaluated by LSF every 10 minutes based on `mbatchd` start time. When an expression evaluates true, LSF dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting `mbatchd`, providing continuous system availability.

## Example

```
Begin Queue  
...  
#if time(8:30-18:30)  
INTERACTIVE = ONLY # interactive only during day shift #endif  
...  
End Queue
```

# lsb.resources

The `lsb.resources` file contains configuration information for resource allocation limits, exports, and resource usage limits. This file is optional.

The `lsb.resources` file is stored in the directory `LSB_CONFDIR/cluster_name/confdir`, where `LSB_CONFDIR` is defined in `lsf.conf`.

## Changing lsb.resources configuration

After making any changes to `lsb.resources`, run `badm n reconf i g` to reconfigure `mbatchd`.

### Limit section

The Limit section sets limits for the maximum amount of the specified resources that must be available for different classes of jobs to start, and which resource consumers the limits apply to. Limits are enforced during job resource allocation.

---

#### Tip:

For limits to be enforced, jobs must specify resource requirements (`bsub -R` or `RES_REQ` in `lsb.queues`).

---

The `blimits` command displays view current usage of resource allocation limits configured in Limit sections in `lsb.resources`:

### Limit section structure

Each set of limits is defined in a Limit section enclosed by `Begin Limit` and `End Limit`.

A Limit section has two formats:

- Vertical tabular
- Horizontal

The file can contain sections in both formats. In either format, you must configure a limit for at least one consumer and one resource. The Limit section cannot be empty.

### Vertical tabular format

Use the vertical format for simple configuration conditions involving only a few consumers and resource limits.

The first row consists of an optional NAME and the following keywords for:

- Resource types:
  - SLOTS or SLOTS\_PER\_PROCESSOR
  - MEM (MB or percentage)
  - SWP (MB or percentage)
  - TMP (MB or percentage)
  - LICENSE
  - JOBS
  - RESOURCE
- Consumer types:

- USERS or PER\_USER
- QUEUES or PER\_QUEUE
- HOSTS or PER\_HOST
- PROJECTS or PER\_PROJECT

Each subsequent row describes the configuration information for resource consumers and the limits that apply to them. Each line must contain an entry for each keyword. Use empty parentheses () or a dash (-) to specify the default value for an entry. Fields cannot be left blank. For resources, the default is no limit; for consumers, the default is all consumers.

---

#### Tip:

Multiple entries must be enclosed in parentheses. For RESOURCE and LICENSE limits, resource and license names must be enclosed in parentheses.

---

## Horizontal format

Use the horizontal format to give a name for your limits and to configure more complicated combinations of consumers and resource limits.

The first line of the Limit section gives the name of the limit configuration.

Each subsequent line in the Limit section consists of keywords identifying the resource limits:

- Job slots and per-processor job slots
- Memory (MB or percentage)
- Swap space (MB or percentage)
- Tmp space (MB or percentage)
- Software licenses
- Running and suspended (RUN, SSUSP, USUSP) jobs
- Other shared resources

and the resource *consumers* to which the limits apply:

- Users and user groups
- Hosts and host groups
- Queues
- Projects

## Example: Vertical tabular format

In the following limit configuration:

- Jobs from user1 and user3 are limited to 2 job slots on hostA
- Jobs from user2 on queue normal are limited to 20 MB of memory
- The short queue can have at most 200 running and suspended jobs

| Begin Limit |               |        |       |       |     |     |     |      |
|-------------|---------------|--------|-------|-------|-----|-----|-----|------|
| NAME        | USERS         | QUEUES | HOSTS | SLOTS | MEM | SWP | TMP | JOBS |
| limit1      | (user1 user3) | -      | hostA | 2     | -   | -   | -   | -    |
| -           | user2         | normal | -     | -     | 20  | -   | -   | -    |
| -           | -             | short  | -     | -     | -   | -   | -   | 200  |
| End Limit   |               |        |       |       |     |     |     |      |

Jobs that do not match these limits; that is, all users except user1 and user3 running jobs on hostA and all users except user2 submitting jobs to queue normal , have no limits.

## Example: Horizontal format

All users in user group ugroup1 except user1 using queue1 and queue2 and running jobs on hosts in host group hgroup1 are limited to 2 job slots per processor on each host:

```

Begin Limit
# ugroup1 except user1 uses queue1 and queue2 with 2 job slots
# on each host in hgroup1
NAME = limit1
# Resources
SLOTS_PER_PROCESSOR = 2
#Consumers
QUEUES = queue1 queue2
USERS = ugroup1 ~user1
PER_HOST = hgroup1
End Limit

```

## Compatibility with lsb.queues, lsb.users, and lsb.hosts

The Limit section of lsb.resources does not support the keywords or format used in lsb.users, lsb.hosts, and lsb.queues. However, your existing job slot limit configuration in these files will continue to apply.

Job slot limits are the only type of limit you can configure in lsb.users, lsb.hosts, and lsb.queues. You cannot configure limits for user groups, host groups, and projects in lsb.users, lsb.hosts, and lsb.queues. You should not configure any new resource allocation limits in lsb.users, lsb.hosts, and lsb.queues. Use lsb.resources to configure all new resource allocation limits, including job slot limits. Limits on running and suspended jobs can only be set in lsb.resources.

Existing limits in lsb.users, lsb.hosts, and lsb.queues with the same scope as a new limit in lsb.resources, but with a different value are ignored. The value of the new limit in lsb.resources is used. Similar limits with different scope enforce the most restrictive limit.

## Parameters

- HOSTS
- JOBS
- LICENSE
- MEM
- NAME
- PER\_HOST
- PER\_PROJECT
- PER\_QUEUE
- PER\_USER
- PROJECTS
- QUEUES

- RESOURCE
- SLOTS
- SLOTS\_PER\_PROCESSOR
- SWP
- TMP
- USERS

## HOSTS

### Syntax

```
HOSTS=all [~]host_name ... | all [~]host_group ...
```

**HOSTS**

```
( [-] | all [~]host_name ... | all [~]host_group ... )
```

### Description

A space-separated list of hosts, host groups defined in `lsb.hosts` on which limits are enforced. Limits are enforced on all hosts or host groups listed.

If a group contains a subgroup, the limit also applies to each member in the subgroup recursively.

To specify a per-host limit, use the `PER_HOST` keyword. Do not configure `HOSTS` and `PER_HOST` limits in the same Limit section.

If you specify `MEM`, `TMP`, or `SWP` as a percentage, you must specify `PER_HOST` and list the hosts that the limit is to be enforced on. You cannot specify `HOSTS`.

In horizontal format, use only one `HOSTS` line per Limit section.

Use the keyword `all` to configure limits that apply to all hosts in a cluster.

Use the not operator (`~`) to exclude hosts from the `all` specification in the limit. This is useful if you have a large cluster but only want to exclude a few hosts from the limit definition.

In vertical tabular format, multiple host names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses `()` or a dash `(-)` to indicate all hosts. Fields cannot be left blank.

### Default

`all` (limits are enforced on all hosts in the cluster).

### Example 1

```
HOSTS=Group1 ~hostA hostB hostC
```

Enforces limits on `hostB`, `hostC`, and all hosts in `Group1` except for `hostA`.

### Example 2

```
HOSTS=all ~group2 ~hostA
```

Enforces limits on all hosts in the cluster, except for `hostA` and the hosts in `group2`.

## Example 3

```
HOSTS SWP (all ~hostK ~hostM) 10
```

Enforces a 10 MB swap limit on all hosts in the cluster, except for hostK and hostM

## JOBS

### Syntax

**JOBS**=*integer*

**JOBS**

- | *integer*

### Description

Maximum number of running or suspended (RUN, SSUSP, USUSP) jobs available to resource consumers. Specify a positive integer greater than or equal 0. Job limits can be defined in both vertical and horizontal limit formats.

With MultiCluster resource lease model, this limit applies only to local hosts being used by the local cluster. The job limit for hosts exported to a remote cluster is determined by the host export policy, not by this parameter. The job limit for borrowed hosts is determined by the host export policy of the remote cluster.

If SLOTS are configured in the Limit section, the most restrictive limit is applied.

If HOSTS are configured in the Limit section, JOBS is the number of running and suspended jobs on a host. If preemptive scheduling is used, the suspended jobs are not counted against the job limit.

Use this parameter to prevent a host from being overloaded with too many jobs, and to maximize the throughput of a machine.

If only QUEUES are configured in the Limit section, JOBS is the maximum number of jobs that can run in the listed queues for any hosts, users, or projects.

If only USERS are configured in the Limit section, JOBS is the maximum number of jobs that the users or user groups can run on any hosts, queues, or projects.

If only HOSTS are configured in the Limit section, JOBS is the maximum number of jobs that can run on the listed hosts for any users, queues, or projects.

If only PROJECTS are configured in the Limit section, JOBS is the maximum number of jobs that can run under the listed projects for any users, queues, or hosts.

Use QUEUES or PER\_QUEUE, USERS or PER\_USER, HOSTS or PER\_HOST, and PROJECTS or PER\_PROJECT in combination to further limit jobs available to resource consumers.

In horizontal format, use only one JOBS line per Limit section.

In vertical format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

### Default

No limit

## Example

```
JOBS=20
```

## LICENSE

### Syntax

```
LICENSE=[license_name,integer] [[license_name,integer] ...]
```

```
LICENSE
```

```
( [license_name,integer] [[license_name,integer] ...] )
```

### Description

Maximum number of specified software licenses available to resource consumers. The value must be a positive integer greater than or equal to zero.

Software licenses must be defined as decreasing numeric shared resources in `lsf . shared`.

The RESOURCE keyword is a synonym for the LICENSE keyword. You cannot specify RESOURCE and LICENSE in the same Limit section.

In horizontal format, use only one LICENSE line per Limit section.

In vertical tabular format, license entries must be enclosed in parentheses.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

### Default

None

### Examples

```
LICENSE=[verilog, 4] [spice, 2]
```

```
Begin Limit
```

```
LICENSE PER_HOST
```

```
([verilog, 1]) (all ~hostA)
```

```
([verilog, 1] [spice, 2]) (hostA)
```

```
End Limit
```

## MEM

### Syntax

```
MEM=integer[%]
```

```
MEM
```

```
- | integer[%]
```

## Description

Maximum amount of memory available to resource consumers. Specify a value in MB or a percentage (%) as a positive integer greater than or equal 0. If you specify a percentage, you must also specify PER\_HOST and list the hosts that the limit is to be enforced on.

The Limit section is ignored if MEM is specified as a percentage:

- Without PER\_HOST, or
- With HOSTS

In horizontal format, use only one MEM line per Limit section.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

If only QUEUES are configured in the Limit section, MEM must be an integer value. MEM is the maximum amount of memory available to the listed queues for any hosts, users, or projects.

If only USERS are configured in the Limit section, MEM must be an integer value. MEM is the maximum amount of memory that the users or user groups can use on any hosts, queues, or projects.

If only HOSTS are configured in the Limit section, MEM must be an integer value. It cannot be a percentage. MEM is the maximum amount of memory available to the listed hosts for any users, queues, or projects.

If only PROJECTS are configured in the Limit section, MEM must be an integer value. MEM is the maximum amount of memory available to the listed projects for any users, queues, or hosts.

Use QUEUES or PER\_QUEUE, USERS or PER\_USER, HOSTS or PER\_HOST, and PROJECTS or PER\_PROJECT in combination to further limit memory available to resource consumers.

## Default

No limit

## Example

```
MEM=20
```

## NAME

## Syntax

**NAME**=*limit\_name*

**NAME**

- | *limit\_name*

## Description

Name of the Limit section

Specify any ASCII string 40 characters or less. You can use letters, digits, underscores (\_) or dashes (-). You cannot use blank spaces.

If duplicate limit names are defined, the Limit section is ignored. If value of NAME is not defined in vertical format, or defined as (-), `bl i m i s` displays `NONAMEnnn`.

## Default

None. In horizontal format, you must provide a name for the Limit section. NAME is optional in the vertical format.

## Example

```
NAME=short_l i m i t s
```

## PER\_HOST

### Syntax

```
PER_HOST=all [~]host_name ... | all [~]host_group ...
```

```
PER_HOST
```

```
( [-] | all [~]host_name ... | all [~]host_group ... )
```

## Description

A space-separated list of host or host groups defined in `lsb. hosts` on which limits are enforced. Limits are enforced on each host or individually to each host of the host group listed. If a group contains a subgroup, the limit also applies to each member in the subgroup recursively.

Do not configure PER\_HOST and HOSTS limits in the same Limit section.

In horizontal format, use only one PER\_HOST line per Limit section.

If you specify MEM, TMP, or SWP as a percentage, you must specify PER\_HOST and list the hosts that the limit is to be enforced on. You cannot specify HOSTS.

Use the keyword `all` to configure limits that apply to each host in a cluster. If host groups are configured, the limit applies to each member of the host group, not the group as a whole.

Use the not operator (`~`) to exclude hosts or host groups from the `all` specification in the limit. This is useful if you have a large cluster but only want to exclude a few hosts from the limit definition.

In vertical tabular format, multiple host names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate each host or host group member. Fields cannot be left blank.

## Default

None. If no limit is specified for PER\_HOST or HOST, no limit is enforced on any host or host group.

## Example

```
PER_HOST=hostA hgroup1 ~hostC
```

## PER\_PROJECT

### Syntax

```
PER_PROJECT=all [~]project_name ...
```

```
PER_PROJECT
```

```
( [-] | all [~]project_name ... )
```

### Description

A space-separated list of project names on which limits are enforced. Limits are enforced on each project listed.

Do not configure PER\_PROJECT and PROJECTS limits in the same Limit section.

In horizontal format, use only one PER\_PROJECT line per Limit section.

Use the keyword all to configure limits that apply to each project in a cluster.

Use the not operator (~) to exclude projects from the all specification in the limit.

In vertical tabular format, multiple project names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate each project. Fields cannot be left blank.

### Default

None. If no limit is specified for PER\_PROJECT or PROJECTS, no limit is enforced on any project.

### Example

```
PER_PROJECT=proj 1 proj 2
```

## PER\_QUEUE

### Syntax

```
PER_QUEUE=all [~]queue_name ..
```

```
PER_QUEUE
```

```
( [-] | all [~]queue_name ... )
```

### Description

A space-separated list of queue names on which limits are enforced. Limits are enforced on jobs submitted to each queue listed.

Do not configure PER\_QUEUE and QUEUES limits in the same Limit section.

In horizontal format, use only one PER\_QUEUE line per Limit section.

Use the keyword all to configure limits that apply to each queue in a cluster.

Use the not operator (~) to exclude queues from the all specification in the limit. This is useful if you have a large number of queues but only want to exclude a few queues from the limit definition.

In vertical tabular format, multiple queue names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate each queue. Fields cannot be left blank.

## Default

None. If no limit is specified for PER\_QUEUE or QUEUES, no limit is enforced on any queue.

## Example

```
PER_QUEUE=pri or i ty ni ght
```

## PER\_USER

### Syntax

```
PER_USER=all [~]user_name ... | all [~]user_group ...
```

```
PER_USER
```

```
( [-] | all [~]user_name ... | all [~]user_group ... )
```

## Description

A space-separated list of user names or user groups on which limits are enforced. Limits are enforced on each user or individually to each user in the user group listed. If a user group contains a subgroup, the limit also applies to each member in the subgroup recursively.

User names must be valid login names. User group names can be LSF user groups or UNIX and Windows user groups. Note that for LSF and UNIX user groups, the groups must be specified in a UserGroup section in lsb.users first.

Do not configure PER\_USER and USERS limits in the same Limit section.

In horizontal format, use only one PER\_USER line per Limit section.

Use the keyword all to configure limits that apply to each user in a cluster. If user groups are configured, the limit applies to each member of the user group, not the group as a whole.

Use the not operator (~) to exclude users or user groups from the all specification in the limit. This is useful if you have a large number of users but only want to exclude a few users from the limit definition.

In vertical tabular format, multiple user names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses () or a dash (-) to indicate user or user group member. Fields cannot be left blank.

## Default

None. If no limit is specified for PER\_USER or USERS, no limit is enforced on any user or user group.

## Example

```
PER_USER=user1 user2 ugroup1 ~user3
```

## PROJECTS

### Syntax

```
PROJECTS=all [~]project_name ...
```

```
PROJECTS
```

```
( [-] | all [~]project_name ... )
```

### Description

A space-separated list of project names on which limits are enforced. Limits are enforced on all projects listed.

To specify a per-project limit, use the `PER_PROJECT` keyword. Do not configure `PROJECTS` and `PER_PROJECT` limits in the same Limit section.

In horizontal format, use only one `PROJECTS` line per Limit section.

Use the keyword `all` to configure limits that apply to all projects in a cluster.

Use the not operator (`~`) to exclude projects from the all specification in the limit. This is useful if you have a large number of projects but only want to exclude a few projects from the limit definition.

In vertical tabular format, multiple project names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses `()` or a dash `(-)` to indicate all projects. Fields cannot be left blank.

### Default

all (limits are enforced on all projects in the cluster)

### Example

```
PROJECTS=proj A proj B
```

## QUEUES

### Syntax

```
QUEUES=all [~]queue_name ...
```

```
QUEUES
```

```
( [-] | all [~]queue_name ... )
```

### Description

A space-separated list of queue names on which limits are enforced. Limits are enforced on all queues listed.

The list must contain valid queue names defined in `lsb.queues`.

To specify a per-queue limit, use the `PER_QUEUE` keyword. Do not configure `QUEUES` and `PER_QUEUE` limits in the same Limit section.

In horizontal format, use only one `QUEUES` line per Limit section.

Use the keyword `all` to configure limits that apply to all queues in a cluster.

Use the not operator (`~`) to exclude queues from the `all` specification in the limit. This is useful if you have a large number of queues but only want to exclude a few queues from the limit definition.

In vertical tabular format, multiple queue names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses `()` or a dash `(-)` to indicate all queues. Fields cannot be left blank.

## Default

`all` (limits are enforced on all queues in the cluster)

## Example

```
QUEUES=normal ni ght
```

## RESOURCE

### Syntax

**RESOURCE**=[*shared\_resource,integer*] [*shared\_resource,integer*] ...]

**RESOURCE**

( [*shared\_resource,integer*] [*shared\_resource,integer*] ... ] )

## Description

Maximum amount of any user-defined shared resource available to consumers.

The `RESOURCE` keyword is a synonym for the `LICENSE` keyword. You can use `RESOURCE` to configure software licenses. You cannot specify `RESOURCE` and `LICENSE` in the same Limit section.

In horizontal format, use only one `RESOURCE` line per Limit section.

In vertical tabular format, resource names must be enclosed in parentheses.

In vertical tabular format, use empty parentheses `()` or a dash `(-)` to indicate all queues. Fields cannot be left blank.

## Default

None

## Examples

```
RESOURCE=[ stat_shared, 4]
Begin Limit
RESOURCE                PER_HOST
([stat_shared, 4])      (all ~hostA)
([dyn_rsrc, 1] [stat_rsrc, 2]) (hostA)
End Limit
```

# SLOTS

## Syntax

**SLOTS**=*integer*

**SLOTS**

- | *integer*

## Description

Maximum number of job slots available to resource consumers. Specify a positive integer greater than or equal 0.

With MultiCluster resource lease model, this limit applies only to local hosts being used by the local cluster. The job slot limit for hosts exported to a remote cluster is determined by the host export policy, not by this parameter. The job slot limit for borrowed hosts is determined by the host export policy of the remote cluster.

If JOBS are configured in the Limit section, the most restrictive limit is applied.

If HOSTS are configured in the Limit section, SLOTS is the number of running and suspended jobs on a host. If preemptive scheduling is used, the suspended jobs are not counted as using a job slot.

To fully use the CPU resource on multiprocessor hosts, make the number of job slots equal to or greater than the number of processors.

Use this parameter to prevent a host from being overloaded with too many jobs, and to maximize the throughput of a machine.

Use “!” to make the number of job slots equal to the number of CPUs on a host.

If the number of CPUs in a host changes dynamically, `mbat chd` adjusts the maximum number of job slots per host accordingly. Allow the `mbat chd` up to 10 minutes to get the number of CPUs for a host. During this period the value of SLOTS is 1.

If only QUEUES are configured in the Limit section, SLOTS is the maximum number of job slots available to the listed queues for any hosts, users, or projects.

If only USERS are configured in the Limit section, SLOTS is the maximum number of job slots that the users or user groups can use on any hosts, queues, or projects.

If only HOSTS are configured in the Limit section, SLOTS is the maximum number of job slots that are available to the listed hosts for any users, queues, or projects.

If only PROJECTS are configured in the Limit section, SLOTS is the maximum number of job slots that are available to the listed projects for any users, queues, or hosts.

Use QUEUES or PER\_QUEUE, USERS or PER\_USER, HOSTS or PER\_HOST, and PROJECTS or PER\_PROJECT in combination to further limit job slots per processor available to resource consumers.

In horizontal format, use only one SLOTS line per Limit section.

In vertical format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

## Default

No limit

## Example

```
SLOTS=20
```

## SLOTS\_PER\_PROCESSOR

### Syntax

**SLOTS\_PER\_PROCESSOR**=*number*

**SLOTS\_PER\_PROCESSOR**

- | *number*

### Description

Per processor job slot limit, based on the number of processors on each host affected by the limit.

Maximum number of job slots that each resource consumer can use per processor. This job slot limit is configured per processor so that multiprocessor hosts will automatically run more jobs.

You must also specify PER\_HOST and list the hosts that the limit is to be enforced on. The Limit section is ignored if SLOTS\_PER\_PROCESSOR is specified:

- Without PER\_HOST, or
- With HOSTS

In vertical format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

To fully use the CPU resource on multiprocessor hosts, make the number of job slots equal to or greater than the number of processors.

Use this parameter to prevent a host from being overloaded with too many jobs, and to maximize the throughput of a machine.

This number can be a fraction such as 0.5, so that it can also serve as a per-CPU limit on multiprocessor machines. This number is rounded up to the nearest integer equal to or greater than the total job slot limits for a host. For example, if SLOTS\_PER\_PROCESSOR is 0.5, on a 4-CPU multiprocessor host, users can only use up to 2 job slots at any time. On a single-processor machine, users can use 1 job slot.

Use “!” to make the number of job slots equal to the number of CPUs on a host.

If the number of CPUs in a host changes dynamically, mbatchd adjusts the maximum number of job slots per host accordingly. Allow the mbatchd up to 10 minutes to get the number of CPUs for a host. During this period the number of CPUs is 1.

If only QUEUES and PER\_HOST are configured in the Limit section, SLOTS\_PER\_PROCESSOR is the maximum amount of job slots per processor available to the listed queues for any hosts, users, or projects.

If only `USERS` and `PER_HOST` are configured in the Limit section, `SLOTS_PER_PROCESSOR` is the maximum amount of job slots per processor that the users or user groups can use on any hosts, queues, or projects.

If only `PER_HOST` is configured in the Limit section, `SLOTS_PER_PROCESSOR` is the maximum amount of job slots per processor available to the listed hosts for any users, queues, or projects.

If only `PROJECTS` and `PER_HOST` are configured in the Limit section, `SLOTS_PER_PROCESSOR` is the maximum amount of job slots per processor available to the listed projects for any users, queues, or hosts.

Use `QUEUES` or `PER_QUEUE`, `USERS` or `PER_USER`, `PER_HOST`, and `PROJECTS` or `PER_PROJECT` in combination to further limit job slots per processor available to resource consumers.

## Default

No limit

## Example

```
SLOTS_PER_PROCESSOR=2
```

## SWP

## Syntax

**SWP**=*integer*[%]

**SWP**

- | *integer*[%]

## Description

Maximum amount of swap space available to resource consumers. Specify a value in MB or a percentage (%) as a positive integer greater than or equal 0. If you specify a percentage, you must also specify `PER_HOST` and list the hosts that the limit is to be enforced on.

The Limit section is ignored if `SWP` is specified as a percentage:

- Without `PER_HOST`, or
- With `HOSTS`

In horizontal format, use only one `SWP` line per Limit section.

In vertical format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

If only `QUEUES` are configured in the Limit section, `SWP` must be an integer value. `SWP` is the maximum amount of swap space available to the listed queues for any hosts, users, or projects.

If only `USERS` are configured in the Limit section, `SWP` must be an integer value. `SWP` is the maximum amount of swap space that the users or user groups can use on any hosts, queues, or projects.

If only `HOSTS` are configured in the Limit section, `SWP` must be an integer value. `SWP` is the maximum amount of swap space available to the listed hosts for any users, queues, or projects.

If only PROJECTS are configured in the Limit section, SWP must be an integer value. SWP is the maximum amount of swap space available to the listed projects for any users, queues, or hosts.

Use QUEUES or PER\_QUEUE, USERS or PER\_USER, HOSTS or PER\_HOST, and PROJECTS or PER\_PROJECT in combination to further limit swap space available to resource consumers.

## Default

No limit

## Example

```
SWP=60
```

## TMP

### Syntax

**TMP**=*integer*[%]

**TMP**

- | *integer*[%]

## Description

Maximum amount of `tmp` space available to resource consumers. Specify a value in MB or a percentage (%) as a positive integer greater than or equal 0. If you specify a percentage, you must also specify PER\_HOST and list the hosts that the limit is to be enforced on.

The Limit section is ignored if TMP is specified as a percentage:

- Without PER\_HOST, or
- With HOSTS

In horizontal format, use only one TMP line per Limit section.

In vertical format, use empty parentheses () or a dash (-) to indicate the default value (no limit). Fields cannot be left blank.

If only QUEUES are configured in the Limit section, TMP must be an integer value. TMP is the maximum amount of `tmp` space available to the listed queues for any hosts, users, or projects.

If only USERS are configured in the Limit section, TMP must be an integer value. TMP is the maximum amount of `tmp` space that the users or user groups can use on any hosts, queues, or projects.

If only HOSTS are configured in the Limit section, TMP must be an integer value. TMP is the maximum amount of `tmp` space available to the listed hosts for any users, queues, or projects.

If only PROJECTS are configured in the Limit section, TMP must be an integer value. TMP is the maximum amount of `tmp` space available to the listed projects for any users, queues, or hosts.

Use QUEUES or PER\_QUEUE, USERS or PER\_USER, HOSTS or PER\_HOST, and PROJECTS or PER\_PROJECT in combination to further limit `tmp` space available to resource consumers.

## Default

No limit

## Example

```
TMP=20%
```

## USERS

### Syntax

```
USERS=all [~]user_name ... | all [~]user_group ...
```

**USERS**

```
( [-] | all [~]user_name ... | all [~]user_group ... )
```

## Description

A space-separated list of user names or user groups on which limits are enforced. Limits are enforced on all users or groups listed. Limits apply to a group as a whole.

If a group contains a subgroup, the limit also applies to each member in the subgroup recursively.

User names must be valid login names. User group names can be LSF user groups or UNIX and Windows user groups.

To specify a per-user limit, use the PER\_USER keyword. Do not configure USERS and PER\_USER limits in the same Limit section.

In horizontal format, use only one USERS line per Limit section.

Use the keyword all to configure limits that apply to all users or user groups in a cluster.

Use the not operator (~) to exclude users or user groups from the all specification in the limit. This is useful if you have a large number of users but only want to exclude a few users or groups from the limit definition.

In vertical format, multiple user names must be enclosed in parentheses.

In vertical format, use empty parentheses () or a dash (-) to indicate all users or groups. Fields cannot be left blank.

## Default

all (limits are enforced on all users in the cluster)

## Example

```
USERS=user1 user2
```

## HostExport section

Defines an export policy for a host or a group of related hosts. Defines how much of each host's resources are exported, and how the resources are distributed among the consumers.

Each export policy is defined in a separate HostExport section, so it is normal to have multiple HostExport sections in lsb.resources.

## HostExport section structure

Use empty parentheses () or a dash (-) to specify the default value for an entry. Fields cannot be left blank.

## Example HostExport section

```
Begin HostExport PER_HOST= hostA hostB SLOTS= 4 DISTRIBUTION= [cluster1, 1]
[cluster2, 3] MEM= 100 SWAP= 100 End HostExport
```

## Parameters

- PER\_HOST
- RES\_SELECT
- NHOSTS
- DISTRIBUTION
- MEM
- SLOTS
- SWAP
- TYPE

## PER\_HOST

### Syntax

**PER\_HOST**=*host\_name...*

### Description

Required when exporting special hosts.

Determines which hosts to export. Specify one or more LSF hosts by name. Separate names by space.

## RES\_SELECT

### Syntax

**RES\_SELECT**=*res\_req*

### Description

Required when exporting workstations.

Determines which hosts to export. Specify the selection part of the resource requirement string (without quotes or parentheses), and LSF will automatically select hosts that meet the specified criteria. For this parameter, if you do not specify the required host type, the default is `type==any`.

When `LSF_STRICT_RESREQ=Y` is configured in `lsf.conf`, resource requirement strings in select sections must conform to a more strict syntax. The strict resource requirement syntax only applies to the select section. It does not apply to the other resource requirement sections (`order`, `rusage`, `same`, `span`, or `cu`). When `LSF_STRICT_RESREQ=Y` in `lsf.conf`, LSF rejects resource requirement strings where a `rusage` section contains a non-consumable resource.

The criteria is only evaluated once, when a host is exported.

## NHOSTS

### Syntax

**NHOSTS**=*integer*

### Description

Required when exporting workstations.

Maximum number of hosts to export. If there are not this many hosts meeting the selection criteria, LSF exports as many as it can.

## DISTRIBUTION

### Syntax

**DISTRIBUTION**=(*[cluster\_name, number\_shares]...*)

### Description

Required. Specifies how the exported resources are distributed among consumer clusters.

The syntax for the distribution list is a series of share assignments. The syntax of each share assignment is the cluster name, a comma, and the number of shares, all enclosed in square brackets, as shown. Use a space to separate multiple share assignments. Enclose the full distribution list in a set of round brackets.

*cluster\_name*

Specify the name of a remote cluster that will be allowed to use the exported resources. If you specify a local cluster, the assignment is ignored.

*number\_shares*

Specify a positive integer representing the number of shares of exported resources assigned to the cluster.

The number of shares assigned to a cluster is only meaningful when you compare it to the number assigned to other clusters, or to the total number. The total number of shares is just the sum of all the shares assigned in each share assignment.

## MEM

### Syntax

**MEM**=*megabytes*

### Description

Used when exporting special hosts. Specify the amount of memory to export on each host, in MB.

### Default

- (provider and consumer clusters compete for available memory)

## SLOTS

### Syntax

**SLOTS=*integer***

### Description

Required when exporting special hosts. Specify the number of job slots to export on each host. To avoid overloading a partially exported host, you can reduce the number of job slots in the configuration of the local cluster.

## SWAP

### Syntax

**SWAP=*megabytes***

### Description

Used when exporting special hosts. Specify the amount of swap space to export on each host, in MB.

### Default

- (provider and consumer clusters compete for available swap space)

## TYPE

### Syntax

**TYPE=*shared***

### Description

Changes the lease type from exclusive to shared. If you export special hosts with a shared lease (using PER\_HOST), you cannot specify multiple consumer clusters in the distribution policy.

### Default

Undefined (the lease type is exclusive; exported resources are never available to the provider cluster)

## SharedResourceExport section

Optional. Requires HostExport section. Defines an export policy for a shared resource. Defines how much of the shared resource is exported, and the distribution among the consumers.

The shared resource must be available on hosts defined in the HostExport sections.

## SharedResourceExport section structure

All parameters are required.

## Example SharedResourceExport section

```
Begin SharedResourceExport
NAME= AppLicense
NINSTANCES= 10
DISTRIBUTION= ([C1, 30] [C2, 70])
End SharedResourceExport
```

### Parameters

- NAME
- NINSTANCES
- DISTRIBUTION

### NAME

#### Syntax

**NAME**=*shared\_resource\_name*

#### Description

Shared resource to export. This resource must be available on the hosts that are exported to the specified clusters; you cannot export resources without hosts.

### NINSTANCES

#### Syntax

**NINSTANCES**=*integer*

#### Description

Maximum quantity of shared resource to export. If the total number available is less than the requested amount, LSF exports all that are available.

### DISTRIBUTION

#### Syntax

**DISTRIBUTION**=(*[cluster\_name, number\_shares]...*)

#### Description

Specifies how the exported resources are distributed among consumer clusters.

The syntax for the distribution list is a series of share assignments. The syntax of each share assignment is the cluster name, a comma, and the number of shares, all enclosed in square brackets, as shown. Use a space to separate multiple share assignments. Enclose the full distribution list in a set of round brackets.

*cluster\_name*

Specify the name of a cluster allowed to use the exported resources.

*number\_shares*

Specify a positive integer representing the number of shares of exported resources assigned to the cluster.

The number of shares assigned to a cluster is only meaningful when you compare it to the number assigned to other clusters, or to the total number. The total number of shares is the sum of all the shares assigned in each share assignment.

## ResourceReservation section

By default, only LSF administrators or root can add or delete advance reservations.

The ResourceReservation section defines an advance reservation policy. It specifies:

- Users or user groups that can create reservations
- Hosts that can be used for the reservation
- Time window when reservations can be created

Each advance reservation policy is defined in a separate ResourceReservation section, so it is normal to have multiple ResourceReservation sections in `lsb.resources`.

## Example ResourceReservation section

Only user1 and user2 can make advance reservations on hostA and hostB. The reservation time window is between 8:00 a.m. and 6:00 p.m. every day:

```
Begin ResourceReservation
NAME = dayPolicy
USERS = user1 user2 # optional
HOSTS = hostA hostB # optional
TIME_WINDOW = 8:00-18:00 # weekly recurring reservation
End ResourceReservation
```

user1 can add the following reservation for user user2 to use on hostA every Friday between 9:00 a.m. and 11:00 a.m.:

```
% user1@hostB> brsvadd -m "hostA" -n 1 -u "user2" -t "5:9:0-5:11:0"
Reservation "user2#2" is created
```

Users can only delete reservations they created themselves. In the example, only user user1 can delete the reservation; user2 cannot. Administrators can delete any reservations created by users.

## Parameters

- HOSTS
- NAME
- TIME\_WINDOW
- USERS

## HOSTS

### Syntax

```
HOSTS=[~]host_name | [~]host_group | all | allremote | all@cluster_name ...
```

## Description

A space-separated list of hosts, host groups defined in `lsb.hosts` on which administrators or users specified in the `USERS` parameter can create advance reservations.

The hosts can be local to the cluster or hosts leased from remote clusters.

If a group contains a subgroup, the reservation configuration applies to each member in the subgroup recursively.

Use the keyword `all` to configure reservation policies that apply to all local hosts in a cluster not explicitly excluded. This is useful if you have a large cluster but you want to use the not operator (`~`) to exclude a few hosts from the list of hosts where reservations can be created.

Use the keyword `allremote` to specify all hosts borrowed from all remote clusters.

---

### Tip:

You cannot specify host groups or host partitions that contain the `allremote` keyword.

---

Use `all@cluster_name` to specify the group of all hosts borrowed from one remote cluster. You cannot specify a host group or partition that includes remote resources.

With MultiCluster resource leasing model, the not operator (`~`) can be used to exclude local hosts or host groups. You cannot use the not operator (`~`) with remote hosts.

## Examples

```
HOSTS=hgroup1 ~hostA hostB hostC
```

Advance reservations can be created on host B, host C, and all hosts in `hgroup1` except for host A.

```
HOSTS=all ~group2 ~hostA
```

Advance reservations can be created on all hosts in the cluster, except for host A and the hosts in `group2`.

## Default

all `allremote` (users can create reservations on all server hosts in the local cluster, and all leased hosts in a remote cluster).

## NAME

## Syntax

**NAME**=*text*

## Description

Required. Name of the ResourceReservation section

Specify any ASCII string 40 characters or less. You can use letters, digits, underscores (`_`) or dashes (`-`). You cannot use blank spaces.

## Example

```
NAME=reservation1
```

## Default

None. You must provide a name for the ResourceReservation section.

## TIME\_WINDOW

### Syntax

```
TIME_WINDOW=time_window...
```

### Description

Optional. Time window for users to create advance reservations. The time for reservations that users create must fall within this time window.

Use the same format for *time\_window* as the recurring reservation option (-t) of brsvadd. To specify a time window, specify two time values separated by a hyphen (-), with no space in between:

```
time_window = begin_time-end_time
```

### Time format

Times are specified in the format:

```
[day: ]hour[:minute]
```

where all fields are numbers with the following ranges:

- *day of the week*: 0-6 (0 is Sunday)
- *hour*: 0-23
- *minute*: 0-59

Specify a time window one of the following ways:

- *hour-hour*
- *hour.minute-hour.minute*
- *day.hour.minute-day.hour.minute*

The default value for minute is 0 (on the hour); the default value for day is every day of the week.

You must specify at least the hour. Day of the week and minute are optional. Both the start time and end time values must use the same syntax. If you do not specify a minute, LSF assumes the first minute of the hour (: 00). If you do not specify a day, LSF assumes every day of the week. If you do specify the day, you must also specify the minute.

You can specify multiple time windows, but they cannot overlap. For example:

```
timeWindow(8: 00- 14: 00 18: 00- 22: 00)
```

is correct, but

```
timeWindow(8: 00- 14: 00 11: 00- 15: 00)
```

is not valid.

### Example

```
TIME_WINDOW=8: 00- 14: 00
```

Users can create advance reservations with begin time (brsvadd -b), end time (brsvadd -e), or time window (brsvadd -t) on any day between 8:00 a.m. and 2:00 p.m.

## Default

Undefined (any time)

## USERS

### Syntax

```
USERS=[~]user_name | [~]user_group ... | all
```

### Description

A space-separated list of user names or user groups who are allowed to create advance reservations. Administrators, root, and all users or groups listed can create reservations.

If a group contains a subgroup, the reservation policy applies to each member in the subgroup recursively.

User names must be valid login names. User group names can be LSF user groups or UNIX and Windows user groups.

Use the keyword `all` to configure reservation policies that apply to all users or user groups in a cluster. This is useful if you have a large number of users but you want to exclude a few users or groups from the reservation policy.

Use the not operator (`~`) to exclude users or user groups from the list of users who can create reservations.

---

#### Caution:

The not operator does not exclude LSF administrators from the policy.

---

### Example

```
USERS=user1 user2
```

## Default

`all` (all users in the cluster can create reservations)

## ReservationUsage section

To enable greater flexibility for reserving numeric resources that are reserved by jobs, configure the `ReservationUsage` section in `lsb.resources` to reserve resources like license tokens per resource as `PER_JOB`, `PER_SLOT`, or `PER_HOST`. For example:

### Example ReservationUsage section

```
Begin ReservationUsage
RESOURCE          METHOD          RESERVE
LicenseX          PER_JOB          Y
LicenseY          PER_HOST          N
LicenseZ          PER_SLOT          N
End ReservationUsage
```

## Parameters

- RESOURCE
- METHOD
- RESERVE

## RESOURCE

The name of the resource to be reserved. User-defined numeric resources can be reserved, but only if they are shared (they are not specific to one host).

The following built-in resources can be configured in the `ReservationUsage` section and reserved:

- mem
- tmp
- swp

Any custom resource can also be reserved if it is shared (defined in the `Resource` section of `lsf.shared`) or host based (listed in the `Host` section of the `lsf.cluster` file in the resource column).

## METHOD

The resource reservation method. One of:

- PER\_JOB
- PER\_HOST
- PER\_SLOT

The cluster-wide `RESOURCE_RESERVE_PER_SLOT` parameter in `lsb.params` is obsolete.

`RESOURCE_RESERVE_PER_SLOT` parameter still controls resources not configured in `lsb.resources`. Resources not reserved in `lsb.resources` are reserved per job.

`PER_HOST` reservation means that for the parallel job, LSF reserves one instance of a for each host. For example, some application licenses are charged only once no matter how many applications are running provided those applications are running on the same host under the same user.

Use no method ("-") when setting mem, swp, or tmp as `RESERVE=Y`.

## RESERVE

Reserves the resource for pending jobs that are waiting for another resource to become available.

For example, job A requires resources X, Y, and Z to run, but resource Z is a high demand or scarce resource. This job pends until Z is available. In the meantime, other jobs requiring only X and Y resources run. If X and Y are set as reservable resources (the `RESERVE` parameter is set to "Y"), as soon as Z resource is available, job A runs. If they are not, job A may never be able to run because all resources are never available at the same time.

---

### Restriction:

Only the following built-in resources can be defined as reservable:

- mem
  - swp
  - tmp
- 

Use no method ("-") when setting mem, swp, or tmp as RESERVE=Y.

When submitting a job, the queue must have RESOURCE\_RESERVE defined.

Backfill of the reservable resources is also supported when you submit a job with reservable resources to a queue with BACKFILL defined.

Valid values are Y and N. If not specified, resources are not reserved.

## Assumptions and limitations

- Per-resource configuration defines resource usage for individual resources, but it does not change any existing resource limit behavior (PER\_JOB, PER\_SLOT).
- In a MultiCluster environment, you should configure resource usage in the scheduling cluster (submission cluster in lease model or receiving cluster in job forward model).

## Automatic time-based configuration

Variable configuration is used to automatically change LSF configuration based on time windows. You define automatic configuration changes in `lsb.resources` by using if-else constructs and time expressions. After you change the files, reconfigure the cluster with the `badm n reconfi g` command.

The expressions are evaluated by LSF every 10 minutes based on `mbatchd` start time. When an expression evaluates true, LSF dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting `mbatchd`, providing continuous system availability.

## Example

```

# limit usage of hosts in 'license1' group and time
# based configuration
# - 10 jobs can run from normal queue
# - any number can run from short queue between 18:30
#   and 19:30
# all other hours you are limited to 100 slots in the
# short queue
# - each other queue can run 30 jobs

Begin Limit
PER_QUEUE          HOSTS          SLOTS      # Example
normal             license1      10
# if time(18:30-19:30)
short              license1      -
#else
short              license1      100
#endif
(all ~normal ~short) license1      30
End Limit

```

# lsb.serviceclasses

The `lsb.serviceclasses` file defines the service-level agreements (SLAs) in an LSF cluster as *service classes*, which define the properties of the SLA.

This file is optional.

You can configure as many service class sections as you need.

Use `bsl a` to display the properties of service classes configured in `lsb.serviceclasses` and dynamic information about the state of each configured service class.

By default, `lsb.serviceclasses` is installed in `LSB_CONFDIR/cluster_name/configdir`.

## Changing lsb.serviceclasses configuration

After making any changes to `lsb.serviceclasses`, run `badm n reconfi g` to reconfigure `mbatchd`.

## lsb.serviceclasses structure

Each service class definition begins with the line `Begin ServiceClass` and ends with the line `End ServiceClass`.

### Syntax

```
Begin ServiceClass
NAME           = string
PRIORITY      = integer
GOALS         = [ throughput | velocity | deadline ] [ \
                [ throughput | velocity | deadline ] ... ]
CONTROL_ACTION = VIOLATION_PERIOD[minutes] CMD [ action ]
USER_GROUP    = all | [ user_name ] [ user_group ] ...
DESCRIPTION   = text
End ServiceClass
```

You must specify:

- Service class name
- Goals
- Priority

To configure EGO-enabled SLA scheduling, you must specify an existing EGO consumer name to allow the SLA to get host allocations from EGO.

All other parameters are optional.

### Example

```
Begin ServiceClass
NAME=Uclulet
PRIORITY=20
GOALS=[DEADLINE timeWindow (8:30-16:00)]
DESCRIPTION="working hours"
End ServiceClass
```

## Parameters

- CONSUMER
- CONTROL\_ACTION
- DESCRIPTION
- EGO\_RES\_REQ
- GOALS
- MAX\_HOST\_IDLE\_TIME
- NAME
- PRIORITY
- USER\_GROUP

## CONSUMER

### Syntax

**CONSUMER**=*ego\_consumer\_name*

### Description

For EGO-enabled SLA service classes, the name of the EGO consumer from which hosts are allocated to the SLA. This parameter is not mandatory, but must be configured for the SLA to receive hosts from EGO.

---

#### Important:

CONSUMER must specify the name of a valid consumer in EGO. If a default SLA is configured with ENABLE\_DEFAULT\_EGO\_SLA in `lsb.params`, all services classes configured in `lsb.serviceclasses` must specify a consumer name.

---

### Default

None

## CONTROL\_ACTION

### Syntax

**CONTROL\_ACTION**=VIOLATION\_PERIOD[*minutes*] CMD [*action*]

### Description

Optional. Configures a control action to be run if the SLA goal is delayed for a specified number of minutes.

If the SLA goal is delayed for longer than VIOLATION\_PERIOD, the action specified by CMD is invoked. The violation period is reset and if the SLA is still active when the violation period expires again, the action runs again. If the SLA has multiple active goals that are in violation, the action is run for each of them.

### Example

```
CONTROL_ACTION=VIOLATION_PERIOD[10] CMD [echo `date`: SLA is in violation
>> ! /tmp/sla_violation.log]
```

## Default

None

## DESCRIPTION

### Syntax

**DESCRIPTION**=*text*

### Description

Optional. Description of the service class. Use `bsl a` to display the description text.

This description should clearly describe the features of the service class to help users select the proper service class for their jobs.

The text can include any characters, including white space. The text can be extended to multiple lines by ending the preceding line with a backslash (`\`).

## Default

None

## EGO\_RES\_REQ

### Syntax

**EGO\_RES\_REQ**=*res\_req*

### Description

For EGO-enabled SLA service classes, the EGO resource requirement that specifies the characteristics of the hosts that EGO will assign to the SLA.

Must be a valid EGO resource requirement. The EGO resource requirement string supports the `select` section, but the format is different from LSF resource requirements.

### Example

```
EGO_RES_REQ=select (linux && maxmem > 100)
```

## Default

None

## GOALS

### Syntax

**GOALS**=[*throughput* | *velocity* | *deadline*] [*\*  
[*throughput* | *velocity* | *deadline*] ...]

### Description

*Required.* Defines the service-level goals for the service class. A service class can have more than one goal, each active at different times of the day and days of the week. Outside of the

time window, the SLA is inactive and jobs are scheduled as if no service class is defined. LSF does not enforce any service-level goal for an inactive SLA.

The time windows of multiple service-level goals can overlap. In this case, the largest number of jobs is run.

An active SLA can have a status of On time if it is meeting the goal, and a status Delayed, if it is missing its goals.

A service-level goal defines:

*throughput* — expressed as *finished* jobs per hour and an optional time window when the goal is active. *throughput* has the form:

```
GOALS=[THROUGHPUT num_jobs timeWindow [(time_window)]]
```

If no time window is configured, THROUGHPUT can be the only goal in the service class. The service class is always active, and bsl a displays ACTIVE WINDOW: Always Open.

*velocity* — expressed as *concurrently* running jobs and an optional time window when the goal is active. *velocity* has the form:

```
GOALS=[VELOCITY num_jobs timeWindow [(time_window)]]
```

If no time window is configured, VELOCITY can be the only goal in the service class. The service class is always active, and bsl a displays ACTIVE WINDOW: Always Open.

*deadline* — indicates that all jobs in the service class should complete by the end of the specified time window. The time window is required for a deadline goal. *deadline* has the form:

```
GOALS=[DEADLINE timeWindow (time_window)]
```

---

### Restriction:

EGO-enabled SLA service classes only support velocity goals. Deadline and throughput goals are not supported. The configured velocity value for EGO-enabled SLA service classes is considered to be a *minimum* number of jobs that should be in run state from the SLA

---

## Time window format

The time window of an SLA goal has the standard form:

```
begin_time-end_time
```

Times are specified in the format:

```
[ day: ] hour[: minute]
```

where all fields are numbers with the following ranges:

- *day of the week*: 0-6 (0 is Sunday)
- *hour*: 0-23
- *minute*: 0-59

Specify a time window one of the following ways:

- *hour-hour*
- *hour.minute-hour.minute*
- *day.hour.minute-day.hour.minute*

The default value for minute is 0 (on the hour); the default value for day is every day of the week.

You must specify at least the hour. Day of the week and minute are optional. Both the start time and end time values must use the same syntax. If you do not specify a minute, LSF assumes the first minute of the hour (: 00). If you do not specify a day, LSF assumes every day of the week. If you do specify the day, you must also specify the minute.

You can specify multiple time windows, but they cannot overlap. For example:

```
timeWindow(8:00-14:00 18:00-22:00)
```

is correct, but

```
timeWindow(8:00-14:00 11:00-15:00)
```

is not valid.

---

### Tip:

To configure a time window that is always open, use the `timeWindow` keyword with empty parentheses.

---

## Examples

```
GOALS=[THROUGHPUT 2 timeWindow ()]
```

```
GOALS=[THROUGHPUT 10 timeWindow (8:30-16:30)]
```

```
GOALS=[VELOCITY 5 timeWindow ()]
```

```
GOALS=[DEADLINE timeWindow (16:30-8:30)] \
```

```
[VELOCITY 10 timeWindow (8:30-16:30)]
```

## MAX\_HOST\_IDLE\_TIME

### Syntax

**MAX\_HOST\_IDLE\_TIME**=*seconds*

### Description

For EGO-enabled SLA service classes, number of seconds that the SLA will hold its idle hosts before LSF releases them to EGO. Each SLA can configure a different idle time. Do not set this parameter to a small value, or LSF may release hosts too quickly.

### Default

120 seconds

### NAME

### Syntax

**NAME**=*string*

### Description

*Required.* A unique name that identifies the service class.

Specify any ASCII string 60 characters or less. You can use letters, digits, underscores (`_`) or dashes (`-`). You cannot use blank spaces.

---

### Important:

The name you use cannot be the same as an existing host partition, user group name, or fairshare queue name.

## Example

```
NAME=Tofino
```

## Default

None. You must provide a unique name for the service class.

## PRIORITY

### Syntax

**PRIORITY**=*integer*

## Description

*Required.* The service class priority. A higher value indicates a higher priority, relative to other service classes. Similar to queue priority, service classes access the cluster resources in priority order.

LSF schedules jobs from one service class at a time, starting with the highest-priority service class. If multiple service classes have the same priority, LSF runs all the jobs from these service classes in first-come, first-served order.

Service class priority in LSF is completely independent of the UNIX scheduler's priority system for time-sharing processes. In LSF, the NICE parameter is used to set the UNIX time-sharing priority for batch jobs.

## Default

1 (lowest possible priority)

## USER\_GROUP

### Syntax

**USER\_GROUP**=all | [*user\_name*] [*user\_group*] ...

## Description

Optional. A space-separated list of user names or user groups who can submit jobs to the service class. Administrators, root, and all users or groups listed can use the service class.

Use the reserved word all to specify all LSF users. LSF cluster administrators are automatically included in the list of users, so LSF cluster administrators can submit jobs to any service class, or switch any user's jobs into this service class, even if they are not listed.

If user groups are specified in `lsb.users`, each user in the group can submit jobs to this service class. If a group contains a subgroup, the service class policy applies to each member in the subgroup recursively. If the group can define fairshare among its members, the SLA defined by the service class enforces the fairshare policy among the users of the SLA.

User names must be valid login names. User group names can be LSF user groups (in `lsb.users`) or UNIX and Windows user groups.

## Example

```
USER_GROUP=user1 user2 ugroup1
```

## Default

all (all users in the cluster can submit jobs to the service class)

## Examples

- The service class `Ucl ul et` defines one deadline goal that is active during working hours between 8:30 AM and 4:00 PM. All jobs in the service class should complete by the end of the specified time window. Outside of this time window, the SLA is inactive and jobs are scheduled without any goal being enforced:

```
Begin Servi ceCl ass
NAME=Ucl ul et
PRI ORI TY=20
GOALS=[ DEADLI NE ti meWi ndow ( 8: 30- 16: 00) ]
DESCRI PTI ON="worki ng hours"
End Servi ceCl ass
```

- The service class `Nanai mo` defines a deadline goal that is active during the weekends and at nights.

```
Begin Servi ceCl ass
NAME=Nanai mo
PRI ORI TY=20
GOALS=[ DEADLI NE ti meWi ndow ( 5: 18: 00- 1: 8: 30 20: 00- 8: 30) ]
DESCRI PTI ON="weekend ni ghtti me regression tests"
End Servi ceCl ass
```

- The service class `I nuvi k` defines a throughput goal of 6 jobs per hour that is always active:

```
Begin Servi ceCl ass
NAME=I nuvi k
PRI ORI TY=20
GOALS=[ THROUGHPUT 6 ti meWi ndow ( ) ]
DESCRI PTI ON="constant throughput"
End Servi ceCl ass
```

- The service class `Tofi no` defines two velocity goals in a 24 hour period. The first goal is to have a maximum of 10 concurrently running jobs during business hours (9:00 a.m. to 5:00 p.m). The second goal is a maximum of 30 concurrently running jobs during off-hours (5:30 p.m. to 8:30 a.m.)

```
Begin Servi ceCl ass
NAME=Tofi no
PRI ORI TY=20
GOALS=[ VELOCIT Y 10 ti meWi ndow ( 9: 00- 17: 00) ] \
[ VELOCIT Y 30 ti meWi ndow ( 17: 30- 8: 30) ]
DESCRI PTI ON="day and ni ght veloci ty"
End Servi ceCl ass
```

- The service class `Kyuquot` defines a velocity goal that is active during working hours (9:00 a.m. to 5:30 p.m.) and a deadline goal that is active during off-hours (5:30 p.m. to 9:00 a.m.) Only users `user1` and `user2` can submit jobs to this service class.

```
Begin ServiceClass
NAME=Kyuquot
PRIORITY=23
USER_GROUP=user1 user2
GOALS=[ VELOCITY 8 timeWindow (9:00-17:30) ] \
      [ DEADLINE timeWindow (17:30-9:00) ]
DESCRIPTION="Daytime/Nighttime SLA"
End ServiceClass
```

- The service class `Tevere` defines a combination similar to `Kyuquot`, but with a deadline goal that takes effect overnight and on weekends. During the working hours in weekdays the velocity goal favors a mix of short and medium jobs.

```
Begin ServiceClass
NAME=Tevere
PRIORITY=20
GOALS=[ VELOCITY 100 timeWindow (9:00-17:00) ] \
      [ DEADLINE timeWindow (17:30-8:30 5:17:30-1:8:30) ]
DESCRIPTION="nine to five"
End ServiceClass
```

# lsb.users

The `lsb.users` file is used to configure user groups, hierarchical fairshare for users and user groups, and job slot limits for users and user groups. It is also used to configure account mappings in a MultiCluster environment.

This file is optional.

The `lsb.users` file is stored in the directory `LSB_CONFDIR/cluster_name/configdir`, where `LSB_CONFDIR` is defined in `lsf.conf`.

## Changing lsb.users configuration

After making any changes to `lsb.users`, run `badminton reconfig` to reconfigure `mbatchd`.

## UserGroup section

Optional. Defines user groups.

The name of the user group can be used in other user group and queue definitions, as well as on the command line. Specifying the name of a user group in the `GROUP_MEMBER` section has exactly the same effect as listing the names of all users in the group.

The total number of user groups cannot be more than 1024.

## Structure

The first line consists of two mandatory keywords, `GROUP_NAME` and `GROUP_MEMBER`. The `USER_SHARES` and `GROUP_ADMIN` keywords are optional. Subsequent lines name a group and list its membership and optionally its share assignments and administrator.

Each line must contain one entry for each keyword. Use empty parentheses `()` or a dash `-` to specify the default value for an entry.

---

### Restriction:

If specifying a specific user name for a user group, that entry must precede all user groups.

---

## Example of a UserGroup section

```

Begin UserGroup
GROUP_NAME GROUP_MEMBER GROUP_ADMIN
groupA      (user1 user2 user3 user4) (user5)
groupB      (groupA user5) (groupA)
groupC      (!) ()
End UserGroup

Begin UserGroup
GROUP_NAME  GROUP_MEMBER      USER_SHARES
groupB      (user1 user2)      ()
groupC      (user3 user4)      ([User3, 3] [User4, 4])
groupA      (GroupB GroupC user5) ([User5, 1] [default, 10])
End UserGroup

```

## GROUP\_NAME

An alphanumeric string representing the user group name. You cannot use the reserved name `all` or a `" / "` in a group name.

## GROUP\_MEMBER

A list of user names or user group names that belong to the group, enclosed in parentheses and separated by spaces.

User and user group names can appear on multiple lines because users can belong to multiple groups.

---

### Note:

When a user belongs to more than one group, any of the administrators specified for any of the groups the user belongs to can control that users' jobs. Limit administrative control by submitting jobs with the `-G` option, specifying which user group the job is submitted with.

---

User groups may be defined recursively but must not create a loop.

## Syntax

*(user\_name | user\_group ...)* | (all) | (!)

Specify the following, all enclosed in parentheses:

*user\_name | user\_group*

User and user group names, separated by spaces. User names must be valid login names. To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name*).

User group names can be LSF user groups defined previously in this section, or UNIX and Windows user groups. To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_group*).

`all`

The reserved name `all` specifies all users in the cluster.

`!`

An exclamation mark (!) indicates an externally-defined user group, which the `egroup` executable retrieves.

## GROUP\_ADMIN

User group administrators are a list of user names or user group names that administer the jobs of the group members, enclosed in parentheses and separated by spaces.

A user group administrator is allowed to control any jobs of the members of the user group they administer. A user group administrator can also resume jobs stopped by the LSF administrator or queue administrator if the job belongs to a member of their user group.

A user group administrator has privileges equivalent to those of a job owner. A user group administrator can control any job belonging to member users of the group they administer.

---

**Restriction:**

Unlike a job owner, a user group administrator cannot run `brestart` and `bread` - a *data\_file*.

---

To manage security concerns, you cannot specify the keyword `ALL` for any user group administrators.

## Syntax

*(user\_name | user\_group ...)*

Specify the following, all enclosed in parentheses:

*user\_name | user\_group*

User and user group names, separated by spaces. User names must be valid login names. To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name*).

User group names can be LSF user groups defined previously in this section, or UNIX and Windows user groups. To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_group*).

## Valid values

- You can specify a user group as an administrator for another user group. In that case, all members of the first user group become administrators for the second user group.
- You can also specify that all users of a group are also administrators of that same group.
- Users can be administrators for more than one user group at the same time.

---

**Note:**

When a user belongs to more than one group, any of the administrators specified for any of the groups the user belongs to can control that users' jobs.

---

## Restrictions

- Wildcard and special characters are not supported (for example: \*, !, \$, #, &, ~)
- The reserved keywords `ALL`, `others`, `default`, `allremote` are not supported.

User groups with members defined with the keyword `ALL` are also not allowed as a user group administrator.

- User groups and user groups administrator definitions cannot be recursive or create a loop.

## USER\_SHARES

Optional. Enables hierarchical fairshare and defines a share tree for users and user groups.

By default, when resources are assigned collectively to a group, the group members compete for the resources according to FCFS scheduling. You can use hierarchical fairshare to further divide the shares among the group members.

## Syntax

*([user, number\_shares])*

Specify the arguments as follows:

- Enclose the list in parentheses, even if you do not specify any user share assignments.
- Enclose each user share assignment in square brackets, as shown.
- Separate the list of share assignments with a space.
- *user*—Specify users or user groups. You can assign the shares to:
  - A single user (specify *user\_name*). To specify a Windows user account, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name*).
  - Users in a group, individually (specify *group\_name@*) or collectively (specify *group\_name*). To specify a Windows user group, include the domain name in uppercase letters (*DOMAIN\_NAMEgroup\_name*).
  - Users not included in any other share assignment, individually (specify the keyword *default@*) or collectively (specify the keyword *default*).

---

#### Note:

By default, when resources are assigned collectively to a group, the group members compete for the resources on a first-come, first-served (FCFS) basis. You can use hierarchical fairshare to further divide the shares among the group members. When resources are assigned to members of a group individually, the share assignment is recursive. Members of the group and of all subgroups always compete for the resources according to FCFS scheduling, regardless of hierarchical fairshare policies.

- *number\_shares*—Specify a positive integer representing the number of shares of the cluster resources assigned to the user. The number of shares assigned to each user is only meaningful when you compare it to the shares assigned to other users or to the total number of shares. The total number of shares is just the sum of all the shares assigned in each share assignment.

## User section

Optional. If this section is not defined, all users and user groups can run an unlimited number of jobs in the cluster.

This section defines the maximum number of jobs a user or user group can run concurrently in the cluster. This is to avoid situations in which a user occupies all or most of the system resources while other users' jobs are waiting.

## Structure

Three fields are mandatory: *USER\_NAME*, *MAX\_JOBS*, *JL/P*.

*MAX\_PEND\_JOBS* is optional.

You must specify a dash (-) to indicate the default value (unlimited) if a user or user group is specified. Fields cannot be left blank.

## Example of a User section

| USER_NAME | MAX_JOBS | JL/P | MAX_PEND_JOBS |
|-----------|----------|------|---------------|
| user1     | 10       | -    | 1000          |
| user2     | 4        | -    | -             |
| user3     | -        | -    | -             |
| groupA    | 10       | 1    | 100000        |
| groupA@   | -        | 1    | 100           |
| groupC    | -        | -    | 500           |
| default   | 6        | 1    | 10            |

## USER\_NAME

User or user group for which job slot limits are defined.

Use the reserved user name default to specify a job slot limit that applies to each user and user group not explicitly named. Since the limit specified with the keyword default applies to user groups also, make sure you select a limit that is high enough, or explicitly define limits for user groups.

User group names can be the LSF user groups defined previously, and/or UNIX and Windows user groups. To specify a Windows user account or user group, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name* or *DOMAIN\_NAME\user\_group*).

Job slot limits apply to a group as a whole. Append the at sign (@) to a group name to make the job slot limits apply individually to each user in the group. If a group contains a subgroup, the job slot limit also applies to each member in the subgroup recursively.

If the group contains the keyword all in the user list, the at sign (@) has no effect. To specify job slot limits for each user in a user group containing all, use the keyword default.

## MAX\_JOBS

Per-user or per-group job slot limit for the cluster. Total number of job slots that each user or user group can use in the cluster.

---

### Note:

If a group contains the keyword all as a member, all users and user groups are included in the group. The per-group job slot limit set for the group applies to the group as a whole, limiting the entire cluster even when ENFORCE\_ONE\_UG\_LIMIT is set in lsb.params.

---

## JL/P

Per processor job slot limit per user or user group.

Total number of job slots that each user or user group can use per processor. This job slot limit is configured per processor so that multiprocessor hosts will automatically run more jobs.

This number can be a fraction such as 0.5, so that it can also serve as a per-host limit. This number is rounded up to the nearest integer equal to or greater than the total job slot limits

for a host. For example, if  $JL/P$  is 0.5, on a 4-CPU multiprocessor host, the user can only use up to 2 job slots at any time. On a uniprocessor machine, the user can use 1 job slot.

## MAX\_PEND\_JOBS

Per-user or per-group pending job limit. This is the total number of pending job slots that each user or user group can have in the system. If a user is a member of multiple user groups, the user's pending jobs are counted towards the pending job limits of all groups from which the user has membership.

If `ENFORCE_ONE_UG_LIMITS` is set to `Y` in `lsb.params` and you submit a job while specifying a user group, only the limits for that user group (or any parent user group) apply to the job even if there are overlapping user group members.

## UserMap section

Optional. Used only in a MultiCluster environment with a non-uniform user name space. Defines system-level cross-cluster account mapping for users and user groups, which allows users to submit a job from a local host and run the job as a different user on a remote host. Both the local and remote clusters must have corresponding user account mappings configured.

## Structure

The following three fields are all required:

- LOCAL
- REMOTE
- DIRECTION

### LOCAL

A list of users or user groups in the local cluster. To specify a Windows user account or user group, include the domain name in uppercase letters (`DOMAIN_NAME` \`user_name` or `DOMAIN_NAME`\`user_group`). Separate multiple user names by a space and enclose the list in parentheses (`()`):

```
(user4 user6)
```

### REMOTE

A list of remote users or user groups in the form `user_name@cluster_name` or `user_group@cluster_name`. To specify a Windows user account or user group, include the domain name in uppercase letters (`DOMAIN_NAME`\`user_name@cluster_name` or `DOMAIN_NAME`\`user_group@cluster_name`). Separate multiple user names by a space and enclose the list in parentheses (`()`):

```
(user4@cluster2 user6@cluster2)
```

### DIRECTION

Specifies whether the user account runs jobs locally or remotely. Both directions must be configured on the local and remote clusters.

- The `export` keyword configures local users/groups to run jobs as remote users/groups.

- The import keyword configures remote users/groups to run jobs as local users/groups.

## Example of a UserMap section

On cluster1:

```
Begin UserMap
LOCAL    REMOTE                                DI RECTI ON
user1    user2@cl uster2                        export
user3    user6@cl uster2    export
End UserMap
```

On cluster2:

```
Begin UserMap
LOCAL    REMOTE                                DI RECTI ON
user2    user1@cl uster1                        i mport
user6    user3@cl uster1                        i mport
End UserMap
```

Cluster1 configures user1 to run jobs as user2 and user3 to run jobs as user6.

Cluster2 configures user1 to run jobs as user2 and user3 to run jobs as user6.

## Automatic time-based configuration

Variable configuration is used to automatically change LSF configuration based on time windows. You define automatic configuration changes in `lsb.users` by using if-else constructs and time expressions. After you change the files, reconfigure the cluster with the `badmi n reconfi g` command.

The expressions are evaluated by LSF every 10 minutes based on `mbatchd` start time. When an expression evaluates true, LSF dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting `mbatchd`, providing continuous system availability.

## Example

From 12 - 1 p.m. daily, user `smith` has 10 job slots, but during other hours, user has only 5 job slots.

```
Begin User
USER_NAME  MAX_JOBS  JL/P
#i f t i me (12-13)
smith      10        -
#e l s e
smith      5         -
defaul t   1         -
#e n d i f
End User
```

# lsf.acct

The `lsf.acct` file is the LSF task log file.

The LSF Remote Execution Server, RES (see [res\(8\)](#)), generates a record for each task completion or failure. If the RES task logging is turned on (see [lsadm n\(8\)](#)), it appends the record to the task log file `lsf.acct.<host_name>`.

## lsf.acct structure

The task log file is an ASCII file with one task record per line. The fields of each record are separated by blanks. The location of the file is determined by the `LSF_RES_ACCTDIR` variable defined in `lsf.conf`. If this variable is not defined, or the RES cannot access the log directory, the log file is created in `/tmp` instead.

## Fields

The fields in a task record are ordered in the following sequence:

### **pid (%d)**

Process ID for the remote task

### **userName (%s)**

User name of the submitter

### **exitStatus (%d)**

Task exit status

### **dispTime (%ld)**

Dispatch time – time at which the task was dispatched for execution

### **termTime (%ld)**

Completion time – time when task is completed/failed

### **fromHost (%s)**

Submission host name

### **execHost (%s)**

Execution host name

### **cwd (%s)**

Current working directory

### **cmdln (%s)**

Command line of the task

### **lsfRusage**

The following fields contain resource usage information for the job (see [getrusage\(2\)](#)). If the value of some field is unavailable (due to job exit or the difference among the operating systems), -1 will be logged. Times are measured in seconds, and sizes are measured in KB.

|                         |                                                                     |
|-------------------------|---------------------------------------------------------------------|
| <b>ru_utime (%f)</b>    | User time used                                                      |
| <b>ru_stime (%f)</b>    | System time used                                                    |
| <b>ru_maxrss (%f)</b>   | Maximum shared text size                                            |
| <b>ru_ixrss (%f)</b>    | Integral of the shared text size over time (in KB seconds)          |
| <b>ru_ismrss (%f)</b>   | Integral of the shared memory size over time (valid only on Ultrix) |
| <b>ru_idrss (%f)</b>    | Integral of the unshared data size over time                        |
| <b>ru_isrss (%f)</b>    | Integral of the unshared stack size over time                       |
| <b>ru_minflt (%f)</b>   | Number of page reclaims                                             |
| <b>ru_majflt (%f)</b>   | Number of page faults                                               |
| <b>ru_nswap (%f)</b>    | Number of times the process was swapped out                         |
| <b>ru_inblock (%f)</b>  | Number of block input operations                                    |
| <b>ru_oublock (%f)</b>  | Number of block output operations                                   |
| <b>ru_ioch (%f)</b>     | Number of characters read and written (valid only on HP-UX)         |
| <b>ru_msgsnd (%f)</b>   | Number of System V IPC messages sent                                |
| <b>ru_msgrcv (%f)</b>   | Number of messages received                                         |
| <b>ru_nsignals (%f)</b> | Number of signals received                                          |
| <b>ru_nvcsw (%f)</b>    |                                                                     |

lsf.acct

Number of voluntary context switches

**ru\_nivcsw (%f)**

Number of involuntary context switches

**ru\_exutime (%f)**

Exact user time used (valid only on ConvexOS)

# lsf.cluster

## Contents

- About lsf.cluster
- Parameters section
- ClusterAdmins section
- Host section
- ResourceMap section
- RemoteClusters section

## About lsf.cluster

This is the cluster configuration file. There is one for each cluster, called `lsf.cluster.cluster_name`. The `cluster_name` suffix is the name of the cluster defined in the Cluster section of `lsf.shared`. All LSF hosts are listed in this file, along with the list of LSF administrators and the installed LSF features.

The `lsf.cluster.cluster_name` file contains two types of configuration information:

- Cluster definition information — affects all LSF applications. Defines cluster administrators, hosts that make up the cluster, attributes of each individual host such as host type or host model, and resources using the names defined in `lsf.shared`.
- LIM policy information — affects applications that rely on LIM job placement policy. Defines load sharing and job placement policies provided by LIM.

## Changing lsf.cluster configuration

After making any changes to `lsf.cluster.cluster_name`, run the following commands:

- `lsadmin reconfig` to reconfigure LIM
- `badmin mbdrestart` to restart `mbatchd`

## Location

This file is typically installed in the directory defined by `LSF_ENVDIR`.

## Structure

The `lsf.cluster.cluster_name` file contains the following configuration sections:

- Parameters section
- ClusterAdmins section
- Host section
- ResourceMap section
- RemoteClusters section

## Parameters

- `ADJUST_DURATION`
- `ELIM_POLL_INTERVAL`
- `ELIMARGS`

- EXINTERVAL
- FLOAT\_CLIENTS
- FLOAT\_CLIENTS\_ADDR\_RANGE
- HOST\_INACTIVITY\_LIMIT
- LSF\_ELIM\_BLOCKTIME
- LSF\_ELIM\_DEBUG
- LSF\_ELIM\_RESTARTS
- LSF\_HOST\_ADDR\_RANGE
- MASTER\_INACTIVITY\_LIMIT
- PROBE\_TIMEOUT
- PRODUCTS
- RETRY\_LIMIT

## ADJUST\_DURATION

### Syntax

ADJUST\_DURATION=*integer*

### Description

Integer reflecting a multiple of EXINTERVAL that controls the time period during which load adjustment is in effect

The `lspl ace(1)` and `lspl oadadj (1)` commands artificially raise the load on a selected host. This increase in load decays linearly to 0 over time.

### Default

3

## ELIM\_POLL\_INTERVAL

### Syntax

ELIM\_POLL\_INTERVAL=*seconds*

### Description

Time interval, in seconds, that the LIM samples external load index information. If your `elim` executable is programmed to report values more frequently than every 5 seconds, set the ELIM\_POLL\_INTERVAL so that it samples information at a corresponding rate.

### Valid values

0.001 to 5

### Default

5 seconds

## ELIMARGS

### Syntax

ELIMARGS=*cmd\_line\_args*

## Description

Specifies command-line arguments required by an `elim` executable on startup. Used only when the external load indices feature is enabled.

## Default

Undefined

## EXINTERVAL

## Syntax

`EXINTERVAL=time_in_seconds`

## Description

Time interval, in seconds, at which the LIM daemons exchange load information

On extremely busy hosts or networks, or in clusters with a large number of hosts, load may interfere with the periodic communication between LIM daemons. Setting EXINTERVAL to a longer interval can reduce network load and slightly improve reliability, at the cost of slower reaction to dynamic load changes.

Note that if you define the time interval as less than 5 seconds, LSF automatically resets it to 5 seconds.

## Default

15 seconds

## FLOAT\_CLIENTS

## Syntax

`FLOAT_CLIENTS=number_of_floating_client_licenses`

## Description

Sets the size of your license pool in the cluster

When the master LIM starts, up to *number\_of\_floating\_client\_licenses* will be checked out for use as floating client licenses. If fewer licenses are available than specified by *number\_of\_floating\_client\_licenses*, only the available licenses will be checked out and used.

If FLOAT\_CLIENTS is not specified in `lsf.cluster.cluster_name` or there is an error in either `license.dat` or in `lsf.cluster.cluster_name`, the floating LSF client license feature is disabled.

---

### Caution:

When the LSF floating client feature is enabled, any host can submit jobs to the cluster. You can limit which hosts can be LSF floating clients with the parameter

`FLOAT_CLIENTS_ADDR_RANGE` in `lsf.cluster.cluster_name`.

---

## LSF Floating Client

Although an LSF Floating Client requires a license, `LSF_Float_Client` does not need to be added to the `PRODUCTS` line. `LSF_Float_Client` also cannot be added as a resource for specific hosts already defined in `lsf.cluster.cluster_name`. Should these lines be present, they are ignored by LSF.

### Default

Undefined

## FLOAT\_CLIENTS\_ADDR\_RANGE

### Syntax

`FLOAT_CLIENTS_ADDR_RANGE=IP_address ...`

### Description

Optional. IP address or range of addresses of domains from which floating client hosts can submit requests. Multiple ranges can be defined, separated by spaces. The IP address can have either a dotted quad notation (IPv4) or IP Next Generation (IPv6) format. LSF supports both formats; you do not have to map IPv4 addresses to an IPv6 format.

---

#### Note:

To use IPv6 addresses, you must define the parameter `LSF_ENABLE_SUPPORT_IPV6` in `lsf.conf`.

---

If the value of `FLOAT_CLIENT_ADDR_RANGE` is undefined, there is no security and any hosts can be LSF floating clients.

If a value is defined, security is enabled. If there is an error in the configuration of this variable, by default, no hosts will be allowed to be LSF floating clients.

When this parameter is defined, client hosts that do not belong to the domain will be denied access.

If a requesting host belongs to an IP address that falls in the specified range, the host will be accepted to become a floating client.

IP addresses are separated by spaces, and considered "OR" alternatives.

If you define `FLOAT_CLIENT_ADDR_RANGE` with:

- No range specified, all IPv4 and IPv6 clients can submit requests.
- Only an IPv4 range specified, only IPv4 clients within the range can submit requests.
- Only an IPv6 range specified, only IPv6 clients within the range can submit requests.
- Both an IPv6 and IPv4 range specified, IPv6 and IPv4 clients within the ranges can submit requests.

The asterisk (\*) character indicates any value is allowed.

The dash (-) character indicates an explicit range of values. For example 1-4 indicates 1,2,3,4 are allowed.

Open ranges such as \*-30, or 10-\*, are allowed.

If a range is specified with fewer fields than an IP address such as 10.161, it is considered as 10.161.\*.\*.

Address ranges are validated at configuration time so they must conform to the required format. If any address range is not in the correct format, no hosts will be accepted as LSF floating clients, and an error message will be logged in the LIM log.

This parameter is limited to 2048 characters.

For IPv6 addresses, the double colon symbol (::) indicates multiple groups of 16-bits of zeros. You can also use (::) to compress leading and trailing zeros in an address filter, as shown in the following example:

**FLOAT\_CLIENTS\_ADDR\_RANGE=1080::8:800:20fc:\***

This definition allows hosts with addresses 1080:0:0:0:8:800:20fc:\* (three leading zeros).

You cannot use the double colon (::) more than once within an IP address. You cannot use a zero before or after (::). For example, 1080:0::8:800:20fc:\* is not a valid address.

## Notes

After you configure `FLOAT_CLIENTS_ADDR_RANGE`, check the `lim.log`. `host_name` file to make sure this parameter is correctly set. If this parameter is not set or is wrong, this will be indicated in the log file.

## Examples

`FLOAT_CLIENTS_ADDR_RANGE=100`

All IPv4 and IPv6 hosts with a domain address starting with 100 will be allowed access.

- To specify only IPv4 hosts, set the value to **100.\***
- To specify only IPv6 hosts, set the value to **100:\***

`FLOAT_CLIENTS_ADDR_RANGE=100-110.34.1-10.4-56`

All client hosts belonging to a domain with an address having the first number between 100 and 110, then 34, then a number between 1 and 10, then, a number between 4 and 56 will be allowed access. Example: 100.34.9.45, 100.34.1.4, 102.34.3.20, etc. No IPv6 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE=100.172.1.13 100.*.30-54 124.24-*.1.*-34`

All client hosts belonging to a domain with the address 100.172.1.13 will be allowed access. All client hosts belonging to domains starting with 100, then any number, then a range of 30 to 54 will be allowed access. All client hosts belonging to domains starting with 124, then from 24 onward, then 1, then from 0 to 34 will be allowed access. No IPv6 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE=12.23.45.*`

All client hosts belonging to domains starting with 12.23.45 are allowed. No IPv6 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE=100.*43`

The \* character can only be used to indicate any value. In this example, an error will be inserted in the LIM log and no hosts will be accepted to become LSF floating clients. No IPv6 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE=100.*43 100.172.1.13`

Although one correct address range is specified, because \*43 is not correct format, the entire line is considered not valid. An error will be inserted in the LIM log and no hosts will be accepted to become LSF floating clients. No IPv6 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE = 3ffe`

All client IPv6 hosts with a domain address starting with 3ffe will be allowed access. No IPv4 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE = 3ffe: fffe: : 88bb: *`

Expands to 3ffe:ffe:0:0:0:88bb:\*. All IPv6 client hosts belonging to domains starting with 3ffe:ffe::88bb:\* are allowed. No IPv4 hosts are allowed.

`FLOAT_CLIENTS_ADDR_RANGE = 3ffe- 4fff: fffe: : 88bb: aa- ff 12. 23. 45. *`

All IPv6 client hosts belonging to domains starting with 3ffe up to 4fff, then fffe::88bb, and ending with aa up to ff are allowed. All IPv4 client hosts belonging to domains starting with 12.23.45 are allowed.

`FLOAT_CLIENTS_ADDR_RANGE = 3ffe- *: fffe: : 88bb: *- ff`

All IPv6 client hosts belonging to domains starting with 3ffe up to ffff and ending with 0 up to ff are allowed. No IPv4 hosts are allowed.

## Default

Undefined. No security is enabled. Any host in any domain is allowed access to LSF floating client licenses.

## See also

`LSF_ENABLE_SUPPORT_IPV6`

## HOST\_INACTIVITY\_LIMIT

### Syntax

`HOST_INACTIVITY_LIMIT=integer`

### Description

Integer that is multiplied by `EXINTERVAL`, the time period you set for the communication between the master and slave LIMs to ensure all parties are functioning.

A slave LIM can send its load information any time from `EXINTERVAL` to  $(\text{HOST\_INACTIVITY\_LIMIT}-1) * \text{EXINTERVAL}$  seconds. A master LIM sends a master announce to each host at least every  $\text{EXINTERVAL} * \text{HOST\_INACTIVITY\_LIMIT}$  seconds.

The `HOST_INACTIVITY_LIMIT` must be greater than or equal to 2.

Increase or decrease the host inactivity limit to adjust for your tolerance for communication between master and slaves. For example, if you have hosts that frequently become inactive, decrease the host inactivity limit. Note that to get the right interval, you may also have to adjust your `EXINTERVAL`.

## Default

5

## LSF\_ELIM\_BLOCKTIME

### Syntax

LSF\_ELIM\_BLOCKTIME=*seconds*

### Description

UNIX only; used when the external load indices feature is enabled.

Maximum amount of time the master external load information manager (MELIM) waits for a complete load update string from an `elim` executable. After the time period specified by `LSF_ELIM_BLOCKTIME`, the MELIM writes the last string sent by an `elim` in the LIM log file (`lim.log.host_name`) and restarts the `elim`.

Defining `LSF_ELIM_BLOCKTIME` also triggers the MELIM to restart `elim` executables if the `elim` does not write a complete load update string within the time specified for `LSF_ELIM_BLOCKTIME`.

### Valid Values

Non-negative integers. For example, if your `elim` writes name-value pairs with 1 second intervals between them, and your `elim` reports 12 load indices, allow at least 12 seconds for the `elim` to finish writing the entire load update string. In this case, define `LSF_ELIM_BLOCKTIME` as 15 seconds or more.

A value of 0 indicates that the MELIM expects to receive the entire load string all at once.

If you comment out or delete `LSF_ELIM_BLOCKTIME`, the MELIM waits 2 seconds for a complete load update string.

### Default

4 seconds

### See also

`LSF_ELIM_RESTARTS` to limit how many times the ELIM can be restarted.

## LSF\_ELIM\_DEBUG

### Syntax

LSF\_ELIM\_DEBUG=*y*

### Description

UNIX only; used when the external load indices feature is enabled.

When this parameter is set to `y`, all external load information received by the load information manager (LIM) from the master external load information manager (MELIM) is logged in the LIM log file (`lim.log.host_name`).

Defining `LSF_ELIM_DEBUG` also triggers the MELIM to restart `elim` executables if the `elim` does not write a complete load update string within the time specified for `LSF_ELIM_BLOCKTIME`.

## Default

Undefined; external load information sent by an to the MELIM is not logged.

## See also

LSF\_ELIM\_BLOCKTIME to configure how long LIM waits before restarting the ELIM.

LSF\_ELIM\_RESTARTS to limit how many times the ELIM can be restarted.

## LSF\_ELIM\_RESTARTS

### Syntax

LSF\_ELIM\_RESTARTS=*integer*

### Description

UNIX only; used when the external load indices feature is enabled.

Maximum number of times the master external load information manager (MELIM) can restart `el i m` executables on a host. Defining this parameter prevents an ongoing restart loop in the case of a faulty `el i m`. The MELIM waits the LSF\_ELIM\_BLOCKTIME to receive a complete load update string before restarting the `el i m`. The MELIM does not restart any `el i m` executables that exit with ELIM\_ABORT\_VALUE.

---

**Important:**

Either LSF\_ELIM\_BLOCKTIME or LSF\_ELIM\_DEBUG must also be defined; defining these parameters triggers the MELIM to restart `el i m` executables.

---

### Valid Values

Non-negative integers.

### Default

Undefined; the number of `el i m` restarts is unlimited.

### See also

LSF\_ELIM\_BLOCKTIME, LSF\_ELIM\_DEBUG

## LSF\_HOST\_ADDR\_RANGE

### Syntax

LSF\_HOST\_ADDR\_RANGE=*IP\_address ...*

### Description

Identifies the range of IP addresses that are allowed to be LSF hosts that can be dynamically added to or removed from the cluster.

---

**Caution:**

To enable dynamically added hosts after installation, you must define `LSF_HOST_ADDR_RANGE` in `lsf.cluster.cluster_name`, and `LSF_DYNAMIC_HOST_WAIT_TIME` in `lsf.conf`. If you enable dynamic hosts during installation, you must define an IP address range after installation to enable security.

If a value is defined, security for dynamically adding and removing hosts is enabled, and only hosts with IP addresses within the specified range can be added to or removed from a cluster dynamically.

Specify an IP address or range of addresses, using either a dotted quad notation (IPv4) or IP Next Generation (IPv6) format. LSF supports both formats; you do not have to map IPv4 addresses to an IPv6 format. Multiple ranges can be defined, separated by spaces.

---

**Note:**

To use IPv6 addresses, you must define the parameter `LSF_ENABLE_SUPPORT_IPV6` in `lsf.conf`.

If there is an error in the configuration of `LSF_HOST_ADDR_RANGE` (for example, an address range is not in the correct format), no host will be allowed to join the cluster dynamically and an error message will be logged in the LIM log. Address ranges are validated at startup, reconfiguration, or restart, so they must conform to the required format.

If a requesting host belongs to an IP address that falls in the specified range, the host will be accepted to become a dynamic LSF host.

IP addresses are separated by spaces, and considered "OR" alternatives.

If you define the parameter `LSF_HOST_ADDR_RANGE` with:

- No range specified, all IPv4 and IPv6 clients are allowed.
- Only an IPv4 range specified, only IPv4 clients within the range are allowed.
- Only an IPv6 range specified, only IPv6 clients within the range are allowed.
- Both an IPv6 and IPv4 range specified, IPv6 and IPv4 clients within the ranges are allowed.

The asterisk (\*) character indicates any value is allowed.

The dash (-) character indicates an explicit range of values. For example 1-4 indicates 1,2,3,4 are allowed.

Open ranges such as \*-30, or 10-\*, are allowed.

For IPv6 addresses, the double colon symbol (::) indicates multiple groups of 16-bits of zeros. You can also use (::) to compress leading and trailing zeros in an address filter, as shown in the following example:

**LSF\_HOST\_ADDR\_RANGE=1080::8:800:20fc:\***

This definition allows hosts with addresses 1080:0:0:0:8:800:20fc:\* (three leading zeros).

You cannot use the double colon (::) more than once within an IP address. You cannot use a zero before or after (::). For example, 1080:0::8:800:20fc:\* is not a valid address.

If a range is specified with fewer fields than an IP address such as 10.161, it is considered as 10.161.\*.\*.

This parameter is limited to 2048 characters.

## Notes

After you configure `LSF_HOST_ADDR_RANGE`, check the `lim.log` `host_name` file to make sure this parameter is correctly set. If this parameter is not set or is wrong, this will be indicated in the log file.

## Examples

```
LSF_HOST_ADDR_RANGE=100
```

All IPv4 and IPv6 hosts with a domain address starting with 100 will be allowed access.

- To specify only IPv4 hosts, set the value to **100.\***
- To specify only IPv6 hosts, set the value to **100:\***

```
LSF_HOST_ADDR_RANGE=100-110.34.1-10.4-56
```

All hosts belonging to a domain with an address having the first number between 100 and 110, then 34, then a number between 1 and 10, then, a number between 4 and 56 will be allowed access. No IPv6 hosts are allowed. Example: 100.34.9.45, 100.34.1.4, 102.34.3.20, etc.

```
LSF_HOST_ADDR_RANGE=100.172.1.13 100.*.30-54 124.24-*.1.*-34
```

The host with the address 100.172.1.13 will be allowed access. All hosts belonging to domains starting with 100, then any number, then a range of 30 to 54 will be allowed access. All hosts belonging to domains starting with 124, then from 24 onward, then 1, then from 0 to 34 will be allowed access. No IPv6 hosts are allowed.

```
LSF_HOST_ADDR_RANGE=12.23.45.*
```

All hosts belonging to domains starting with 12.23.45 are allowed. No IPv6 hosts are allowed.

```
LSF_HOST_ADDR_RANGE=100.*43
```

The `*` character can only be used to indicate any value. The format of this example is not correct, and an error will be inserted in the LIM log and no hosts will be able to join the cluster dynamically. No IPv6 hosts are allowed.

```
LSF_HOST_ADDR_RANGE=100.*43 100.172.1.13
```

Although one correct address range is specified, because `*43` is not correct format, the entire line is considered not valid. An error will be inserted in the LIM log and no hosts will be able to join the cluster dynamically. No IPv6 hosts are allowed.

```
LSF_HOST_ADDR_RANGE = 3ffe
```

All client IPv6 hosts with a domain address starting with 3ffe will be allowed access. No IPv4 hosts are allowed.

```
LSF_HOST_ADDR_RANGE = 3ffe:fffe::88bb:*
```

Expands to `3ffe:fffe:0:0:0:88bb:*`. All IPv6 client hosts belonging to domains starting with `3ffe:fffe::88bb:*` are allowed. No IPv4 hosts are allowed.

```
LSF_HOST_ADDR_RANGE = 3ffe-4fff:fffe::88bb:aa-ff 12.23.45.*
```

All IPv6 client hosts belonging to domains starting with 3ffe up to 4fff, then fffe::88bb, and ending with aa up to ff are allowed. IPv4 client hosts belonging to domains starting with 12.23.45 are allowed.

```
LSF_HOST_ADDR_RANGE = 3ffe-*:fffe::88bb:*-ff
```

All IPv6 client hosts belonging to domains starting with 3ffe up to ffff and ending with 0 up to ff are allowed. No IPv4 hosts are allowed.

## Default

Undefined (dynamic host feature disabled). If you enable dynamic hosts during installation, no security is enabled and all hosts can join the cluster.

## See also

LSF\_ENABLE\_SUPPORT\_IPV6

## MASTER\_INACTIVITY\_LIMIT

### Syntax

MASTER\_INACTIVITY\_LIMIT=*integer*

### Description

An integer reflecting a multiple of EXINTERVAL. A slave will attempt to become master if it does not hear from the previous master after  $(\text{HOST\_INACTIVITY\_LIMIT} + \text{host\_number} * \text{MASTER\_INACTIVITY\_LIMIT}) * \text{EXINTERVAL}$  seconds, where *host\_number* is the position of the host in `lsf.cluster.cluster_name`.

The master host is *host\_number* 0.

## Default

2

## PROBE\_TIMEOUT

### Syntax

PROBE\_TIMEOUT=*time\_in\_seconds*

### Description

Specifies the timeout in seconds to be used for the `connect(2)` system call

Before taking over as the master, a slave LIM will try to connect to the last known master via TCP.

## Default

2 seconds

## PRODUCTS

### Syntax

PRODUCTS=*product\_name ...*

### Description

Specifies the LSF products and features that the cluster will run (you must also have a license for every product you want to run). The list of items is separated by space.

The PRODUCTS parameter is set automatically during installation to include core features. Here are some of the optional products and features that can be specified:

- LSF\_Make
- LSF\_MultiCluster

## Default

LSF\_Base LSF\_Manager LSF\_Make

## RETRY\_LIMIT

### Syntax

RETRY\_LIMIT=*integer*

### Description

Integer reflecting a multiple of EXINTERVAL that controls the number of retries a master or slave LIM makes before assuming that the slave or master is unavailable.

If the master does not hear from a slave for HOST\_INACTIVITY\_LIMIT exchange intervals, it will actively poll the slave for RETRY\_LIMIT exchange intervals before it will declare the slave as unavailable. If a slave does not hear from the master for HOST\_INACTIVITY\_LIMIT exchange intervals, it will actively poll the master for RETRY\_LIMIT intervals before assuming that the master is down.

## Default

2

## ClusterAdmins section

(Optional) The ClusterAdmins section defines the LSF administrators for the cluster. The only keyword is ADMINISTRATORS.

If the ClusterAdmins section is not present, the default LSF administrator is root. Using root as the primary LSF administrator is not recommended.

## ADMINISTRATORS

### Syntax

ADMINISTRATORS=*administrator\_name ...*

### Description

Specify UNIX user names.

You can also specify UNIX user group names, Windows user names, and Windows user group names. To specify a Windows user account or user group, include the domain name in uppercase letters (*DOMAIN\_NAME\user\_name* or *DOMAIN\_NAME\user\_group*).

The first administrator of the expanded list is considered the primary LSF administrator. The primary administrator is the owner of the LSF configuration files, as well as the working files under `LSB_SHARED1R/cluster_name`. If the primary administrator is changed, make sure the owner of the configuration files and the files under `LSB_SHARED1R/cluster_name` are changed as well.

Administrators other than the primary LSF administrator have the same privileges as the primary LSF administrator except that they do not have permission to change LSF configuration files. They can perform clusterwide operations on jobs, queues, or hosts in the system.

For flexibility, each cluster may have its own LSF administrators, identified by a user name, although the same administrators can be responsible for several clusters.

Use the `-l` option of the `lscluster` command to display all of the administrators within a cluster.

Windows domain:

- If the specified user or user group is a domain administrator, member of the `Power Users` group or a group with domain administrative privileges, the specified user or user group must belong to the LSF user domain.
- If the specified user or user group is a user or user group with a lower degree of privileges than outlined in the previous point, the user or user group must belong to the LSF user domain and be part of the Global Admins group.

Windows workgroup

- If the specified user or user group is not a workgroup administrator, member of the `Power Users` group, or a group with administrative privileges on each host, the specified user or user group must belong to the Local Admins group on each host.

## Compatibility

For backwards compatibility, `ClusterManager` and `Manager` are synonyms for `ClusterAdmins` and `ADMINISTRATORS` respectively. It is possible to have both sections present in the same `lsf.cluster.cluster_name` file to allow daemons from different LSF versions to share the same file.

## Example

The following gives an example of a cluster with two LSF administrators. The user listed first, `user2`, is the primary administrator.

```
Begin ClusterAdmins
ADMINISTRATORS = user2 user7
End ClusterAdmins
```

## Default

lsfadmin

## Host section

The Host section is the last section in `lsf.cluster.cluster_name` and is the only required section. It lists all the hosts in the cluster and gives configuration information for each host.

The order in which the hosts are listed in this section is important, because the first host listed becomes the LSF master host. Since the master LIM makes all placement decisions for the cluster, it should be on a fast machine.

The LIM on the first host listed becomes the master LIM if this host is up; otherwise, that on the second becomes the master if its host is up, and so on. Also, to avoid the delays involved in switching masters if the first machine goes down, the master should be on a reliable machine. It is desirable to arrange the list such that the first few hosts in the list are always in the same

subnet. This avoids a situation where the second host takes over as master when there are communication problems between subnets.

Configuration information is of two types:

- Some fields in a host entry simply describe the machine and its configuration.
- Other fields set thresholds for various resources.

## Example Host section

This example Host section contains descriptive and threshold information for three hosts:

```

Begin Host
HOSTNAME  model  type  server  r1m  pg  tmp  RESOURCES  RUNWINDOW
hostA     SparcIPC Sparc  1      3.5 15  0 (sunos frame)  ()
hostD     Sparc10  Sparc  1      3.5 15  0 (sunos)       (5: 18: 30- 1: 8: 30)
hostD     !        !      1      2.0 10  0 ()            ()
hostE     !        !      1      2.0 10  0 (linux !bi gmem)  ()
End Host

```

## Descriptive fields

The following fields are required in the Host section:

- HOSTNAME
- RESOURCES
- type
- model

The following fields are optional:

- server
- nd
- RUNWINDOW
- REXPRI

## HOSTNAME

### Description

Official name of the host as returned by `hostname(1)`

The name must be listed in `lsf.shared` as belonging to this cluster.

## model

### Description

Host model

The name must be defined in the HostModel section of `lsf.shared`. This determines the CPU speed scaling factor applied in load and placement calculations.

Optionally, the `!` keyword for the model or type column, indicates that the host model or type is to be automatically detected by the LIM running on the host.

nd

## Description

Number of local disks

This corresponds to the `ndisks` static resource. On most host types, LSF automatically determines the number of disks, and the `nd` parameter is ignored.

`nd` should only count local disks with file systems on them. Do not count either disks used only for swapping or disks mounted with NFS.

## Default

The number of disks determined by the LIM, or 1 if the LIM cannot determine this

## RESOURCES

### Description

The static Boolean resources and static or dynamic numeric and string resources available on this host.

The resource names are strings defined in the Resource section of `lsf.shared`. You may list any number of resources, enclosed in parentheses and separated by blanks or tabs. For example:

```
(fs frame hpux)
```

Optionally, you can specify an exclusive resource by prefixing the resource with an exclamation mark (!). For example, resource `bigmem` is defined in `lsf.shared`, and is defined as an exclusive resource for host E:

```
Begin Host
HOSTNAME  model  type  server  r1m  pg  tmp  RESOURCES  RUNWI NDOW
...
hostE     !      !      1      2.0  10  0  (linux !bigmem)  ()
...
End Host
```

You must explicitly specify the exclusive resources in the resource requirements for the job to select a host with an exclusive resource for a job. For example:

```
bsub -R "bigmem" myjob
```

or

```
bsub -R "defined(bigmem)" myjob
```

You can specify static and dynamic numeric and string resources in the resource column of the Host clause. For example:

```

Begin      Host
-----
HOSTNAME  model  type  server  r1m  mem  swp  RESOURCES  #Keywords
hostA     !      !      1       3.5  ()   ()   (mg elimres patchrev=3 owner=user1)
hostB     !      !      1       3.5  ()   ()   (specman=5 switch=1 owner=test)
hostC     !      !      1       3.5  ()   ()   (switch=2 rack=rack2_2_3 owner=test)
hostD     !      !      1       3.5  ()   ()   (switch=1 rack=rack2_2_3 owner=test)
End       Host

```

## REXPRI

### Description

UNIX only

Default execution priority for interactive remote jobs run under the RES

The range is from -20 to 20. REXPRI corresponds to the BSD-style nice value used for remote jobs. For hosts with System V-style nice values with the range 0 - 39, a REXPRI of -20 corresponds to a nice value of 0, and +20 corresponds to 39. Higher values of REXPRI correspond to lower execution priority; -20 gives the highest priority, 0 is the default priority for login sessions, and +20 is the lowest priority.

### Default

0

## RUNWINDOW

### Description

Dispatch window for interactive tasks.

When the host is not available for remote execution, the host status is `lockW` (locked by run window). LIM does not schedule interactive tasks on hosts locked by dispatch windows. Run windows only apply to interactive tasks placed by LIM. The LSF batch system uses its own (optional) host dispatch windows to control batch job processing on batch server hosts.

### Format

A dispatch window consists of one or more time windows in the format *begin\_time-end\_time*. No blanks can separate *begin\_time* and *end\_time*. Time is specified in the form *[day:]hour[:minute]*. If only one field is specified, LSF assumes it is an *hour*. Two fields are assumed to be *hour.minute*. Use blanks to separate time windows.

### Default

Always accept remote jobs

## server

### Description

Indicates whether the host can receive jobs from other hosts

Specify 1 if the host can receive jobs from other hosts; specify 0 otherwise. Servers that are set to 0 are LSF clients. Client hosts do not run the LSF daemons. Client hosts can submit interactive and batch jobs to the cluster, but they cannot execute jobs sent from other hosts.

### Default

1

## type

### Description

Host type as defined in the HostType section of `lsf.shared`

The strings used for host types are determined by the system administrator: for example, SUNSOL, DEC, or HPPA. The host type is used to identify binary-compatible hosts.

The host type is used as the default resource requirement. That is, if no resource requirement is specified in a placement request, the task is run on a host of the same type as the sending host.

Often one host type can be used for many machine models. For example, the host type name SUNSOL6 might be used for any computer with a SPARC processor running SunOS 6. This would include many Sun models and quite a few from other vendors as well.

Optionally, the ! keyword for the model or type column, indicates that the host model or type is to be automatically detected by the LIM running on the host.

## Threshold fields

The LIM uses these thresholds in determining whether to place remote jobs on a host. If one or more LSF load indices exceeds the corresponding threshold (too many users, not enough swap space, etc.), then the host is regarded as busy, and LIM will not recommend jobs to that host.

The CPU run queue length threshold values (`r15s`, `r1m`, and `r15m`) are taken as effective queue lengths as reported by `lsload -E`.

All of these fields are optional; you only need to configure thresholds for load indices that you wish to use for determining whether hosts are busy. Fields that are not configured are not considered when determining host status. The keywords for the threshold fields are not case sensitive.

Thresholds can be set for any of the following:

- The built-in LSF load indexes (`r15s`, `r1m`, `r15m`, `ut`, `pg`, `it`, `io`, `ls`, `swp`, `mem`, `tmp`)
- External load indexes defined in the Resource section of `lsf.shared`

## ResourceMap section

The ResourceMap section defines shared resources in your cluster. This section specifies the mapping between shared resources and their sharing hosts. When you define resources in the Resources section of `lsf.shared`, there is no distinction between a shared and non-shared

resource. By default, all resources are not shared and are local to each host. By defining the ResourceMap section, you can define resources that are shared by all hosts in the cluster or define resources that are shared by only some of the hosts in the cluster.

This section must appear after the Host section of `lsf.cluster.cluster_name`, because it has a dependency on host names defined in the Host section.

## ResourceMap section structure

The first line consists of the keywords `RESOURCE` and `LOCATION`. Subsequent lines describe the hosts that are associated with each configured resource.

## Example ResourceMap section

```
Begin ResourceMap
RESOURCENAME LOCATION
verilog (5@[all])
local ([host1 host2] [others])
End ResourceMap
```

The resource `verilog` must already be defined in the `RESOURCE` section of the `lsf.shared` file. It is a static numeric resource shared by all hosts. The value for `verilog` is 5. The resource `local` is a numeric shared resource that contains two instances in the cluster. The first instance is shared by two machines, `host1` and `host2`. The second instance is shared by all other hosts.

Resources defined in the ResourceMap section can be viewed by using the `-s` option of the `lshosts` (for static resource) and `lsload` (for dynamic resource) commands.

## LOCATION Description

Defines the hosts that share the resource

For a static resource, you must define an initial value here as well. Do not define a value for a dynamic resource.

*instance* is a list of host names that share an instance of the resource. The reserved words `all`, `others`, and `default` can be specified for the instance:

`all` — Indicates that there is only one instance of the resource in the whole cluster and that this resource is shared by all of the hosts

Use the not operator (`~`) to exclude hosts from the `all` specification. For example:

```
(2@[all ~host3 ~host4])
```

means that 2 units of the resource are shared by all server hosts in the cluster made up of `host1 host2 . . . hostn`, except for `host3` and `host4`. This is useful if you have a large cluster but only want to exclude a few hosts.

The parentheses are required in the specification. The not operator can only be used with the `all` keyword. It is not valid with the keywords `others` and `default`.

`others` — Indicates that the rest of the server hosts not explicitly listed in the `LOCATION` field comprise one instance of the resource

For example:

```
2@[host1] 4@[others]
```

indicates that there are 2 units of the resource on host 1 and 4 units of the resource shared by all other hosts.

default — Indicates an instance of a resource on each host in the cluster

This specifies a special case where the resource is in effect not shared and is local to every host. default means at each host. Normally, you should not need to use default, because by default all resources are local to each host. You might want to use ResourceMap for a non-shared static resource if you need to specify different values for the resource on different hosts.

## RESOURCENAME

### Description

Name of the resource

This resource name must be defined in the Resource section of `lsf.shared`. You must specify at least a name and description for the resource, using the keywords RESOURCENAME and DESCRIPTION.

- A resource name cannot begin with a number.
- A resource name cannot contain any of the following characters:  
: . ( ) [ + - \* / ! & | < > @ =
- A resource name cannot be any of the following reserved names:  
cpu cpuf io logins ls idle maxmem maxswp maxtmp type model status it  
mem ncpus define\_ncpus\_cores define\_ncpus\_procs  
define\_ncpus\_threads ndisks pg r15m r15s r1m swap swp tmp ut
- To avoid conflict with inf and nan keywords in 3rd-party libraries, resource names should not begin with inf or nan (upper case or lower case). Resource requirement strings, such as `-R "infra"` or `-R "nano"` will cause an error. Use `-R "defined(infxx)"` or `-R "defined(nanxx)"`, to specify these resource names.
- Resource names are case sensitive
- Resource names can be up to 39 characters in length

### RemoteClusters section

Optional. This section is used only in a MultiCluster environment. By default, the local cluster can obtain information about all other clusters specified in `lsf.shared`. The RemoteClusters section limits the clusters that the local cluster can obtain information about.

The RemoteClusters section is required if you want to configure cluster equivalency, cache interval, daemon authentication across clusters, or if you want to run parallel jobs across clusters. To maintain compatibility in this case, make sure the list includes all clusters specified in `lsf.shared`, even if you only configure the default behavior for some of the clusters.

The first line consists of keywords. CLUSTERNAME is mandatory and the other parameters are optional.

Subsequent lines configure the remote cluster.

## Example RemoteClusters section

```

Begin RemoteClusters
CLUSTERNAME  EQUIV  CACHE_INTERVAL  RECV_FROM  AUTH
cluster1     Y      60              Y          KRB
cluster2     N      60              Y          -
cluster4     N      60              N          PKI
End RemoteClusters

```

### CLUSTERNAME

#### Description

Remote cluster name

Defines the Remote Cluster list. Specify the clusters you want the local cluster will recognize. Recognized clusters must also be defined in `lsf.shared`. Additional clusters listed in `lsf.shared` but not listed here will be ignored by this cluster.

### EQUIV

#### Description

Specify 'Y' to make the remote cluster equivalent to the local cluster. Otherwise, specify 'N'. The master LIM considers all equivalent clusters when servicing requests from clients for load, host, or placement information.

EQUIV changes the default behavior of LSF commands and utilities and causes them to automatically return load (`lsload(1)`), host (`lshosts(1)`), or placement (`lsplace(1)`) information about the remote cluster as well as the local cluster, even when you don't specify a cluster name.

### CACHE\_INTERVAL

#### Description

Specify the load information cache threshold, in seconds. The host information threshold is twice the value of the load information threshold.

To reduce overhead and avoid updating information from remote clusters unnecessarily, LSF displays information in the cache, unless the information in the cache is older than the threshold value.

#### Default

60 (seconds)

### RECV\_FROM

#### Description

Specifies whether the local cluster accepts parallel jobs that originate in a remote cluster. RECV\_FROM does not affect regular or interactive batch jobs.

Specify 'Y' if you want to run parallel jobs across clusters. Otherwise, specify 'N'.

## Default

Y

## AUTH

### Description

Defines the preferred authentication method for LSF daemons communicating across clusters. Specify the same method name that is used to identify the corresponding `eauth` program (`eauth.method_name`). If the remote cluster does not prefer the same method, LSF uses default security between the two clusters.

## Default

- (only privileged port (setuid) authentication is used between clusters)

# lsf.*cluster\_name*.license.acct

This is the license accounting file. There is one for each cluster, called lsf. *cluster\_name*. license. acct. The *cluster\_name* variable is the name of the cluster defined in the Cluster section of lsf. shared.

The lsf. *cluster\_name*. license. acct file contains three types of configuration information:

- LSF license information
- MultiCluster license information

## lsf.*cluster\_name*.license.acct structure

The license audit log file is an ASCII file with one record per line. The fields of a record are separated by blanks.

## File properties

### Location

The default location of this file is defined by LSF\_LOGDIR in lsf. conf, but you can override this by defining LSF\_LICENSE\_ACCT\_PATH in lsf. conf.

### Owner

The primary LSF admin is the owner of this file.

### Permissions

```
-rw-r--r--
```

## Records and fields

The fields of a record are separated by blanks. The fields in order of occurrence are as follows:

### timestamp (%d)

Time stamp of the logged event (in seconds since the epoch).

### type (%s)

The LSF product type. The valid values are as follows:

- LSF\_MANAGER
- LSF\_MULTI CLUSTER

### version (%s)

The version of the LSF product.

### value (%s)

The actual tracked value. The format of this field depends on the product type as specified by the type field:

### LSF\_MANAGER

*E e\_peak e\_max\_avail S s\_peak s\_max\_avail B b\_peak b\_max\_avail*

Where

*e\_peak*, *s\_peak*, and *b\_peak* are the peak usage values (in number of CPUs) of the E, S, and B class licenses, respectively.

*e\_max\_avail*, *s\_max\_avail*, and *b\_max\_avail* are the maximum availability and usage values (in number of CPUs) of the E, S, and B class licenses, respectively. This is determined by the license that you purchased.

## LSF\_MULTICLUSTER

*mc\_peak mc\_max\_avail*

Where

*mc\_peak* is the peak usage value (in number of CPUs) of the LSF MultiCluster license

*mc\_max\_avail* is the maximum availability and usage (in number of CPUs) of the LSF MultiCluster license. This is determined by the license that you purchased.

## status (%s)

The results of the license usage check. The valid values are as follows:

## OK

Peak usage is less than the maximum license availability

## OVERUSE

Peak usage is more than the maximum license availability

## hash (%s)

Line encryption used to authenticate the record.

## Example record Format

```
1128372131 LSF_MANAGER 7.0 E hostA OVERUSE 7c7998a6861ea119cd48414a820be18cd641
1128372131 LSF_MULTICLUSTER 7.0 8 10 OK 281288c606a50065ea0e2f3e7161972c56491dc
1128372185 LSF_MANAGER 7.0 E 8 0 S 0 2 B 0 10 OVERUSE fb439ee293821761af9ed0785 1128372185
LSF_MANAGER 7.0 E hostA OVERUSE 2d22a06d6c5cfd5aba40875c2cb8544444a5
```

# lsf.conf

The `lsf.conf` file controls the operation of LSF.

## About lsf.conf

`lsf.conf` is created during installation and records all the settings chosen when LSF was installed. The `lsf.conf` file dictates the location of the specific configuration files and operation of individual servers and applications.

The `lsf.conf` file is used by LSF and applications built on top of it. For example, information in `lsf.conf` is used by LSF daemons and commands to locate other configuration files, executables, and network services. `lsf.conf` is updated, if necessary, when you upgrade to a new version.

This file can also be expanded to include application-specific parameters.

## Corresponding parameters in ego.conf

When Platform EGO is enabled in LSF Version 7, you can configure some LSF parameters in `lsf.conf` that have corresponding Platform EGO parameter names in `EGO_CONFDIR/ego.conf` (`LSF_CONFDIR/lsf.conf` is a separate file from `EGO_CONFDIR/ego.conf`). If both the LSF and the EGO parameters are set in their respective files, the definition in `ego.conf` is used. You must continue to set LSF parameters only in `lsf.conf`.

When EGO is enabled in the LSF cluster (`LSF_ENABLE_EGO=Y`), you also can set the following EGO parameters related to LIM, PIM, and ELIM in either `lsf.conf` or `ego.conf`:

- `EGO_DISABLE_UNRESOLVABLE_HOST` (dynamically added hosts only)
- `EGO_PREDEFINED_RESOURCES`
- `EGO_ENABLE_AUTO_DAEMON_SHUTDOWN`
- `EGO_DAEMONS_CPUS`
- `EGO_DEFINE_NCPUS`
- `EGO_SLAVE_CTRL_REMOTE_HOST`
- `EGO_WORKDIR`
- `EGO_PIM_SWAP_REPORT`
- `EGO_ESLIM_TIMEOUT`

If EGO is not enabled, you can set these parameters only in `lsf.conf`.

See *Administering Platform LSF* for more information about configuring LSF for EGO. See the *Platform EGO Reference* for information about `ego.conf` parameters.

## Changing lsf.conf configuration

After making any changes to `lsf.conf`, run the following commands:

- `lsadmin reconfig` to reconfigure LIM
- `badmin mbdrestart` to restart `mbatchd`

If you have installed LSF in a mixed cluster, you must make sure that `lsf.conf` parameters set on UNIX and Linux match any corresponding parameters in the local `lsf.conf` files on your Windows hosts.

## Location

The default location of `lsf.conf` is in `/conf`. This default location can be overridden when necessary by either the environment variable `LSF_ENVDIR` or the command line option `-d` available to some of the applications.

## Format

Each entry in `lsf.conf` has one of the following forms:

```
NAME=VALUE
```

```
NAME=
```

```
NAME="STRING1 STRING2 ..."
```

The equal sign = must follow each NAME even if no value follows and there should be no space beside the equal sign.

A value that contains multiple strings separated by spaces must be enclosed in quotation marks.

Lines starting with a pound sign (#) are comments and are ignored. Do not use #if as this is reserved syntax for time-based configuration.

## DAEMON\_SHUTDOWN\_DELAY

### Syntax

```
DAEMON_SHUTDOWN_DELAY=time_in_seconds
```

### Description

Applies when `EGO_ENABLE_AUTO_DAEMON_SHUTDOWN=Y`. Controls amount of time the slave LIM waits to communicate with other (RES and SBD) local daemons before exiting. Used to shorten or lengthen the time interval between a host attempting to join the cluster and, if it was unsuccessful, all of the local daemons shutting down.

The value should not be less than the minimum interval of RES and SBD housekeeping. Most administrators should set this value to somewhere between 3 minutes and 60 minutes.

### Default

1800 seconds (30 minutes)

## EGO\_DEFINE\_NCPUS

### Syntax

```
EGO_DEFINE_NCPUS=procs | cores | threads
```

### Description

If defined, enables an administrator to define a value other than the number of processors available. Follow one of the three equations below for an accurate value.

- `EGO_DEFINE_NCPUS=procs-ncpus=number of processors`
- `EGO_DEFINE_NCPUS=cores-ncpus=number of processors x number of cores`
- `EGO_DEFINE_NCPUS=threads-ncpus=number of processors x number of cores x number of threads.`

---

#### Note:

When `PARALLEL_SCHED_BY_SLOT=Y` in `lsb.params`, the resource requirement string keyword `ncpus` refers to the number of slots instead of the number of processors, however `lshosts` output will continue to show `ncpus` as defined by `EGO_DEFINE_NCPUS` in `lsf.conf`.

---

## Default

EGO\_DEFINE\_NCPUS=procs

## EGO\_ENABLE\_AUTO\_DAEMON\_SHUTDOWN

### Syntax

EGO\_ENABLE\_AUTO\_DAEMON\_SHUTDOWN="Y" | "N"

### Description

For hosts that attempted to join the cluster but failed to communicate within the LSF\_DYNAMIC\_HOST\_WAIT\_TIME period, automatically shuts down any running daemons.

This parameter can be useful if an administrator remove machines from the cluster regularly (by editing `lsf.cluster` file) or when a host belonging to the cluster is imaged, but the new host should not be part of the cluster. An administrator no longer has to go to each host that is not a part of the cluster to shut down any running daemons.

## Default

N (daemons continue to run on hosts that were not successfully added to the cluster)

## EGO\_PARAMETER

EGO\_ENABLE\_AUTO\_DAEMON\_SHUTDOWN

## EGO\_ESLIM\_TIMEOUT

### Syntax

EGO\_ESLIM\_TIMEOUT=*time\_seconds*

### Description

Controls how long the LIM waits for any external static LIM scripts to run. After the timeout period expires, the LIM stops the scripts.

Use the external static LIM to automatically detect the operating system type and version of hosts.

LSF automatically detects the operating systems types and versions and displays them when running `lshosts -l` or `lshosts -s`. You can then specify those types in any `-R` resource requirement string. For example, `bsub -R "select[ostype=RHEL4.6]"`.

## Default

10 seconds

## EGO\_PARAMETER

EGO\_ESLIM\_TIMEOUT

## LSB\_API\_CONNTIMEOUT

### Syntax

**LSB\_API\_CONNTIMEOUT**=*time\_seconds*

### Description

The timeout in seconds when connecting to LSF.

### Valid values

Any positive integer or zero

### Default

10

### See also

LSB\_API\_RECVTIMEOUT

## LSB\_API\_RECVTIMEOUT

### Syntax

**LSB\_API\_RECVTIMEOUT**=*time\_seconds*

### Description

Timeout in seconds when waiting for a reply from LSF.

### Valid values

Any positive integer or zero

### Default

10

### See also

LSB\_API\_CONNTIMEOUT

## LSB\_API\_VERBOSE

### Syntax

**LSB\_API\_VERBOSE**=Y | N

### Description

When LSB\_API\_VERBOSE=Y, LSF batch commands will display a retry error message to `stderr` when LIM is not available:

LSF daemon (LIM) not responding ... still trying

When `LSB_API_VERBOSE=N`, LSF batch commands will not display a retry error message when LIM is not available.

## Default

Y. Retry message is displayed to `stderr`.

## LSB\_BJOBS\_CONSISTENT\_EXIT\_CODE

## Syntax

`LSB_BJOBS_CONSISTENT_EXIT_CODE=Y | N`

## Description

When `LSB_BJOBS_CONSISTENT_EXIT_CODE=Y`, the `bjobs` command exits with 0 only when unfinished jobs are found, and 255 when no jobs are found, or a non-existent job ID is entered.

No jobs are running:

```
bjobs
```

```
No unfinished job found
```

```
echo $?
```

```
255
```

Job 123 does not exist:

```
bjobs 123
```

```
Job <123> is not found
```

```
echo $?
```

```
255
```

Job 111 is running:

```
bjobs 111
```

| JOBID | USER  | STAT | QUEUE  | FROM_HOST | EXEC_HOST | JOB_NAME | SUBMIT_TIME  |
|-------|-------|------|--------|-----------|-----------|----------|--------------|
| 111   | user1 | RUN  | normal | hostA     | hostB     | myjob    | Oct 22 09:22 |

```
echo $?
```

```
0
```

Job 111 is running, and job 123 does not exist:

```
bjobs 111 123
```

| JOBID | USER  | STAT | QUEUE  | FROM_HOST | EXEC_HOST | JOB_NAME | SUBMIT_TIME  |
|-------|-------|------|--------|-----------|-----------|----------|--------------|
| 111   | user1 | RUN  | normal | hostA     | hostB     | myjob    | Oct 22 09:22 |

```
Job <123> is not found
```

```
echo $?
```

```
255
```

Job 111 is finished:

```
bjobs 111
```

```
No unfinished job found
```

```
echo $?
```

```
255
```

When `LSB_BJOBS_CONSISTENT_EXIT_CODE=N`, the `bj obs` command exits with 255 only when a non-existent job ID is entered. `bj obs` returns 0 when no jobs are found, all jobs are finished, or if at least one job ID is valid.

No jobs are running:

```
bjobs
```

```
No unfinished job found
```

```
echo $?
```

```
0
```

Job 123 does not exist:

```
bjobs 123
```

```
Job <123> is not found
```

```
echo $?
```

```
0
```

Job 111 is running:

```
bjobs 111
```

| JOBID | USER  | STAT | QUEUE  | FROM_HOST | EXEC_HOST | JOB_NAME | SUBMIT_TIME  |
|-------|-------|------|--------|-----------|-----------|----------|--------------|
| 111   | user1 | RUN  | normal | hostA     | hostB     | myjob    | Oct 22 09:22 |

```
echo $?
```

```
0
```

Job 111 is running, and job 123 does not exist:

```
bjobs 111 123
```

| JOBID | USER  | STAT | QUEUE  | FROM_HOST | EXEC_HOST | JOB_NAME | SUBMIT_TIME  |
|-------|-------|------|--------|-----------|-----------|----------|--------------|
| 111   | user1 | RUN  | normal | hostA     | hostB     | myjob    | Oct 22 09:22 |

```
Job <123> is not found
```

```
echo $?
```

```
255
```

Job 111 is finished:

```
bjobs 111
```

```
No unfinished job found
```

```
echo $?
```

```
0
```

## Default

N.

## LSB\_BLOCK\_JOBINFO\_TIMEOUT

### Syntax

```
LSB_BLOCK_JOBINFO_TIMEOUT=time_minutes
```

### Description

Timeout in minutes for job information query commands (e.g., `bj obs`).

lsf.conf

## Valid values

Any positive integer

## Default

Not defined (no timeout)

## See also

MAX\_JOBINFO\_QUERY\_PERIOD in lsb.params

## LSB\_BPEEK\_METHOD

### Syntax

**LSB\_BPEEK\_METHOD="rsh" | "lsrun"**

### Description

Specifies to bpeek how to get output of a remote running job.

## Valid values

Specify "rsh" or "lsrun" or both, in the order you want to invoke the bpeek method.

## Default

"rsh lsrun"

## LSB\_BPEEK\_WAIT\_TIME

### Syntax

**LSB\_BPEEK\_WAIT\_TIME=*seconds***

### Description

Defines how long the bpeek process waits to get the output of a remote running job.

## Valid values

Any positive integer

## Default

80 seconds

## LSB\_CHUNK\_RUSAGE

### Syntax

**LSB\_CHUNK\_RUSAGE=*y***

### Description

Applies only to chunk jobs. When set, sbat chd contacts PIM to retrieve resource usage information to enforce resource usage limits on chunk jobs.

By default, resource usage limits are not enforced for chunk jobs because chunk jobs are typically too short to allow LSF to collect resource usage.

If `LSB_CHUNK_RUSAGE=Y` is defined, limits may not be enforced for chunk jobs that take less than a minute to run.

## Default

Not defined. No resource usage is collected for chunk jobs.

## LSB\_CMD\_LOG\_MASK

### Syntax

`LSB_CMD_LOG_MASK=log_level`

### Description

Specifies the logging level of error messages from LSF batch commands.

To specify the logging level of error messages for LSF commands, use `LSB_CMD_LOG_MASK`. To specify the logging level of error messages for LSF daemons, use `LSF_LOG_MASK`.

`LSB_CMD_LOG_MASK` sets the log level and is used in combination with `LSB_DEBUG_CMD`, which sets the log class for LSF batch commands. For example:

```
LSB_CMD_LOG_MASK=LOG_DEBUG LSB_DEBUG_CMD="LC_TRACE LC_EXEC"
```

LSF commands log error messages in different levels so that you can choose to log all messages, or only log messages that are deemed critical. The level specified by `LSB_CMD_LOG_MASK` determines which messages are recorded and which are discarded. All messages logged at the specified level or higher are recorded, while lower level messages are discarded.

For debugging purposes, the level `LOG_DEBUG` contains the fewest number of debugging messages and is used for basic debugging. The level `LOG_DEBUG3` records all debugging messages, and can cause log files to grow very large; it is not often used. Most debugging is done at the level `LOG_DEBUG2`.

The commands log to the `syslog` facility unless `LSB_CMD_LOGDIR` is set.

### Valid values

The log levels from highest to lowest are:

- `LOG_EMERG`
- `LOG_ALERT`
- `LOG_CRIT`
- `LOG_ERR`
- `LOG_WARNING`
- `LOG_NOTICE`
- `LOG_INFO`
- `LOG_DEBUG`
- `LOG_DEBUG1`
- `LOG_DEBUG2`
- `LOG_DEBUG3`

lsf.conf

## Default

LOG\_WARNING

## See also

LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD, LSB\_TIME\_CMD,  
LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR,  
LSF\_TIME\_CMD

## LSB\_CMD\_LOGDIR

### Syntax

**LSB\_CMD\_LOGDIR=***path*

### Description

Specifies the path to the LSF command log files.

### Default

/tmp

## See also

LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD, LSB\_TIME\_CMD,  
LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR,  
LSF\_TIME\_CMD

## LSB\_CPUSET\_BESTCPUS

### Syntax

**LSB\_CPUSET\_BESTCPUS=***y* | Y

### Description

If set, enables the best-fit algorithm for SGI cpusets

### Default

Y (best-fit)

## LSB\_CONFDIR

### Syntax

**LSB\_CONFDIR=***path*

### Description

Specifies the path to the directory containing the LSF configuration files.  
The configuration directories are installed under LSB\_CONFDIR.

Configuration files for each cluster are stored in a subdirectory of `LSB_CONFDIR`. This subdirectory contains several files that define user and host lists, operation parameters, and queues.

All files and directories under `LSB_CONFDIR` must be readable from all hosts in the cluster. `LSB_CONFDIR/cluster_name/configdir` must be owned by the LSF administrator.

---

**Caution:**

Do not change this parameter after LSF has been installed.

---

## Default

`LSB_CONFDIR/lsbatch`

## See also

`LSB_CONFDIR`

## LSB\_CRDIR

### Syntax

**LSB\_CRDIR**=*path*

### Description

Specifies the path and directory to the checkpointing executables on systems that support kernel-level checkpointing. `LSB_CRDIR` specifies the directory containing the `chkpnt` and `restart` utility programs that `sbatchd` uses to checkpoint or restart a job.

For example:

```
LSB_CRDIR=/usr/bin
```

If your platform supports kernel-level checkpointing, and if you want to use the utility programs provided for kernel-level checkpointing, set `LSB_CRDIR` to the location of the utility programs.

## Default

Not defined. The system uses `/bin`.

## LSB\_DEBUG

### Syntax

**LSB\_DEBUG**=1 | 2

### Description

Sets the LSF batch system to debug.

If defined, LSF runs in single user mode:

- No security checking is performed
- Daemons do not run as root

When `LSB_DEBUG` is defined, LSF does not look in the system services database for port numbers. Instead, it uses the port numbers defined by the parameters `LSB_MBD_PORT/`

LSB\_SBD\_PORT in `lsf.conf`. If these parameters are not defined, it uses port number 40000 for `mbatchd` and port number 40001 for `sbatchd`.

You should always specify 1 for this parameter unless you are testing LSF.

Can also be defined from the command line.

## Valid values

LSB\_DEBUG=1

The LSF system runs in the background with no associated control terminal.

LSB\_DEBUG=2

The LSF system runs in the foreground and prints error messages to `tty`.

## Default

Not defined

## See also

LSB\_DEBUG, LSB\_DEBUG\_CMD, LSB\_DEBUG\_MBD, LSB\_DEBUG\_NQS, LSB\_DEBUG\_SBD, LSB\_DEBUG\_SCH, LSF\_DEBUG\_LIM, LSF\_DEBUG\_RES, LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT, LSF\_LOGDIR, LSF\_LIM\_DEBUG, LSF\_RES\_DEBUG

## LSB\_DEBUG\_CMD

### Syntax

**LSB\_DEBUG\_CMD**=*log\_class*

### Description

Sets the debugging log class for commands and APIs.

Specifies the log class filtering to be applied to LSF batch commands or the API. Only messages belonging to the specified log class are recorded.

LSB\_DEBUG\_CMD sets the log class and is used in combination with LSB\_CMD\_LOG\_MASK, which sets the log level. For example:

```
LSB_CMD_LOG_MASK=LOG_DEBUG LSB_DEBUG_CMD="LC_TRACE LC_EXEC"
```

Debugging is turned on when you define both parameters.

The daemons log to the `syslog` facility unless LSB\_CMD\_LOGDIR is defined.

To specify multiple log classes, use a space-separated list enclosed by quotation marks. For example:

```
LSB_DEBUG_CMD="LC_TRACE LC_EXEC"
```

Can also be defined from the command line.

## Valid values

Valid log classes are:

- LC\_ADVRSV - Log advance reservation modifications

- LC\_AFS - Log AFS messages
- LC\_AUTH - Log authentication messages
- LC\_CHKPNT - Log checkpointing messages
- LC\_COMM - Log communication messages
- LC\_DCE - Log messages pertaining to DCE support
- LC\_EEVENTD - Log eeveventd messages
- LC\_ELIM - Log ELIM messages
- LC\_EXEC - Log significant steps for job execution
- LC\_FAIR - Log fairshare policy messages
- LC\_FILE - Log file transfer messages
- LC\_HANG - Mark where a program might hang
- LC\_JARRAY - Log job array messages
- LC\_JLIMIT - Log job slot limit messages
- LC\_LICENSE - Log license management messages (LC\_LICENSE is also supported for backward compatibility)
- LC\_LOADINDX - Log load index messages
- LC\_M\_LOG - Log multievent logging messages
- LC\_MPI - Log MPI messages
- LC\_MULTI - Log messages pertaining to MultiCluster
- LC\_PEND - Log messages related to job pending reasons
- LC\_PERFM - Log performance messages
- LC\_PIM - Log PIM messages
- LC\_PREEMPT - Log preemption policy messages
- LC\_RESREQ - Log resource requirement messages
- LC\_SIGNAL - Log messages pertaining to signals
- LC\_SYS - Log system call messages
- LC\_TRACE - Log significant program walk steps
- LC\_XDR - Log everything transferred by XDR

## Default

Not defined

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_MBD, LSB\_DEBUG\_NQS, LSB\_DEBUG\_SBD, LSB\_DEBUG\_SCH, LSF\_DEBUG\_LIM, LSF\_DEBUG\_RES, LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT, LSF\_LOGDIR, LSF\_LIM\_DEBUG, LSF\_RES\_DEBUG

## LSB\_DEBUG\_MBD

### Syntax

**LSB\_DEBUG\_MBD**=*log\_class*

### Description

Sets the debugging log class for mbatchd.

Specifies the log class filtering to be applied to mbatchd. Only messages belonging to the specified log class are recorded.

LSB\_DEBUG\_MBD sets the log class and is used in combination with LSF\_LOG\_MASK, which sets the log level. For example:

```
LSF_LOG_MASK=LOG_DEBUG LSB_DEBUG_MBD="LC_TRACE LC_EXEC"
```

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSB_DEBUG_MBD="LC_TRACE LC_EXEC"
```

You need to restart the daemons after setting LSB\_DEBUG\_MBD for your changes to take effect.

If you use the command `badmi n mbddebug` to temporarily change this parameter without changing `lsf.conf`, you do not need to restart the daemons.

## Valid values

Valid log classes are the same as for LSB\_DEBUG\_CMD except for the log class LC\_ELIM, which cannot be used with LSB\_DEBUG\_MBD. See LSB\_DEBUG\_CMD.

## Default

Not defined

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_MBD, LSB\_DEBUG\_NQS, LSB\_DEBUG\_SBD, LSB\_DEBUG\_SCH, LSF\_DEBUG\_LIM, LSF\_DEBUG\_RES, LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT, LSF\_LOGDIR, LSF\_LIM\_DEBUG, LSF\_RES\_DEBUG

## LSB\_DEBUG\_NQS

### Syntax

```
LSB_DEBUG_NQS=log_class
```

### Description

Sets the log class for debugging the NQS interface.

Specifies the log class filtering to be applied to NQS. Only messages belonging to the specified log class are recorded.

LSB\_DEBUG\_NQS sets the log class and is used in combination with LSF\_LOG\_MASK, which sets the log level. For example:

```
LSF_LOG_MASK=LOG_DEBUG LSB_DEBUG_NQS="LC_TRACE LC_EXEC"
```

Debugging is turned on when you define both parameters.

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSB_DEBUG_NQS="LC_TRACE LC_EXEC"
```

This parameter can also be defined from the command line.

## Valid values

For a list of valid log classes, see LSB\_DEBUG\_CMD.

## Default

Not defined

## See also

LSB\_DEBUG\_CMD, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK,  
LSF\_LOGDIR

## LSB\_DEBUG\_SBD

### Syntax

**LSB\_DEBUG\_SBD**=*log\_class*

### Description

Sets the debugging log class for sbatchd.

Specifies the log class filtering to be applied to sbatchd. Only messages belonging to the specified log class are recorded.

LSB\_DEBUG\_SBD sets the log class and is used in combination with LSF\_LOG\_MASK, which sets the log level. For example:

```
LSF_LOG_MASK=LOG_DEBUG LSB_DEBUG_SBD="LC_TRACE LC_EXEC"
```

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSB_DEBUG_SBD="LC_TRACE LC_EXEC"
```

You need to restart the daemons after setting LSB\_DEBUG\_SBD for your changes to take effect.

If you use the command `badmi n sbddebug` to temporarily change this parameter without changing `lsf.conf`, you do not need to restart the daemons.

### Valid values

Valid log classes are the same as for LSB\_DEBUG\_CMD except for the log class LC\_ELIM, which cannot be used with LSB\_DEBUG\_SBD. See LSB\_DEBUG\_CMD.

## Default

Not defined

## See also

LSB\_DEBUG\_MBD, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK,  
LSF\_LOGDIR, badmi n

## LSB\_DEBUG\_SCH

### Syntax

**LSB\_DEBUG\_SCH**=*log\_class*

## Description

Sets the debugging log class for mbschd.

Specifies the log class filtering to be applied to mbschd. Only messages belonging to the specified log class are recorded.

LSB\_DEBUG\_SCH sets the log class and is used in combination with LSF\_LOG\_MASK, which sets the log level. For example:

```
LSF_LOG_MASK=LOG_DEBUG LSB_DEBUG_SCH="LC_SCHED"
```

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSB_DEBUG_SCH="LC_SCHED LC_TRACE LC_EXEC"
```

You need to restart the daemons after setting LSB\_DEBUG\_SCH for your changes to take effect.

## Valid values

Valid log classes are the same as for LSB\_DEBUG\_CMD except for the log class LC\_ELIM, which cannot be used with LSB\_DEBUG\_SCH, and LC\_HPC and LC\_SCHED, which are only valid for LSB\_DEBUG\_SCH. See LSB\_DEBUG\_CMD.

## Default

Not defined

## See also

LSB\_DEBUG\_MBD, LSB\_DEBUG\_SBD, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR, badmi n

## LSB\_DISABLE\_LIMLOCK\_EXCL

### Syntax

```
LSB_DISABLE_LIMLOCK_EXCL=y | n
```

### Description

If preemptive scheduling is enabled, this parameter enables preemption of and preemption by exclusive jobs when PREEMPT\_JOBTYPE=EXCLUSIVE in lsb.params. Changing this parameter requires a restart of all sbatchds in the cluster (badmi n hrestart). Do not change this parameter while exclusive jobs are running.

When LSB\_DISABLE\_LIMLOCK\_EXCL=y, for a host running an exclusive job:

- LIM is not locked on a host running an exclusive job
- lsl oad displays the host status ok.
- bhost.s displays the host status closed.
- Users can run tasks on the host using lsr un or l sgr un. To prevent users from running tasks during execution of an exclusive job, the parameter LSF\_DISABLE\_LSRUN=y must be defined in lsf.conf.

## Default

n. LSF locks the LIM on a host running an exclusive job and unlocks the LIM when the exclusive job finishes.

## LSB\_DISABLE\_RERUN\_POST\_EXEC

### Syntax

**LSB\_DISABLE\_RERUN\_POST\_EXEC=y | Y**

### Description

If set, and the job is rerunnable, the POST\_EXEC configured in the queue is not executed if the job is rerun.

Running of post-execution commands upon restart of a rerunnable job may not always be desirable. For example, if the post-exec removes certain files, or does other cleanup that should only happen if the job finishes successfully, use LSB\_DISABLE\_RERUN\_POST\_EXEC to prevent the post-exec from running and allow the successful continuation of the job when it reruns.

## Default

Not defined

## LSB\_ECHKPNT\_KEEP\_OUTPUT

### Syntax

**LSB\_ECHKPNT\_KEEP\_OUTPUT=y | Y**

### Description

Saves the standard output and standard error of custom echkpt and erestart methods to:

- `checkpoint_dir/$LSB_JOBID/echkpt.out`
- `checkpoint_dir/$LSB_JOBID/echkpt.err`
- `checkpoint_dir/$LSB_JOBID/erestart.out`
- `checkpoint_dir/$LSB_JOBID/erestart.err`

Can also be defined as an environment variable.

## Default

Not defined. Standard error and standard output messages from custom echkpt and erestart programs is directed to `/dev/null` and discarded by LSF.

## See also

LSB\_ECHKPNT\_METHOD, LSB\_ECHKPNT\_METHOD\_DIR

## LSB\_ECHKPNT\_METHOD

### Syntax

**LSB\_ECHKPNT\_METHOD="method\_name [method\_name] ..."**

## Description

Name of custom `echkpnt` and `erestart` methods.

Can also be defined as an environment variable, or specified through the `bsub -k` option.

The name you specify here is used for both your custom `echkpnt` and `erestart` programs. You must assign your custom `echkpnt` and `erestart` programs the name `echkpnt.method_name` and `erestart.method_name`. The programs `echkpnt.method_name` and `erestart.method_name` must be in `LSF_SERVERDIR` or in the directory specified by `LSB_ECHKPNT_METHOD_DIR`.

Do not define `LSB_ECHKPNT_METHOD=default` as `default` is a reserved keyword to indicate to use the default `echkpnt` and `erestart` methods of LSF. You can however, specify `bsub -k "my_dir method=default" my_job` to indicate that you want to use the default checkpoint and restart methods.

When this parameter is not defined in `lsf.conf` or as an environment variable and no custom method is specified at job submission through `bsub -k`, LSF uses `echkpnt.default` and `erestart.default` to checkpoint and restart jobs.

When this parameter is defined, LSF uses the custom checkpoint and restart methods specified.

## Limitations

The method name and directory (`LSB_ECHKPNT_METHOD_DIR`) combination must be unique in the cluster.

For example, you may have two `echkpnt` applications with the same name such as `echkpnt.mymethod` but what differentiates them is the different directories defined with `LSB_ECHKPNT_METHOD_DIR`. It is the cluster administrator's responsibility to ensure that method name and method directory combinations are unique in the cluster.

## Default

Not defined. LSF uses `echkpnt.default` and `erestart.default` to checkpoint and restart jobs

## See also

`LSB_ECHKPNT_METHOD_DIR`, `LSB_ECHKPNT_KEEP_OUTPUT`

## LSB\_ECHKPNT\_METHOD\_DIR

## Syntax

`LSB_ECHKPNT_METHOD_DIR=path`

## Description

Absolute path name of the directory in which custom `echkpnt` and `erestart` programs are located.

The checkpoint method directory should be accessible by all users who need to run the custom `echkpnt` and `erestart` programs.

Can also be defined as an environment variable.

## Default

Not defined. LSF searches in `LSF_SERVERDIR` for custom `echkptnt` and `erestart` programs.

## See also

`LSB_ESUB_METHOD`, `LSB_ECHKPNT_KEEP_OUTPUT`

## LSB\_ESUB\_METHOD

### Syntax

```
LSB_ESUB_METHOD="esub_application [esub_application] ..."
```

### Description

Specifies a mandatory esub that applies to all job submissions. `LSB_ESUB_METHOD` lists the names of the application-specific esub executables used in addition to any executables specified by the `bsub -a` option.

For example, `LSB_ESUB_METHOD="dce fluent"` runs `LSF_SERVERDIR/esub.dce` and `LSF_SERVERDIR/esub.fluent` for all jobs submitted to the cluster. These esubs define, respectively, DCE as the mandatory security system and FLUENT as the mandatory application for all jobs.

`LSB_ESUB_METHOD` can also be defined as an environment variable.

The value of `LSB_ESUB_METHOD` must correspond to an actual esub file. For example, to use `LSB_ESUB_METHOD=fluent`, the file `esub.fluent` must exist in `LSF_SERVERDIR`.

The name of the esub program must be a valid file name. Valid file names contain only alphanumeric characters, underscore (`_`) and hyphen (`-`).

---

#### Restriction:

The name `esub.user` is reserved. Do not use the name `esub.user` for an application-specific esub.

---

The master esub (`mesub`) uses the name you specify to invoke the appropriate esub program. The `esub` and `esub.esub_application` programs must be located in `LSF_SERVERDIR`.

LSF does not detect conflicts based on esub names. For example, if `LSB_ESUB_METHOD="openmpi"` and `bsub -a pvm` is specified at job submission, the job could fail because these esubs define two different types of parallel job handling.

## Default

Not defined. LSF does not apply a mandatory esub to jobs submitted to the cluster.

## LSB\_INTERACT\_MSG\_ENH

### Syntax

```
LSB_INTERACT_MSG_ENH=y | Y
```

## Description

If set, enables enhanced messaging for interactive batch jobs. To disable interactive batch job messages, set `LSB_INTERACT_MSG_ENH` to any value other than `y` or `Y`; for example, `LSB_INTERACT_MSG_ENH=N`.

## Default

Not defined

## See also

`LSB_INTERACT_MSG_INTVAL`

## LSB\_INTERACT\_MSG\_INTVAL

## Syntax

`LSB_INTERACT_MSG_INTVAL=time_seconds`

## Description

Specifies the update interval in seconds for interactive batch job messages. `LSB_INTERACT_MSG_INTVAL` is ignored if `LSB_INTERACT_MSG_ENH` is not set.

Job information that LSF uses to get the pending or suspension reason is updated according to the value of `PEND_REASON_UPDATE_INTERVAL` in `lsb.params`.

## Default

Not defined. If `LSB_INTERACT_MSG_INTVAL` is set to an incorrect value, the default update interval is 60 seconds.

## See also

`LSB_INTERACT_MSG_ENH`

## LSB\_JOBID\_DISP\_LENGTH

## Syntax

`LSB_JOBID_DISP_LENGTH=integer`

## Description

By default, LSF commands `bjobs` and `bhist` display job IDs with a maximum length of 7 characters. Job IDs greater than 9999999 are truncated on the left.

When `LSB_JOBID_DISP_LENGTH=10`, the width of the `JOBID` column in `bjobs` and `bhist` increases to 10 characters.

## Valid values

Specify an integer between 7 and 10.

## Default

Not defined. LSF uses the default 7-character length for job ID display.

## LSB\_JOB\_CPULIMIT

### Syntax

**LSB\_JOB\_CPULIMIT=y | n**

### Description

Determines whether the CPU limit is a per-process limit enforced by the OS or whether it is a per-job limit enforced by LSF:

- The per-process limit is enforced by the OS when the CPU time of one process of the job exceeds the CPU limit.
- The per-job limit is enforced by LSF when the total CPU time of all processes of the job exceed the CPU limit.

This parameter applies to CPU limits set when a job is submitted with `bsub -c`, and to CPU limits set for queues by `CPULIMIT` in `l sb. queues`.

- **LSF-enforced per-job limit:** When the sum of the CPU time of all processes of a job exceed the CPU limit, LSF sends a `SIGXCPU` signal (where supported by the operating system) from the operating system to all processes belonging to the job, then `SIGINT`, `SIGTERM` and `SIGKILL`. The interval between signals is 10 seconds by default. The time interval between `SIGXCPU`, `SIGINT`, `SIGKILL`, `SIGTERM` can be configured with the parameter `JOB_TERMINATE_INTERVAL` in `l sb. params`.

#### Restriction:

`SIGXCPU` is not supported by Windows.

- **OS-enforced per process limit:** When one process in the job exceeds the CPU limit, the limit is enforced by the operating system. For more details, refer to your operating system documentation for `setrlimit()`.

The setting of `LSB_JOB_CPULIMIT` has the following effect on how the limit is enforced:

| When <code>LSB_JOB_CPULIMIT</code> is | LSF-enforced per-job limit | OS-enforced per-process limit |
|---------------------------------------|----------------------------|-------------------------------|
| y                                     | Enabled                    | Disabled                      |
| n                                     | Disabled                   | Enabled                       |
| Not defined                           | Enabled                    | Enabled                       |

## Default

Not defined

## Notes

To make `LSB_JOB_CPULIMIT` take effect, use the command `badmi n hrestart all` to restart all `sbatchds` in the cluster.

Changing the default Terminate job control action: You can define a different terminate action in `lsb.queues` with the parameter `JOB_CONTROLS` if you do not want the job to be killed. For more details on job controls, see *Administering Platform LSF*.

## Limitations

If a job is running and the parameter is changed, LSF is not able to reset the type of limit enforcement for running jobs.

- If the parameter is changed from per-process limit enforced by the OS to per-job limit enforced by LSF (`LSB_JOB_CPULIMIT=n` changed to `LSB_JOB_CPULIMIT=y`), both per-process limit and per-job limit affect the running job. This means that signals may be sent to the job either when an individual process exceeds the CPU limit or the sum of the CPU time of all processes of the job exceed the limit. A job that is running may be killed by the OS or by LSF.
- If the parameter is changed from per-job limit enforced by LSF to per-process limit enforced by the OS (`LSB_JOB_CPULIMIT=y` changed to `LSB_JOB_CPULIMIT=n`), the job is allowed to run without limits because the per-process limit was previously disabled.

## See also

`lsb.queues`, `bsub`, `JOB_TERMINATE_INTERVAL` in `lsb.params`, `LSB_MOD_ALL_JOBS`

## LSB\_JOB\_MEMLIMIT

### Syntax

`LSB_JOB_MEMLIMIT=y | n`

### Description

Determines whether the memory limit is a per-process limit enforced by the OS or whether it is a per-job limit enforced by LSF.

- The per-process limit is enforced by the OS when the memory allocated to one process of the job exceeds the memory limit.
- The per-job limit is enforced by LSF when the sum of the memory allocated to all processes of the job exceeds the memory limit.

This parameter applies to memory limits set when a job is submitted with `bsub -M mem_limit`, and to memory limits set for queues with `MEMLIMIT` in `lsb.queues`.

The setting of `LSB_JOB_MEMLIMIT` has the following effect on how the limit is enforced:

| When <code>LSB_JOB_MEMLIMIT</code> is | LSF-enforced per-job limit | OS-enforced per-process limit |
|---------------------------------------|----------------------------|-------------------------------|
| y                                     | Enabled                    | Disabled                      |
| n or not defined                      | Disabled                   | Enabled                       |

When `LSB_JOB_MEMLIMIT` is Y, the LSF-enforced per-job limit is enabled, and the OS-enforced per-process limit is disabled.

When `LSB_JOB_MEMLIMIT` is N or not defined, the LSF-enforced per-job limit is disabled, and the OS-enforced per-process limit is enabled.

*LSF-enforced per-job limit:* When the total memory allocated to all processes in the job exceeds the memory limit, LSF sends the following signals to kill the job: SIGINT, SIGTERM, then SIGKILL. The interval between signals is 10 seconds by default.

On UNIX, the time interval between SIGINT, SIGKILL, SIGTERM can be configured with the parameter `JOB_TERMINATE_INTERVAL` in `lsb.params`.

*OS-enforced per process limit:* When the memory allocated to one process of the job exceeds the memory limit, the operating system enforces the limit. LSF passes the memory limit to the operating system. Some operating systems apply the memory limit to each process, and some do not enforce the memory limit at all.

OS memory limit enforcement is only available on systems that support `RLIMIT_RSS` for `setrlimit()`.

The following operating systems do not support the memory limit at the OS level and the job is allowed to run without a memory limit:

- Windows
- Sun Solaris 2.x

## Default

Not defined. Per-process memory limit enforced by the OS; per-job memory limit enforced by LSF disabled

## Notes

To make `LSB_JOB_MEMLIMIT` take effect, use the command `badm in hrestart al l` to restart all `sbatchds` in the cluster.

If `LSB_JOB_MEMLIMIT` is set, it overrides the setting of the parameter `LSB_MEMLIMIT_ENFORCE`. The parameter `LSB_MEMLIMIT_ENFORCE` is ignored.

The difference between `LSB_JOB_MEMLIMIT` set to `y` and `LSB_MEMLIMIT_ENFORCE` set to `y` is that with `LSB_JOB_MEMLIMIT`, only the per-job memory limit enforced by LSF is enabled. The per-process memory limit enforced by the OS is disabled. With `LSB_MEMLIMIT_ENFORCE` set to `y`, both the per-job memory limit enforced by LSF and the per-process memory limit enforced by the OS are enabled.

Changing the default Terminate job control action: You can define a different Terminate action in `lsb.queues` with the parameter `JOB_CONTROLS` if you do not want the job to be killed. For more details on job controls, see *Administering Platform LSF*.

## Limitations

If a job is running and the parameter is changed, LSF is not able to reset the type of limit enforcement for running jobs.

- If the parameter is changed from per-process limit enforced by the OS to per-job limit enforced by LSF (`LSB_JOB_MEMLIMIT=n` or not defined changed to `LSB_JOB_MEMLIMIT=y`), both per-process limit and per-job limit affect the running job. This means that signals may be sent to the job either when the memory allocated to an individual process exceeds the memory limit or the sum of memory allocated to all processes of the job exceed the limit. A job that is running may be killed by LSF.
- If the parameter is changed from per-job limit enforced by LSF to per-process limit enforced by the OS (`LSB_JOB_MEMLIMIT=y` changed to `LSB_JOB_MEMLIMIT=n` or

not defined), the job is allowed to run without limits because the per-process limit was previously disabled.

## See also

LSB\_MEMLIMIT\_ENFORCE, LSB\_MOD\_ALL\_JOBS, lsb.queues, bsub, JOB\_TERMINATE\_INTERVAL in lsb.params

## LSB\_KEEP\_SYSDEF\_RLIMIT

### Syntax

`LSB_KEEP_SYSDEF_RLIMIT=y | n`

### Description

If resource limits are configured for a user in the SGI IRIX User Limits Database (ULDB) domain specified in LSF\_ULDB\_DOMAIN, and there is no domain default, the system default is honored.

If `LSB_KEEP_SYSDEF_RLIMIT=n`, and no resource limits are configured in the domain for the user and there is no domain default, LSF overrides the system default and sets system limits to unlimited.

### Default

Not defined. No resource limits are configured in the domain for the user and there is no domain default.

## LSB\_LOAD\_TO\_SERVER\_HOSTS (OBSOLETE)

### Syntax

`LSB_LOAD_TO_SERVER_HOSTS=Y | y`

### Description

---

#### Note:

This parameter is obsolete in LSF 7 Update 2. By default, client sbatchd contacts the local LIM for host status and load information.

---

Highly recommended for large clusters to decrease the load on the master LIM. Forces the client sbatchd to contact the local LIM for host status and load information. The client sbatchd only contacts the master LIM or a LIM on one of the LSF\_SERVER\_HOSTS if sbatchd cannot find the information locally.

### Default

Y. Client sbatchd contacts the local LIM for host status and load information.

## See also

LSF\_SERVER\_HOSTS in slave.config

## LSB\_LOCALDIR

### Syntax

**LSB\_LOCALDIR**=*path*

### Description

Enables duplicate logging.

Specify the path to a local directory that exists only on the first LSF master host. LSF puts the primary copies of the event and accounting log files in this directory. LSF puts the duplicates in LSB\_SHAREDIR.

---

#### Important:

Always restart both the mbacthd and sbatchd when modifying LSB\_LOCALDIR.

---

### Example

```
LSB_LOCALDIR=/usr/share/l sbatchd/ loginfo
```

### Default

Not defined

### See also

LSB\_SHAREDIR, EVENT\_UPDATE\_INTERVAL in lsb.params

## LSB\_MAILPROG

### Syntax

**LSB\_MAILPROG**=*file\_name*

### Description

Path and file name of the mail program used by LSF to send email. This is the electronic mail program that LSF uses to send system messages to the user. When LSF needs to send email to users it invokes the program defined by LSB\_MAILPROG in `lsf.conf`. You can write your own custom mail program and set LSB\_MAILPROG to the path where this program is stored.

LSF administrators can set the parameter as part of cluster reconfiguration. Provide the name of any mail program. For your convenience, LSF provides the `sendmail` mail program, which supports the `sendmail` protocol on UNIX.

In a mixed cluster, you can specify different programs for Windows and UNIX. You can set this parameter during installation on Windows. For your convenience, LSF provides the `lsmail.exe` mail program, which supports SMTP and Microsoft Exchange Server protocols on Windows. If `lsmail` is specified, the parameter LSB\_MAILSERVER must also be specified.

If you change your mail program, the LSF administrator must restart sbatchd on all hosts to retrieve the new value.

## UNIX

By default, LSF uses `/usr/lib/sendmail` to send email to users. LSF calls `LSB_MAILPROG` with two arguments; one argument gives the full name of the sender, and the other argument gives the return address for mail.

`LSB_MAILPROG` must read the body of the mail message from the standard input. The end of the message is marked by end-of-file. Any program or shell script that accepts the arguments and input, and delivers the mail correctly, can be used.

`LSB_MAILPROG` must be executable by any user.

## Windows

If `LSB_MAILPROG` is not defined, no email is sent.

## Examples

```
LSB_MAILPROG=lsmail.exe
```

```
LSB_MAILPROG=/serverA/tools/lsf/bin/unixhost.exe
```

## Default

`/usr/lib/sendmail` (UNIX)

blank (Windows)

## See also

`LSB_MAILSERVER`, `LSB_MAILTO`

## LSB\_MAILSERVER

### Syntax

```
LSB_MAILSERVER=mail_protocol:mail_server
```

### Description

Part of mail configuration on Windows.

This parameter only applies when `lsmail` is used as the mail program (`LSB_MAILPROG=lsmail.exe`). Otherwise, it is ignored.

Both *mail\_protocol* and *mail\_server* must be indicated.

Set this parameter to either SMTP or Microsoft Exchange protocol (SMTP or EXCHANGE) and specify the name of the host that is the mail server.

This parameter is set during installation of LSF on Windows or is set or modified by the LSF administrator.

If this parameter is modified, the LSF administrator must restart `sbatchd` on all hosts to retrieve the new value.

## Examples

```
LSB_MAILSERVER=EXCHANGE: Host2@company.com
```

```
LSB_MAILSERVER=SMTP: MailHost
```

## Default

Not defined

## See also

LSB\_LOCALDIR

## LSB\_MAILSIZELIMIT

## Syntax

**LSB\_MAILSIZELIMIT**=*email\_size\_KB*

## Description

Limits the size in KB of the email containing job output information.

The system sends job information such as CPU, process and memory usage, job output, and errors in email to the submitting user account. Some batch jobs can create large amounts of output. To prevent large job output files from interfering with your mail system, use LSB\_MAILSIZELIMIT to set the maximum size in KB of the email containing the job information. Specify a positive integer.

If the size of the job output email exceeds LSB\_MAILSIZELIMIT, the output is saved to a file under JOB\_SPOOL\_DIR or to the default job output directory if JOB\_SPOOL\_DIR is not defined. The email informs users of where the job output is located.

If the -o option of bsub is used, the size of the job output is not checked against LSB\_MAILSIZELIMIT.

If you use a custom mail program specified by the LSB\_MAILPROG parameter that can use the LSB\_MAILSIZELIMIT environment variable, it is not necessary to configure LSB\_MAILSIZELIMIT.

## Default

By default, LSB\_MAILSIZELIMIT is not enabled. No limit is set on size of batch job output email.

## See also

LSB\_MAILPROG, LSB\_MAILTO

## LSB\_MAILTO

## Syntax

**LSB\_MAILTO**=*mail\_account*

## Description

LSF sends electronic mail to users when their jobs complete or have errors, and to the LSF administrator in the case of critical errors in the LSF system. The default is to send mail to the user who submitted the job, on the host on which the daemon is running; this assumes that your electronic mail system forwards messages to a central mailbox.

The `LSB_MAILTO` parameter changes the mailing address used by LSF. `LSB_MAILTO` is a format string that is used to build the mailing address.

Common formats are:

- `!U`: Mail is sent to the submitting user's account name on the local host. The substring `!U`, if found, is replaced with the user's account name.
- `!U@company_name.com`: Mail is sent to `user@company_name.com` on the mail server. The mail server is specified by `LSB_MAILSERVER`.
- `!U!H`: Mail is sent to `user@submission_hostname`. The substring `!H` is replaced with the name of the submission host. This format is valid on UNIX only. It is not supported on Windows.

All other characters (including any other '!') are copied exactly.

If this parameter is modified, the LSF administrator must restart `sbatchd` on all hosts to retrieve the new value.

Windows only: When a job exception occurs (for example, a job is overrun or underrun), an email is sent to the primary administrator set in the `lsf.cluster.cluster_name` file to the domain set in `LSB_MAILTO`. For example, if the primary administrator is `lsfadmin` and `LSB_MAILTO=fred@company.com`, an email is sent to `lsfadmin@company.com`. The email must be a valid Windows email account.

## Default

`!U`

## See also

`LSB_MAILPROG`, `LSB_MAILSIZE_LIMIT`

## LSB\_MAX\_ASKED\_HOSTS\_NUMBER

### Syntax

`LSB_MAX_ASKED_HOSTS_NUMBER=integer`

### Description

Limits the number of hosts a user can specify with the `-m` (host preference) option of the following commands:

- `bsub`
- `brun`
- `bmod`
- `brestart`
- `brsvadd`
- `brsvmod`
- `brsvs`

The job is rejected if more hosts are specified than the value of `LSB_MAX_ASKED_HOSTS_NUMBER`.

---

**Caution:**

If this value is set high, there will be a performance effect if users submit or modify jobs using the -m option and specify a large number of hosts. 512 hosts is the suggested upper limit.

---

## Valid values

Any whole, positive integer.

## Default

512

## LSB\_MAX\_JOB\_DISPATCH\_PER\_SESSION

### Syntax

**LSB\_MAX\_JOB\_DISPATCH\_PER\_SESSION**=*integer*

### Description

Defines the maximum number of jobs that mbatchd can dispatch during one job scheduling session.

Both mbatchd and sbatchd must be restarted when you change the value of this parameter.

If set to a value greater than 300, the file descriptor limit is increased on operating systems that support a file descriptor limit greater than 1024.

Use together with MAX\_SBD\_CONNS in lsb.params. Set LSB\_MAX\_JOB\_DISPATCH\_PER\_SESSION to a value no greater than one-half the value of MAX\_SBD\_CONNS. This setting configures mbatchd to dispatch jobs at a high rate while maintaining the processing speed of other mbatchd tasks.

### Examples

```
LSB_MAX_JOB_DISPATCH_PER_SESSION=300
```

The file descriptor limit is 1024.

```
LSB_MAX_JOB_DISPATCH_PER_SESSION=1000
```

The file descriptor limit is greater than 1024 on operating systems that support a greater limit.

### Default

300

### See also

MAX\_SBD\_CONNS in lsb.params

## LSB\_MAX\_PROBE\_SBD

### Syntax

**LSB\_MAX\_PROBE\_SBD**=*integer*

## Description

Specifies the maximum number of sbatchd instances can be polled by mbatchd in the interval `MBD_SLEEP_TIME/10` (6 seconds by default). Use this parameter in large clusters to reduce the time it takes for mbatchd to probe all sbatchds.

The value of `LSB_MAX_PROBE_SBD` cannot be greater than the number of hosts in the cluster. If it is, mbatchd adjusts the value of `LSB_MAX_PROBE_SBD` to be same as the number of hosts.

After modifying `LSB_MAX_PROBE_SBD`, use `badmi n mbdrestart` to restart mbatchd and let the modified value take effect.

If `LSB_MAX_PROBE_SBD` is defined, the value of `MAX_SBD_FAIL` in `lsb.params` can be less than 3.

## Valid values

Any positive integer between 0 and 64

## Default

20

## See also

`MAX_SBD_FAIL` in `lsb.params`

## LSB\_MAX\_NQS\_QUEUES

## Syntax

**LSB\_MAX\_NQS\_QUEUES**=*nqs\_queues*

## Description

The maximum number of NQS queues allowed in the LSF cluster. Required for LSF to work with NQS. You must restart mbatchd if you change the value of `LSB_MAX_NQS_QUEUES`.

The total number of NQS queues configured by `NQS_QUEUES` in `lsb_queues` cannot exceed the value of `LSB_MAX_NQS_QUEUES`. NQS queues in excess of the maximum queues are ignored.

If you do not define `LSB_MAX_NQS_QUEUES` or define an incorrect value, LSF-NQS interoperation is disabled.

## Valid values

Any positive integer

## Default

None

## LSB\_MBD\_BUSY\_MSG

### Syntax

**LSB\_MBD\_BUSY\_MSG**="*message\_string*"

### Description

Specifies the message displayed when mbatchd is too busy to accept new connections or respond to client requests.

Define this parameter if you want to customize the message.

### Valid values

String, either non-empty or empty.

### Default

Not defined. By default, LSF displays the message "LSF is processing your request. Please wait. . . "

Batch commands retry the connection to mbatchd at the intervals specified by the parameters LSB\_API\_CONNTIMEOUT and LSB\_API\_RECVTIMEOUT.

## LSB\_MBD\_CONNECT\_FAIL\_MSG

### Syntax

**LSB\_MBD\_CONNECT\_FAIL\_MSG**="*message\_string*"

### Description

Specifies the message displayed when internal system connections to mbatchd fail.

Define this parameter if you want to customize the message.

### Valid values

String, either non-empty or empty.

### Default

Not defined. By default, LSF displays the message "Cannot connect to LSF. Please wait. . . "

Batch commands retry the connection to mbatchd at the intervals specified by the parameters LSB\_API\_CONNTIMEOUT and LSB\_API\_RECVTIMEOUT.

## LSB\_MBD\_DOWN\_MSG

### Syntax

**LSB\_MBD\_DOWN\_MSG**="*message\_string*"

## Description

Specifies the message displayed by the `bhost s` command when `mbatchd` is down or there is no process listening at either the `LSB_MBD_PORT` or the `LSB_QUERY_PORT`.

Define this parameter if you want to customize the message.

## Valid values

String, either non-empty or empty.

## Default

Not defined. By default, LSF displays the message "LSF is down. Please wait..."

Batch commands retry the connection to `mbatchd` at the intervals specified by the parameters `LSB_API_CONNTIMEOUT` and `LSB_API_RECVTIMEOUT`.

## LSB\_MBD\_MAX\_SIG\_COUNT

### Syntax

`LSB_MBD_MAX_SIG_COUNT=integer`

### Description

When a host enters an unknown state, the `mbatchd` attempts to retry any pending jobs. This parameter specifies the maximum number of pending signals that the `mbatchd` deals with concurrently in order not to overload it. A high value for `LSB_MBD_MAX_SIG_COUNT` can negatively impact the performance of your cluster.

### Valid Valid values

Integers between 5-100, inclusive.

### Default

5

## LSB\_MBD\_PORT

See `LSF_LIM_PORT`, `LSF_RES_PORT`, `LSB_MBD_PORT`, `LSB_SBD_PORT`.

## LSB\_MC\_CHKPNT\_RERUN

### Syntax

`LSB_MC_CHKPNT_RERUN=y | n`

### Description

For checkpointable MultiCluster jobs, if a restart attempt fails, the job is rerun from the beginning (instead of from the last checkpoint) without administrator or user intervention.

The submission cluster does not need to forward the job again. The execution cluster reports the job's new pending status back to the submission cluster, and the job is dispatched to the same host to restart from the beginning

## Default

n

### LSB\_MC\_INITFAIL\_MAIL

## Syntax

LSB\_MC\_INITFAIL\_MAIL=Y | All | Administrator

## Description

MultiCluster job forwarding model only.

Specify Y to make LSF email the job owner when a job is suspended after reaching the retry threshold.

Specify **Administrator** to make LSF email the primary administrator when a job is suspended after reaching the retry threshold.

Specify All to make LSF email both the job owner and the primary administrator when a job is suspended after reaching the retry threshold.

## Default

not defined

### LSB\_MC\_INITFAIL\_RETRY

## Syntax

LSB\_MC\_INITFAIL\_RETRY=*integer*

## Description

MultiCluster job forwarding model only. Defines the retry threshold and causes LSF to suspend a job that repeatedly fails to start. For example, specify 2 retry attempts to make LSF attempt to start a job 3 times before suspending it.

## Default

5

### LSB\_MEMLIMIT\_ENFORCE

## Syntax

LSB\_MEMLIMIT\_ENFORCE=y | n

## Description

Specify y to enable LSF memory limit enforcement.

If enabled, LSF sends a signal to kill all processes that exceed queue-level memory limits set by MEMLIMIT in l sb. queues or job-level memory limits specified by bsub -M *mem\_limit*.

Otherwise, LSF passes memory limit enforcement to the OS. UNIX operating systems that support `RLIMIT_RSS` for `setrlimit()` can apply the memory limit to each process.

The following operating systems do not support memory limit at the OS level:

- Windows
- Sun Solaris 2.x

## Default

Not defined. LSF passes memory limit enforcement to the OS.

## See also

[lsb.queues](#)

## LSB\_MIG2PEND

### Syntax

**LSB\_MIG2PEND=0 | 1**

### Description

Applies only to migrating checkpointable or rerunnable jobs.

When defined with a value of 1, requeues migrating jobs instead of restarting or rerunning them on the first available host. Requeues the jobs in the PENDING state in order of the original submission time and with the original job priority.

If you want to place the migrated jobs at the bottom of the queue without considering submission time, define both `LSB_MIG2PEND=1` and `LSB_REQUEUE_TO_BOTTOM=1` in `lsf.conf`.

Ignored in a MultiCluster environment.

## Default

Not defined. LSF restarts or reruns migrating jobs on the first available host.

## See also

[LSB\\_REQUEUE\\_TO\\_BOTTOM](#)

## LSB\_MIXED\_PATH\_DELIMITER

### Syntax

**LSB\_MIXED\_PATH\_DELIMITER="|"**

### Description

Defines the delimiter between UNIX and Windows paths if `LSB_MIXED_PATH_ENABLE=y`. For example, `/home/tmp/J.out|c:\tmp\J.out`.

## Default

A pipe "|" is the default delimiter.

## See also

LSB\_MIXED\_PATH\_ENABLE

## LSB\_MIXED\_PATH\_ENABLE

### Syntax

**LSB\_MIXED\_PATH\_ENABLE=y | n**

### Description

Allows you to specify both a UNIX and Windows path when submitting a job in a mixed cluster (both Windows and UNIX hosts).

The format is always **unix\_path\_cmd|windows\_path\_cmd**.

Applies to the following options of bsub:

- -o, -oo
- -e, -eo
- -i, -is
- -cwd
- -E, -Ep
- CMD
- queue level PRE\_EXEC, POST\_EXEC
- application level PRE\_EXEC, POST\_EXEC

For example:

```
bsub -o "/home/tmp/job%J.out|c:\tmp\job%J.out" -e "/home/tmp/err%J.out|c:\tmp\err%J.out" -E "sleep 9| sleep 8" -Ep "sleep 7| sleep 6" -cwd "/home/tmp|c:\tmp" "sleep 121|sleep 122"
```

The delimiter is configurable: LSB\_MIXED\_PATH\_DELIMITER.

### Default

Not defined. LSF jobs submitted .

## See also

LSB\_MIXED\_PATH\_DELIMITER

## LSB\_MOD\_ALL\_JOBS

### Syntax

**LSB\_MOD\_ALL\_JOBS=y | Y**

### Description

If set, enables bmod to modify resource limits and location of job output files for running jobs.

After a job has been dispatched, the following modifications can be made:

- CPU limit (-c [hour:]minute[/host\_name | /host\_model] | -cn)
- Memory limit (-M mem\_limit | -Mn)

- Rerunnable jobs (-r | -rn)
- Resource requirements (-R "*res\_req*" except -R "cu[*cu\_string*"])
- Run limit (-W *run\_limit*[/*host\_name* | /*host\_model*] | -Wn)
- Standard output file name (-o *output\_file* | -on)
- Standard error file name (-e *error\_file* | -en)
- Overwrite standard output (st dout) file name up to 4094 characters for UNIX or 255 characters for Windows (-oo *output\_file*)
- Overwrite standard error (st derr) file name up to 4094 characters for UNIX or 255 characters for Windows (-eo *error\_file*)

To modify the CPU limit or the memory limit of running jobs, the parameters `LSB_JOB_CPULIMIT=Y` and `LSB_JOB_MEMLIMIT=Y` must be defined in `lsf.conf`.

---

### Important:

Always run `badmi n mbdrestart` after modifying `LSB_MOD_ALL_JOBS`.

---

## Default

Not defined

## See also

`LSB_JOB_CPULIMIT`, `LSB_JOB_MEMLIMIT`

## LSB\_NCPU\_ENFORCE

### Description

When set to 1, enables parallel fairshare and considers the number of CPUs when calculating dynamic priority for queue-level user-based fairshare. `LSB_NCPU_ENFORCE` does not apply to host-partition user-based fairshare. For host-partition user-based fairshare, the number of CPUs is automatically considered.

## Default

Not defined

## LSB\_NQS\_PORT

### Syntax

`LSB_NQS_PORT=port_number`

### Description

Required for LSF to work with NQS.

TCP service port to use for communication with NQS.

## Where defined

This parameter can alternatively be set as an environment variable or in the services database such as `/etc/services`.

## Example

```
LSB_NQS_PORT=607
```

## Default

Not defined

## LSB\_NUM\_NIOS\_CALLBACK\_THREADS

### Syntax

```
LSB_NUM_NIOS_CALLBACK_THREADS=integer
```

### Description

Specifies the number of callback threads to use for batch queries.

If your cluster runs a large amount of blocking mode (bsub -K) and interactive jobs (bsub -I), response to batch queries can become very slow. If you run large number of bsub -I or bsub -K jobs, you can define the threads to the number of processors on the master host.

## Default

Not defined

## LSB\_PSET\_BIND\_DEFAULT

### Syntax

```
LSB_PSET_BIND_DEFAULT=y | Y
```

### Description

If set, Platform LSF HPC binds a job that is not explicitly associated with an HP-UX pset to the default pset 0. If LSB\_PSET\_BIND\_DEFAULT is not set, LSF HPC must still attach the job to a pset, and so binds the job to the same pset used by the LSF HPC daemons.

Use LSB\_PSET\_BIND\_DEFAULT to improve LSF daemon performance by automatically unbinding a job with no pset options from the pset used by the LSF daemons, and binding it to the default pset.

## Default

Not defined

## LSB\_QUERY\_PORT

### Syntax

```
LSB_QUERY_PORT=port_number
```

### Description

Optional. Applies only to UNIX platforms that support thread programming.

This parameter is recommended for busy clusters with many jobs and frequent query requests to increase mbatchd performance when you use the bj obs command.

This may indirectly increase overall mbatchd performance.

The `port_number` is the TCP/IP port number to be used by mbatchd to only service query requests from the LSF system. mbatchd checks the query port during initialization.

If `LSB_QUERY_PORT` *is not* defined:

- mbatchd uses the port specified by `LSB_MBD_PORT` in `lsf.conf`, or, if `LSB_MBD_PORT` is not defined, looks into the system services database for port numbers to communicate with other hosts in the cluster.
- For each query request it receives, mbatchd forks one child mbatchd to service the request. Each child mbatchd processes one request and then exits.

If `LSB_QUERY_PORT` is defined:

- mbatchd prepares this port for connection. The default behavior of mbatchd changes, a child mbatchd is forked, and the child mbatchd creates threads to process requests.
- mbatchd responds to requests by forking one child mbatchd. As soon as mbatchd has forked a child mbatchd, the child mbatchd takes over and listens on the port to process more query requests. For each request, the child mbatchd creates a thread to process it.

The interval used by mbatchd for forking new child mbatchds is specified by the parameter `MBD_REFRESH_TIME` in `lsb.params`.

The child mbatchd continues to listen to the port number specified by `LSB_QUERY_PORT` and creates threads to service requests until the job changes status, a new job is submitted, or the time specified in `MBD_REFRESH_TIME` in `lsb.params` has passed (see `MBD_REFRESH_TIME` in `lsb.params` for more details). When any of these happens, the parent mbatchd sends a message to the child mbatchd to exit.

`LSB_QUERY_PORT` must be defined when `NEWJOB_REFRESH=Y` in `lsb.params` to enable a child mbatchd to get up to date information about new jobs from the parent mbatchd.

## Operating system support

---

### Tip:

See the Online Support area of the Platform Computing Web site at [www.platform.com](http://www.platform.com) for the latest information about operating systems that support multithreaded mbatchd.

---

## Default

Not defined

## See also

`MBD_REFRESH_TIME` and `NEWJOB_REFRESH` in `lsb.params`

## LSB\_QUEUE\_TO\_BOTTOM

### Syntax

`LSB_QUEUE_TO_BOTTOM=0 | 1`

## Description

When defined with a value of 1, requeues automatically requeued jobs to the bottom of the queue instead of to the top. Also requeues migrating jobs to the bottom of the queue if `LSB_MIG2PEND` is also defined with a value of 1.

Ignored in a MultiCluster environment.

## Default

Not defined. LSF requeues jobs in order of original submission time and job priority.

## See also

`LSB_MIG2PEND`, `REQUEUE_EXIT_VALUES` in `lsb.queues`

## LSB\_RLA\_HOST\_LIST

### Syntax

```
LSB_RLA_HOST_LIST="host_name ..."
```

## Description

By default, the LSF scheduler can contact the LSF HPC topology adapter (RLA) running on any host for Linux/QsNet RMS allocation requests. `LSB_RLA_HOST_LIST` defines a list of hosts to restrict which RLAs the LSF scheduler contacts.

If `LSB_RLA_HOST_LIST` is configured, you must list at least one host per RMS partition for the RMS partition to be considered for job scheduling.

Listed hosts must be defined in `lsf.cluster.cluster_name`.

Host names are separated by spaces.

## Default

Not defined

## LSB\_RLA\_PORT

### Syntax

```
LSB_RLA_PORT=port_number
```

## Description

TCP port used for communication between the LSF HPC topology adapter (RLA) and the LSF HPC scheduler plugin.

## Default

6883

## LSB\_RLA\_UPDATE

### Syntax

**LSB\_RLA\_UPDATE**=*time\_seconds*

### Description

Specifies how often the LSF HPC scheduler refreshes free node information from the LSF HPC topology adapter (RLA).

### Default

600 seconds

## LSB\_RLA\_WORKDIR

### Syntax

**LSB\_RLA\_WORKDIR**=*directory*

### Description

Directory to store the LSF HPC topology adapter (RLA) status file. Allows RLA to recover its original state when it restarts. When RLA first starts, it creates the directory defined by LSB\_RLA\_WORKDIR if it does not exist, then creates subdirectories for each host.

You should avoid using /tmp or any other directory that is automatically cleaned up by the system. Unless your installation has restrictions on the LSB\_SHAREDIR directory, you should use the default for LSB\_RLA\_WORKDIR.

### Default

LSB\_SHAREDIR/*cluster\_name*/rla\_workdir

## LSB\_RMSACCT\_DELAY

### Syntax

**LSB\_RMSACCT\_DELAY**=*time\_seconds*

### Description

If set, RES waits the specified number of seconds before exiting to allow LSF and RMS job statistics to synchronize.

If LSB\_RMSACCT\_DELAY=0, RES waits forever until the database is up to date.

### Default

Not defined. RES does not wait at all.

## LSB\_RMS\_MAXNUMNODES

### Syntax

**LSB\_RMS\_MAXNUMNODES**=*integer*

## Description

Maximum number of nodes in a system. Specifies a maximum value for the `nodes` argument to the topology scheduler options specified in:

- `-extsched` option of `bsub`
- `DEFAULT_EXTSCHEDED` and `MANDATORY_EXTSCHEDED` in `l sb. queues`

## Default

1024

## LSB\_RMS\_MAXNUMRAILS

## Syntax

**LSB\_RMS\_MAXNUMRAILS**=*integer*

## Description

Maximum number of rails in a system. Specifies a maximum value for the `rails` argument to the topology scheduler options specified in:

- `-extsched` option of `bsub`
- `DEFAULT_EXTSCHEDED` and `MANDATORY_EXTSCHEDED` in `l sb. queues`

## Default

32

## LSB\_RMS\_MAXPTILE

## Syntax

**LSB\_RMS\_MAXPTILE**=*integer*

## Description

Maximum number of CPUs per node in a system. Specifies a maximum value for the `ptile` argument to the topology scheduler options specified in:

- `-extsched` option of `bsub`
- `DEFAULT_EXTSCHEDED` and `MANDATORY_EXTSCHEDED` in `l sb. queues`

## Default

32

## LSB\_SLURM\_BESTFIT

## Syntax

**LSB\_SLURM\_BESTFIT**=*y | Y*

## Description

Enables best-fit node allocation for SLURM jobs.

By default, LSF applies a *first-fit* allocation policy to select from the nodes available for the job. The allocations are made left to right for all parallel jobs, and right to left for all serial jobs (all other job requirements being equal).

In a heterogeneous SLURM cluster, a *best-fit* allocation may be preferable for clusters where a mix of serial and parallel jobs run. In this context, best fit means: "the nodes that minimally satisfy the requirements." Nodes with the maximum number of CPUs are chosen first. For parallel and serial jobs, the nodes with minimal memory, minimal tmp space, and minimal weight are chosen.

## Default

Not defined

## LSB\_SBD\_PORT

See LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT.

## LSB\_SET\_TMPDIR

### Syntax

**LSB\_SET\_TMPDIR=y | n**

If y, LSF sets the TMPDIR environment variable, overwriting the current value with `/tmp/job_ID.tmpdir`.

## Default

n

## LSB\_SHAREDIR

### Syntax

**LSB\_SHAREDIR=directory**

## Description

Directory in which the job history and accounting logs are kept for each cluster. These files are necessary for correct operation of the system. Like the organization under LSB\_CONFDIR, there is one subdirectory for each cluster.

The LSB\_SHAREDIR directory must be owned by the LSF administrator. It must be accessible from all hosts that can potentially become the master host, and must allow read and write access from the master host.

The LSB\_SHAREDIR directory typically resides on a reliable file server.

## Default

LSF\_INDEP/work

## See also

LSB\_LOCALDIR

## LSB\_SHORT\_HOSTLIST

### Syntax

```
LSB_SHORT_HOSTLIST=1
```

### Description

Displays an abbreviated list of hosts in `bj obs` and `bhi st` for a parallel job where multiple processes of a job are running on a host. Multiple processes are displayed in the following format:

```
processes*hostA
```

For example, if a parallel job is running 5 processes on host A, the information is displayed in the following manner:

```
5*hostA
```

Setting this parameter may improve `mbatchd` restart performance and accelerate event replay.

### Default

Not defined

## LSB\_SIGSTOP

### Syntax

```
LSB_SIGSTOP=signal_name | signal_value
```

### Description

Specifies the signal sent by the SUSPEND action in LSF. You can specify a signal name or a number.

If `LSB_SIGSTOP` is set to anything other than `SIGSTOP`, the `SIGTSTP` signal that is normally sent by the SUSPEND action is not sent.

If this parameter is not defined, by default the SUSPEND action in LSF sends the following signals to a job:

- Parallel or interactive jobs: 1. `SIGTSTP` is sent first to allow user programs to catch the signal and clean up. 2. `SIGSTOP` is sent 10 seconds after `SIGTSTP`. `SIGSTOP` cannot be caught by user programs.
- Other jobs: `SIGSTOP` is sent. `SIGSTOP` cannot be caught by user programs. The same set of signals is not supported on all UNIX systems. To display a list of the symbolic names of the signals (without the `SIG` prefix) supported on your system, use the `kill -l` command.

### Example

```
LSB_SIGSTOP=SIGKILL
```

In this example, the SUSPEND action sends the three default signals sent by the TERMINATE action (`SIGINT`, `SIGTERM`, and `SIGKILL`) 10 seconds apart.

### Default

Not defined. Default SUSPEND action in LSF is sent.

## LSB\_STDOUT\_DIRECT

### Syntax

**LSB\_STDOUT\_DIRECT=y | Y**

### Description

When set, and used with the `-o` or `-e` options of `bsub`, redirects standard output or standard error from the job directly to a file as the job runs.

If `LSB_STDOUT_DIRECT` is not set and you use the `bsub -o` option, the standard output of a job is written to a temporary file and copied to the file you specify *after* the job finishes.

`LSB_STDOUT_DIRECT` is not supported on Windows.

### Default

Not defined

## LSB\_STOP\_IGNORE\_IT

### Usage

**LSB\_STOP\_IGNORE\_IT= Y | y**

### Description

Allows a solitary job to be stopped regardless of the idle time (IT) of the host that the job is running on. By default, if only one job is running on a host, the host idle time must be zero in order to stop the job.

### Default

Not defined

## LSB\_SUB\_COMMANDNAME

### Syntax

**LSB\_SUB\_COMMANDNAME=y | Y**

### Description

If set, enables `esub` to use the variable `LSB_SUB_COMMAND_LINE` in the `esub` job parameter file specified by the `$LSB_SUB_PARM_FILE` environment variable.

The `LSB_SUB_COMMAND_LINE` variable carries the value of the `bsub` command argument, and is used when `esub` runs.

### Example

`esub` contains:

```
#!/bin/sh . $LSB_SUB_PARM_FILE exec 1>&2 if
[ $LSB_SUB_COMMAND_LINE="netscape" ]; then echo "netscape is not allowed to
run in batch mode" exit $LSB_SUB_ABORT_VALUE fi
```

LSB\_SUB\_COMMAND\_LINE is defined in \$LSB\_SUB\_PARM\_FILE as:

```
LSB_SUB_COMMAND_LINE=netscape
```

A job submitted with:

```
bsub netscape . . .
```

Causes esub to echo the message:

```
netscape is not allowed to run in batch mode
```

## Default

Not defined

## See also

LSB\_SUB\_COMMAND\_LINE and LSB\_SUB\_PARM\_FILE environment variables

## LSB\_TIME\_CMD

### Syntax

```
LSB_TIME_CMD=timing_level
```

### Description

The timing level for checking how long batch commands run.

Time usage is logged in milliseconds; specify a positive integer.

Example: LSB\_TIME\_CMD=1

## Default

Not defined

## See also

LSB\_TIME\_MBD, LSB\_TIME\_SBD, LSF\_TIME\_LIM, LSF\_TIME\_RES

## LSB\_TIME\_MBD

### Syntax

```
LSB_TIME_MBD=timing_level
```

### Description

The timing level for checking how long mbatchd routines run.

Time usage is logged in milliseconds; specify a positive integer.

Example: LSB\_TIME\_MBD=1

## Default

Not defined

## See also

LSB\_TIME\_CMD, LSB\_TIME\_SBD, LSF\_TIME\_LIM, LSF\_TIME\_RES

## LSB\_TIME\_RESERVE\_NUMJOBS

### Syntax

**LSB\_TIME\_RESERVE\_NUMJOBS**=*maximum\_reservation\_jobs*

### Description

Enables time-based slot reservation. The value must be positive integer.

LSB\_TIME\_RESERVE\_NUMJOBS controls maximum number of jobs using time-based slot reservation. For example, if LSB\_TIME\_RESERVE\_NUMJOBS=4, only the top 4 jobs get their future allocation information.

Use LSB\_TIME\_RESERVE\_NUMJOBS=1 to allow only the highest priority job to get accurate start time prediction.

### Recommended value

3 or 4 is the recommended setting. Larger values are not as useful because after the first pending job starts, the estimated start time of remaining jobs may be changed.

### Default

Not defined

## LSB\_TIME\_SBD

### Syntax

**LSB\_TIME\_SBD**=*timing\_level*

### Description

The timing level for checking how long sbatchd routines run.

Time usage is logged in milliseconds; specify a positive integer.

Example: LSB\_TIME\_SBD=1

### Default

Not defined

## See also

LSB\_TIME\_CMD, LSB\_TIME\_MBD, LSF\_TIME\_LIM, LSF\_TIME\_RES

## LSB\_TIME\_SCH

### Syntax

**LSB\_TIME\_SCH**=*timing\_level*

## Description

The timing level for checking how long mbschd routines run.  
Time usage is logged in milliseconds; specify a positive integer.  
Example: LSB\_TIME\_SCH=1

## Default

Not defined

## LSB\_UTMP

## Syntax

**LSB\_UTMP=y | Y**

## Description

If set, enables registration of user and account information for interactive batch jobs submitted with `bsub -I p` or `bsub -I s`. To disable utmp file registration, set LSB\_UTMP to any value other than y or Y; for example, LSB\_UTMP=N.

LSF registers interactive batch jobs the job by adding a entries to the utmp file on the execution host when the job starts. After the job finishes, LSF removes the entries for the job from the utmp file.

## Limitations

Registration of utmp file entries is supported on the following platforms:

- SGI IRIX (6.4 and later)
- Solaris (all versions)
- HP-UX (all versions)
- Linux (all versions)

utmp file registration is not supported in a MultiCluster environment.

Because interactive batch jobs submitted with `bsub -I` are not associated with a pseudo-terminal, utmp file registration is not supported for these jobs.

## Default

Not defined

## LSF\_AFS\_CELLNAME

## Syntax

**LSF\_AFS\_CELLNAME=*AFS\_cell\_name***

## Description

Must be defined to AFS cell name if the AFS file system is in use.

Example:

LSF\_AFS\_CELLNAME=cern.ch

## Default

Not defined

## LSF\_AM\_OPTIONS

### Syntax

**LSF\_AM\_OPTIONS=AMFIRST | AMNEVER**

### Description

Determines the order of file path resolution when setting the user's home directory.

This variable is rarely used but sometimes LSF does not properly change the directory to the user's home directory when the user's home directory is automounted. Setting LSF\_AM\_OPTIONS forces LSF to change directory to \$HOME before attempting to automount the user's home.

When this parameter is not defined or set to AMFIRST, LSF, sets the user's \$HOME directory from the automount path. If it cannot do so, LSF sets the user's \$HOME directory from the passwd file.

When this parameter is set to AMNEVER, LSF, never uses automount to set the path to the user's home. LSF sets the user's \$HOME directory directly from the passwd file.

### Valid values

The two values are AMFIRST and AMNEVER

## Default

Same as AMFIRST

## LSF\_API\_CONNTIMEOUT

### Syntax

**LSF\_API\_CONNTIMEOUT=*time\_seconds***

### Description

Timeout when connecting to LIM.

### EGO parameter

EGO\_LIM\_CONNTIMEOUT

## Default

5

### See also

LSF\_API\_RECVTIMEOUT

## LSF\_API\_RECVMTIMEOUT

### Syntax

`LSF_API_RECVMTIMEOUT=time_seconds`

### Description

Timeout when receiving a reply from LIM.

### EGO parameter

EGO\_LIM\_RECVMTIMEOUT

### Default

20

### See also

LSF\_API\_CONNTIMEOUT

## LSF\_AUTH

### Syntax

`LSF_AUTH=eauth | ident`

### Description

Enables either external authentication or authentication by means of identification daemons. This parameter is required for any cluster that contains Windows hosts, and is optional for UNIX-only clusters. After defining or changing the value of LSF\_AUTH, you must shut down and restart the LSF daemons on all server hosts to apply the new authentication method.

#### **eauth**

For site-specific customized external authentication. Provides the highest level of security of all LSF authentication methods.

#### **ident**

For authentication using the RFC 931/1413/1414 protocol to verify the identity of the remote client. If you want to use ident authentication, you must download and install the ident protocol, available from the public domain, and register ident as required by your operating system.

For UNIX-only clusters, privileged ports authentication (setuid) can be configured by commenting out or deleting the LSF\_AUTH parameter. If you choose privileged ports authentication, LSF commands must be installed as setuid programs owned by root. If the commands are installed in an NFS-mounted shared file system, the file system must be mounted with setuid execution allowed, that is, without the nosuid option.

---

#### **Restriction:**

To enable privileged ports authentication, LSF\_AUTH must not be defined; setuid is not a valid value for LSF\_AUTH.

---

## Default

### eauth

During LSF installation, a default eauth executable is installed in the directory specified by the parameter `LSF_SERVERDIR` in the `lsf.conf` file. The default executable provides an example of how the eauth protocol works. You should write your own eauth executable to meet the security requirements of your cluster.

## LSF\_ASPLUGIN

### Syntax

**LSF\_ASPLUGIN=***path*

### Description

Points to the SGI Array Services library `libarray.so`. The parameter only takes effect on 64-bit x-86 Linux 2.6, glibc 2.3.

### Default

`/usr/lib64/libarray.so`

## LSF\_AUTH\_DAEMONS

### Syntax

**LSF\_AUTH\_DAEMONS=***y | Y*

### Description

Enables LSF daemon authentication when external authentication is enabled (`LSF_AUTH=eauth` in the file `lsf.conf`). Daemons invoke `eauth` to authenticate each other as specified by the `eauth` executable.

### Default

Not defined.

## LSF\_BINDIR

### Syntax

**LSF\_BINDIR=***directory*

### Description

Directory in which all LSF user commands are installed.

### Default

`LSF_MACHDEP/bin`

## LSF\_BIND\_JOB

### Syntax

**LSF\_BIND\_JOB=**`NONE | BALANCE | PACK | ANY | USER | USER_CPU_LIST`

## Description

Specifies the processor binding policy for sequential and parallel job processes that run on a single host.

On Linux execution hosts that support this feature, job processes are hard bound to selected processors.

If processor binding feature is not configured with the BIND\_JOB parameter in an application profile in `lsb. applications`, the `lsf.conf` configuration setting takes effect. The application profile configuration for processor binding overrides the `lsf.conf` configuration.

For backwards compatibility:

- LSF\_BIND\_JOB=Y is interpreted as LSF\_BIND\_JOB=BALANCE
- LSF\_BIND\_JOB=N is interpreted as LSF\_BIND\_JOB=NONE

## Supported platforms

Linux with kernel version 2.6 or higher

## Default

Not defined. Processor binding is disabled.

## LSF\_BMPLUGIN

### Syntax

**LSF\_BMPLUGIN**=*path*

### Description

Points to the bitmask library `libbitmask.so`. The parameter only takes effect on 64-bit x-86 Linux 2.6, glibc 2.3.

### Default

`/usr/lib64/libbitmask.so`

## LSF\_CMD\_LOGDIR

### Syntax

**LSF\_CMD\_LOGDIR**=*path*

### Description

The path to the log files used for debugging LSF commands.

This parameter can also be set from the command line.

### Default

`/tmp`

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD,  
LSB\_TIME\_CMD, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR,  
LSF\_TIME\_CMD

## LSF\_CMD\_LOG\_MASK

### Syntax

```
LSF_CMD_LOG_MASK=log_level
```

### Description

Specifies the logging level of error messages from LSF commands.

For example:

```
LSF_CMD_LOG_MASK=LOG_DEBUG
```

To specify the logging level of error messages, use `LSB_CMD_LOG_MASK`. To specify the logging level of error messages for LSF daemons, use `LSF_LOG_MASK`.

LSF commands log error messages in different levels so that you can choose to log all messages, or only log messages that are deemed critical. The level specified by `LSF_CMD_LOG_MASK` determines which messages are recorded and which are discarded. All messages logged at the specified level or higher are recorded, while lower level messages are discarded.

For debugging purposes, the level `LOG_DEBUG` contains the fewest number of debugging messages and is used for basic debugging. The level `LOG_DEBUG3` records all debugging messages, and can cause log files to grow very large; it is not often used. Most debugging is done at the level `LOG_DEBUG2`.

The commands log to the `syslog` facility unless `LSF_CMD_LOGDIR` is set.

### Valid values

The log levels from highest to lowest are:

- LOG\_EMERG
- LOG\_ALERT
- LOG\_CRIT
- LOG\_ERR
- LOG\_WARNING
- LOG\_NOTICE
- LOG\_INFO
- LOG\_DEBUG
- LOG\_DEBUG1
- LOG\_DEBUG2
- LOG\_DEBUG3

### Default

```
LOG_WARNING
```

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD,  
LSB\_TIME\_CMD, LSB\_CMD\_LOGDIR, LSF\_LOG\_MASK, LSF\_LOGDIR,  
LSF\_TIME\_CMD

## LSF\_CONF\_RETRY\_INT

### Syntax

**LSF\_CONF\_RETRY\_INT**=*time\_seconds*

### Description

The number of seconds to wait between unsuccessful attempts at opening a configuration file (only valid for LIM). This allows LIM to tolerate temporary access failures.

### EGO parameter

EGO\_CONF\_RETRY\_INT

### Default

30

## See also

LSF\_CONF\_RETRY\_MAX

## LSF\_CONF\_RETRY\_MAX

### Syntax

**LSF\_CONF\_RETRY\_MAX**=*integer*

### Description

The maximum number of retry attempts by LIM to open a configuration file. This allows LIM to tolerate temporary access failures. For example, to allow one more attempt after the first attempt has failed, specify a value of 1.

### EGO parameter

EGO\_CONF\_RETRY\_MAX

### Default

0

## See also

LSF\_CONF\_RETRY\_INT

## LSF\_CONFDIR

### Syntax

**LSF\_CONFDIR**=*directory*

### Description

Directory in which all LSF configuration files are installed. These files are shared throughout the system and should be readable from any host. This directory can contain configuration files for more than one cluster.

The files in the LSF\_CONFDIR directory must be owned by the primary LSF administrator, and readable by all LSF server hosts.

### Default

LSF\_INDEP/conf

### See also

LSB\_CONFDIR

## LSF\_CPUSETLIB

### Syntax

**LSF\_CPUSETLIB**=*path*

### Description

Points to the SGI cpuset library `libcpuset.so`. The parameter only takes effect on 64-bit x-86 Linux 2.6, glibc 2.3.

### Default

`/usr/lib64/libcpuset.so`

## LSF\_CRASH\_LOG

### Syntax

**LSF\_CRASH\_LOG**=**Y | N**

### Description

On Linux hosts only, enables logging when or if a daemon crashes. Relies on the Linux debugger (gdb). Two log files are created, one for the root daemons (res, lim, sbd, and mbatchd) in `/tmp/lsf_root_daemons_crash.log` and one for administrative daemons (mbschd) in `/tmp/lsf_admin_daemons_crash.log`.

File permissions for both files are 600.

If enabling, you must restart the daemons for the change to take effect.

### Default

N (no log files are created for daemon crashes)

## LSF\_DAEMONS\_CPUS

### Syntax

```
LSF_DAEMONS_CPUS="mbatchd_cpu_list:mbschd_cpu_list"
```

#### *mbatchd\_cpu\_list*

Defines the list of master host CPUS where the mbatchd daemon processes can run (hard CPU affinity). Format the list as a white-space delimited list of CPU numbers.

#### *mbschd\_cpu\_list*

Defines the list of master host CPUS where the mbschd daemon processes can run. Format the list as a white-space delimited list of CPU numbers.

### Description

By default, mbatchd and mbschd can run on any CPUs. If LSF\_DAEMONS\_CPUS is set, they only run on a specified list of CPUs. An empty list means LSF daemons can run on any CPUs. Use spaces to separate multiple CPUs.

The operating system can assign other processes to run on the same CPU; however, if utilization of the bound CPU is lower than utilization of the unbound CPUs.

### Related parameters

To improve scheduling and dispatch performance of all LSF daemons, you should use LSF\_DAEMONS\_CPUS together with EGO\_DAEMONS\_CPUS (in ego.conf or lsf.conf), which controls LIM CPU allocation, and MBD\_QUERY\_CPUS, which binds mbactchd query processes to specific CPUs so that higher priority daemon processes can run more efficiently. To get best performance, CPU allocation for all four daemons should be assigned their own CPUs. For example, on a 4 CPU SMP host, the following configuration gives the best performance:

```
EGO_DAEMONS_CPUS=0 LSF_DAEMONS_CPUS=1: 2 MBD_QUERY_CPUS=3
```

### Examples

If you specify

```
LSF_DAEMONS_CPUS="1:2"
```

the mbatchd processes run only on CPU number 1 on the master host, and mbschd run on only on CPU number 2.

If you specify

```
LSF_DAEMONS_CPUS="1 2:1 2"
```

both mbatchd and mbschd run CPU 1 and CPU 2.

### Important

You can specify CPU affinity only for master hosts that use one of the following operating systems:

- Linux 2.6 or higher
- Solaris 8 or higher

## EGO parameter

`LSF_DAEMONS_CPUS=lim_cpu_list`: run the EGO LIM daemon on the specified CPUs.

## Default

Not defined

## See also

`MBD_QUERY_CPUS` in `lsb.params`

## LSF\_DAEMON\_WRAP

### Syntax

`LSF_DAEMON_WRAP=y | Y`

### Description

Applies to Kerberos, DCE/DFS and AFS environments; if you are using LSF with DCE, AFS, or Kerberos, set this parameter to `y` or `Y`.

When this parameter is set to `y` or `Y`, `mbatchd`, `sbatchd`, and `RES` run the executable `daemons.wrap` located in `LSF_SERVERDIR`.

### Default

Not defined. LSF does not run the `daemons.wrap` executable.

## LSF\_DEBUG\_CMD

### Syntax

`LSB_DEBUG_CMD=log_class`

### Description

Sets the debugging log class for LSF commands and APIs.

Specifies the log class filtering to be applied to LSF commands or the API. Only messages belonging to the specified log class are recorded.

`LSF_DEBUG_CMD` sets the log class and is used in combination with `LSF_CMD_LOG_MASK`, which sets the log level. For example:

```
LSF_CMD_LOG_MASK=LOG_DEBUG LSF_DEBUG_CMD="LC_TRACE LC_EXEC"
```

Debugging is turned on when you define both parameters.

The daemons log to the `syslog` facility unless `LSF_CMD_LOGDIR` is defined.

To specify multiple log classes, use a space-separated list enclosed by quotation marks. For example:

```
LSF_DEBUG_CMD="LC_TRACE LC_EXEC"
```

Can also be defined from the command line.

### Valid values

Valid log classes are:

- LC\_AFS - Log AFS messages
- LC\_AUTH - Log authentication messages
- LC\_CHKPNT - Log checkpointing messages
- LC\_COMM - Log communication messages
- LC\_DCE - Log messages pertaining to DCE support
- LC\_EEVENTD - Log eventd messages
- LC\_ELIM - Log ELIM messages
- LC\_EXEC - Log significant steps for job execution
- LC\_FAIR - Log fairshare policy messages
- LC\_FILE - Log file transfer messages
- LC\_HANG - Mark where a program might hang
- LC\_JARRAY - Log job array messages
- LC\_JLIMIT - Log job slot limit messages
- LC\_LICENSE - Log license management messages (LC\_LICENSE is also supported for backward compatibility)
- LC\_LOADINDX - Log load index messages
- LC\_M\_LOG - Log multievent logging messages
- LC\_MPI - Log MPI messages
- LC\_MULTI - Log messages pertaining to MultiCluster
- LC\_PEND - Log messages related to job pending reasons
- LC\_PERFM - Log performance messages
- LC\_PIM - Log PIM messages
- LC\_PREEMPT - Log preemption policy messages
- LC\_RESREQ - Log resource requirement messages
- LC\_SIGNAL - Log messages pertaining to signals
- LC\_SYS - Log system call messages
- LC\_TRACE - Log significant program walk steps
- LC\_XDR - Log everything transferred by XDR

## Default

Not defined

## See also

LSF\_CMD\_LOG\_MASK, LSF\_CMD\_LOGDIR, LSF\_DEBUG\_LIM, LSF\_DEBUG\_RES, LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT, LSF\_LOGDIR, LSF\_LIM\_DEBUG, LSF\_RES\_DEBUG

## LSF\_DEBUG\_LIM

### Syntax

**LSF\_DEBUG\_LIM**=*log\_class*

### Description

Sets the log class for debugging LIM.

Specifies the log class filtering to be applied to LIM. Only messages belonging to the specified log class are recorded.

The `LSF_DEBUG_LIM` sets the log class and is used in combination with `EGO_LOG_MASK` in `ego.conf`, which sets the log level.

For example, in `ego.conf`:

```
EGO_LOG_MASK=LOG_DEBUG
```

and in `lsf.conf`:

```
LSF_DEBUG_LIM=LC_TRACE
```

---

### Important:

`LSF_LOG_MASK` in `lsf.conf` no longer specifies LIM logging level in LSF Version 7. For LIM, you must use `EGO_LOG_MASK` in `ego.conf` to control message logging for LIM. The default value for `EGO_LOG_MASK` is `LOG_WARNING`.

---

You need to restart the daemons after setting `LSF_DEBUG_LIM` for your changes to take effect.

If you use the command `lsadmin limdebug` to temporarily change this parameter without changing `lsf.conf`, you do not need to restart the daemons.

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSF_DEBUG_LIM="LC_TRACE LC_EXEC"
```

This parameter can also be defined from the command line.

## Valid values

Valid log classes are:

- `LC_AFS` - Log AFS messages
- `LC_AUTH` - Log authentication messages
- `LC_CHKPNT` - log checkpointing messages
- `LC_COMM` - Log communication messages
- `LC_DCE` - Log messages pertaining to DCE support
- `LC_EXEC` - Log significant steps for job execution
- `LC_FILE` - Log file transfer messages
- `LC_HANG` - Mark where a program might hang
- `LC_JGRP` - Log job group messages
- `LC_LICENSE` - Log license management messages (`LC_LICENSE` is also supported for backward compatibility)
- `LC_LICSCHEM` - Log LSF License Scheduler messages
- `LC_MEMORY` - Log memory limit messages
- `LC_MULTI` - Log messages pertaining to MultiCluster
- `LC_PIM` - Log PIM messages
- `LC_RESOURCE` - Log resource broker messages
- `LC_SIGNAL` - Log messages pertaining to signals
- `LC_TRACE` - Log significant program walk steps
- `LC_XDR` - Log everything transferred by XDR

## EGO parameter

`EGO_DEBUG_LIM`

## Default

Not defined

## See also

LSF\_DEBUG\_RES, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR

## LSF\_DEBUG\_RES

### Syntax

```
LSF_DEBUG_RES=log_class
```

### Description

Sets the log class for debugging RES.

Specifies the log class filtering to be applied to RES. Only messages belonging to the specified log class are recorded.

LSF\_DEBUG\_RES sets the log class and is used in combination with LSF\_LOG\_MASK, which sets the log level. For example:

```
LSF_LOG_MASK=LOG_DEBUG LSF_DEBUG_RES=LC_TRACE
```

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LSF_DEBUG_RES="LC_TRACE LC_EXEC"
```

You need to restart the daemons after setting LSF\_DEBUG\_RES for your changes to take effect.

If you use the command `lsadmin resdebug` to temporarily change this parameter without changing `lsf.conf`, you do not need to restart the daemons.

### Valid values

For a list of valid log classes see LSF\_DEBUG\_LIM

### Default

Not defined

### See also

LSF\_DEBUG\_LIM, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR

## LSF\_DHCP\_ENV

### Syntax

```
LSF_DHCP_ENV=y
```

### Description

If defined, enables dynamic IP addressing for all LSF client hosts in the cluster.

Dynamic IP addressing is not supported across clusters in a MultiCluster environment.

If you set `LSF_DHCP_ENV`, you must also specify `LSF_DYNAMIC_HOST_WAIT_TIME` in order for hosts to rejoin a cluster after their IP address changes.

---

**Tip:**

After defining or changing this parameter, you must run `l sadmi n reconfi g` and `badmi n mbdrest art` to restart all LSF daemons.

---

## EGO parameter

`EGO_DHCP_ENV`

### Default

Not defined

### See also

`LSF_DYNAMIC_HOST_WAIT_TIME`

## LSF\_DISABLE\_LSRUN

### Syntax

`LSF_DISABLE_LSRUN=y | Y`

### Description

When defined, RES refuses remote connections from `l srun` and `l sgrun` unless the user is either an LSF administrator or root. For remote execution by root, `LSF_ROOT_REX` must be defined.

Other remote execution commands, such as `ch` and `l smake` are not affected.

### Default

Not defined

## LSF\_DISPATCHER\_LOGDIR

### Syntax

`LSF_DISPATCHER_LOGDIR=path`

### Description

Specifies the path to the log files for slot allocation decisions for queue-based fairshare.

If defined, LSF writes the results of its queue-based fairshare slot calculation to the specified directory. Each line in the file consists of a timestamp for the slot allocation and the number of slots allocated to each queue under its control. LSF logs in this file every minute. The format of this file is suitable for plotting with `gnupl ot`.

## Example

```
# clients managed by LSF
# Roma # Verona # Genova # Pi sa # Venezi a # Bol ogna
15/3      19: 4: 50    0 0 0 0 0 0
15/3      19: 5: 51    8 5 2 5 2 0
15/3      19: 6: 51    8 5 2 5 5 1
15/3      19: 7: 53    8 5 2 5 5 5
15/3      19: 8: 54    8 5 2 5 5 0
15/3      19: 9: 55    8 5 0 5 4 2
```

The queue names are in the header line of the file. The columns correspond to the allocations per each queue.

## Default

Not defined

## LSF\_DUALSTACK\_PREFER\_IPV6

## Syntax

**LSF\_DUALSTACK\_PREFER\_IPV6=Y | y**

## Description

Define this parameter when you want to ensure that clients and servers on dual-stack hosts use IPv6 addresses only. Setting this parameter configures LSF to sort the dynamically created address lookup list in order of AF\_INET6 (IPv6) elements first, followed by AF\_INET (IPv4) elements, and then others.

---

### Restriction:

IPv4-only and IPv6-only hosts cannot belong to the same cluster. In a MultiCluster environment, you cannot mix IPv4-only and IPv6-only clusters.

---

Follow these guidelines for using IPv6 addresses within your cluster:

- Define this parameter only if your cluster
  - Includes only dual-stack hosts, or a mix of dual-stack and IPv6-only hosts, *and*
  - Does not include IPv4-only hosts or IPv4 servers running on dual-stack hosts (servers prior to LSF version 7)

---

### Important:

Do not define this parameter for any other cluster configuration.

- Within a MultiCluster environment, do not define this parameter if any cluster contains IPv4-only hosts or IPv4 servers (prior to LSF version 7) running on dual-stack hosts.
- Applications must be engineered to work with the cluster IP configuration.
- If you use IPv6 addresses within your cluster, ensure that you have configured the dual-stack hosts correctly. For more detailed information, see *Administering Platform LSF*.
- Define the parameter LSF\_ENABLE\_SUPPORT\_IPV6 in `lsf.conf`.

## Default

Not defined. LSF sorts the dynamically created address lookup list in order of AF\_INET (IPv4) elements first, followed by AF\_INET6 (IPv6) elements, and then others. Clients and servers on dual-stack hosts use the first address lookup structure in the list (IPv4).

## See also

LSF\_ENABLE\_SUPPORT\_IPV6

## LSF\_DYNAMIC\_HOST\_TIMEOUT

### Syntax

**LSF\_DYNAMIC\_HOST\_TIMEOUT=***time\_hours*

**LSF\_DYNAMIC\_HOST\_TIMEOUT=***time\_minutes***m|M**

### Description

Enables automatic removal of dynamic hosts from the cluster and specifies the timeout value (minimum 10 minutes). To improve performance in very large clusters, you should disable this feature and remove unwanted hosts from the host cache file manually.

Specifies the length of time a dynamic host is unavailable before the master host removes it from the cluster. Each time LSF removes a dynamic host, mbatchd automatically reconfigures itself.

### Valid value

The timeout value must be greater than or equal to 10 minutes.

### Example

```
LSF_DYNAMIC_HOST_TIMEOUT=60
```

A dynamic host is removed from the cluster when it is unavailable for 60 hours.

```
LSF_DYNAMIC_HOST_TIMEOUT=60m
```

A dynamic host is removed from the cluster when it is unavailable for 60 minutes.

### EGO parameter

EGO\_DYNAMIC\_HOST\_TIMEOUT

### Default

Not defined. Unavailable hosts are never removed from the cluster.

## LSF\_DYNAMIC\_HOST\_WAIT\_TIME

### Syntax

**LSF\_DYNAMIC\_HOST\_WAIT\_TIME=***time\_seconds*

## Description

Defines the length of time in seconds that a dynamic host waits communicating with the master LIM to either add the host to the cluster or to shut down any running daemons if the host is not added successfully.

---

### Note:

To enable dynamically added hosts, the following parameters must be defined:

- LSF\_MASTER\_LIST in `lsf.conf`
  - LSF\_DYNAMIC\_HOST\_WAIT\_TIME in `lsf.conf`, or EGO\_DYNAMIC\_HOST\_WAIT\_TIME in `ego.conf`
  - LSF\_HOST\_ADDR\_RANGE in `lsf.cluster.cluster_name`
- 

### Note:

To enable daemons to be shut down automatically for hosts that attempted to join the cluster but were rejected within the LSF\_DYNAMIC\_HOST\_WAIT\_TIME period:

- EGO\_ENABLE\_AUTO\_DAEMON\_SHUTDOWN in `lsf.conf` or in `ego.conf`.
- 

## Recommended value

An integer greater than zero, up to 60 seconds for every 1000 hosts in the cluster, for a maximum of 15 minutes. Selecting a smaller value results in a quicker response time for hosts at the expense of an increased load on the master LIM.

## Example

```
LSF_DYNAMIC_HOST_WAIT_TIME=60
```

A host waits 60 seconds from startup to send a request for the master LIM to add it to the cluster or to shut down any daemons if it is not added to the cluster.

## EGO parameter

```
EGO_DYNAMIC_HOST_WAIT_TIME
```

## Default

```
60
```

## LSF\_EGO\_DAEMON\_CONTROL

## Syntax

```
LSF_EGO_DAEMON_CONTROL="Y" | "N"
```

## Description

Enables EGO Service Controller to control LSF `res` and `sbatchd` startup. Set the value to "Y" if you want EGO Service Controller to start `res` and `sbatchd`, and restart them if they fail.

To configure this parameter at installation, set `EGO_DAEMON_CONTROL` in `install.conf` so that `res` and `sbatchd` start automatically as EGO services.

If `LSF_ENABLE_EGO="N"`, this parameter is ignored and EGO Service Controller is not started.

If you manually set `EGO_DAEMON_CONTROL=Y` after installation, you *must* configure LSF `res` and `sbatchd` startup to `AUTOMATIC` in the EGO configuration files `res.xml` and `sbatchd.xml` under `EGO_ESRVDIR/esc/conf/services`.

To avoid conflicts with existing LSF startup scripts, do not set this parameter to "Y" if you use a script (for example in `/etc/rc` or `/etc/inittab`) to start LSF daemons. If this parameter is not defined in `install.conf` file, it takes default value of "N".

---

### Important:

After installation, `LSF_EGO_DAEMON_CONTROL` alone *does not* change the start type for the `sbatchd` and `res` EGO services to `AUTOMATIC` in `res.xml` and `sbatchd.xml` under `EGO_ESRVDIR/esc/conf/services`. You must edit these files and set the `<sc:StartType>` parameter to `AUTOMATIC`.

---

## Example

```
LSF_EGO_DAEMON_CONTROL="N"
```

## Default

N (`res` and `sbatchd` are started manually or through operating system rc facility)

## LSF\_EGO\_ENVDIR

### Syntax

```
LSF_EGO_ENVDIR=directory
```

### Description

Directory where all Platform EGO configuration files are installed. These files are shared throughout the system and should be readable from any host.

If `LSF_ENABLE_EGO="N"`, this parameter is ignored and `ego.conf` is not loaded.

## Default

`LSF_CONFDIR/ego/cluster_name/kernel`. If not defined, or commented out, `/etc` is assumed.

## LSF\_ENABLE\_CSA

### Syntax

```
LSF_ENABLE_CSA=y | Y
```

## Description

If set, enables LSF to write records for LSF jobs to SGI IRIX Comprehensive System Accounting facility (CSA).

CSA writes an accounting record for each process in the `pacct` file, which is usually located in the `/var/adm/acct/day` directory. IRIX system administrators then use the `csabui ld` command to organize and present the records on a job by job basis.

When `LSF_ENABLE_CSA` is set, for each job run on the IRIX system, LSF writes an LSF-specific accounting record to CSA when the job starts, and when the job finishes. LSF daemon accounting in CSA starts and stops with the LSF daemon.

To disable IRIX CSA accounting, remove `LSF_ENABLE_CSA` from `lsf.conf`.

See the IRIX resource administration documentation for information about CSA.

## Setting up IRIX CSA

1. Define the `LSF_ENABLE_CSA` parameter in `lsf.conf`:
 

```
... LSF_ENABLE_CSA=Y ...
```
2. Set the following parameters in `/etc/csa.conf` to on:
  - `CSA_START`
  - `WKMG_START`
3. Run the `csaswitch` command to turn on the configuration changes in `/etc/csa.conf`.

---

### Note:

See the IRIX resource administration documentation for information about the `csaswitch` command.

---

## Information written to the `pacct` file

LSF writes the following records to the `pacct` file when a job starts and when it exits:

- Job record type (job start or job exit)
- Current system clock time
- Service provider (LSF)
- Submission time of the job (at job start only)
- User ID of the job owner
- Array Session Handle (ASH) of the job
- IRIX job ID
- IRIX project ID
- LSF job name if it exists
- Submission host name
- LSF queue name
- LSF external job ID
- LSF job array index
- LSF job exit code (at job exit only)
- `NCPUS`: number of CPUs the LSF job has been using

## Default

Not defined

## LSF\_ENABLE\_DUALCORE

### Syntax

`LSF_ENABLE_DUALCORE=y | n`

### Description

Enables job scheduling based on dual-core information for a host. If yes (Y), LSF scheduling policies use the detected number of cores as the number of physical processors on the host instead of the number of dual-core chips for job scheduling. For a dual-core host, `lshosts` shows the number of cores under `ncpus` instead of the number of chips.

If `LSF_ENABLE_DUALCORE=n`, then `lshosts` shows the number of processor chips under `ncpus`.

### EGO parameter

`EGO_ENABLE_DUALCORE`

## Default

N

## LSF\_ENABLE\_EGO

### Syntax

`LSF_ENABLE_EGO="Y" | "N"`

### Description

Enables Platform EGO functionality in the LSF cluster.

If you set `LSF_ENABLE_EGO="Y"`, you must set or uncomment `LSF_EGO_ENVDIR` in `lsf.conf`.

If you set `LSF_ENABLE_EGO="N"` you must remove or comment out `LSF_EGO_ENVDIR` in `lsf.conf`.

Set the value to "N" if you do not want to take advantage of the following LSF features that depend on EGO:

- LSF daemon control by EGO Service Controller
- EGO-enabled SLA scheduling
- Platform Management Console (PMC)
- LSF reporting

---

#### Important:

After changing the value of `LSF_ENABLE_EGO`, you must shut down and restart the cluster.

---

## Default

Y (EGO is enabled in the LSF cluster)

## LSF\_ENABLE\_EXTSCHEDULER

## Syntax

`LSF_ENABLE_EXTSCHEDULER=y | Y`

## Description

If set, enables mbatchd external scheduling for LSF HPC.

## Default

Not defined

## LSF\_ENABLE\_SUPPORT\_IPV6

## Syntax

`LSF_ENABLE_SUPPORT_IPV6=y | Y`

## Description

If set, enables the use of IPv6 addresses in addition to IPv4.

## Default

Not defined

## See also

`LSF_DUALSTACK_PREFER_IPV6`

## LSF\_ENVDIR

## Syntax

`LSF_ENVDIR=directory`

## Description

Directory containing the `lsf.conf` file.

By default, `lsf.conf` is installed by creating a shared copy in `LSF_CONFDIR` and adding a symbolic link from `/etc/lsf.conf` to the shared copy. If `LSF_ENVDIR` is set, the symbolic link is installed in `LSF_ENVDIR/lsf.conf`.

The `lsf.conf` file is a global environment configuration file for all LSF services and applications. The LSF default installation places the file in `LSF_CONFDIR`.

## Default

`/etc`

## LSF\_EVENT\_PROGRAM

### Syntax

**LSF\_EVENT\_PROGRAM**=*event\_program\_name*

### Description

Specifies the name of the LSF event program to use.

If a full path name is not provided, the default location of this program is LSF\_SERVERDIR.

If a program that does not exist is specified, event generation does not work.

If this parameter is not defined, the default name is `genevent` on UNIX, and `genevent.exe` on Windows.

### Default

Not defined

## LSF\_EVENT\_RECEIVER

### Syntax

**LSF\_EVENT\_RECEIVER**=*event\_receiver\_program\_name*

### Description

Specifies the LSF event receiver and enables event generation.

Any string may be used as the LSF event receiver; this information is not used by LSF to enable the feature but is only passed as an argument to the event program.

If LSF\_EVENT\_PROGRAM specifies a program that does not exist, event generation does not work.

### Default

Not defined. Event generation is disabled

## LSF\_GET\_CONF

### Syntax

**LSF\_GET\_CONF**=*lim*

### Description

Synchronizes a local host's cluster configuration with the master host's cluster configuration. Specifies that a slave host must request cluster configuration details from the LIM of a host on the SERVER\_HOST list. Use when a slave host does not share a filesystem with master hosts, and therefore cannot access cluster configuration.

### Default

Not defined.

## LSF\_HOST\_CACHE\_NTTL

### Syntax

```
LSF_HOST_CACHE_NTTL=time_seconds
```

### Description

Negative-time-to-live value in seconds. Specifies the length of time the system caches a failed DNS lookup result. If you set this value to zero (0), LSF does not cache the result.

---

**Note:**

Setting this parameter does not affect the positive-time-to-live value set by the parameter LSF\_HOST\_CACHE\_PTTL.

---

### Valid values

Positive integer. Recommended value less than or equal to 60 seconds (1 minute).

### Default

20 seconds

### See also

LSF\_HOST\_CACHE\_PTTL

## LSF\_HOST\_CACHE\_PTTL

### Syntax

```
LSF_HOST_CACHE_PTTL=time_seconds
```

### Description

Positive-time-to-live value in seconds. Specifies the length of time the system caches a successful DNS lookup result. If you set this value to zero (0), LSF does not cache the result.

---

**Note:**

Setting this parameter does not affect the negative-time-to-live value set by the parameter LSF\_HOST\_CACHE\_NTTL.

---

### Valid values

Positive integer. Recommended value equal to or greater than 3600 seconds (1 hour).

### Default

86400 seconds (24 hours)

### See also

LSF\_HOST\_CACHE\_NTTL

## LSF\_HPC\_EXTENSIONS

### Syntax

```
LSF_HPC_EXTENSIONS="extension_name ..."
```

### Description

Enables Platform LSF HPC extensions.

### Valid values

The following extension names are supported:

**CUMULATIVE\_RUSAGE** : When a parallel job script runs multiple commands, resource usage is collected for jobs in the job script, rather than being overwritten when each command is executed.

**DISP\_RES\_USAGE\_LIMITS** : bj obs displays resource usage limits configured in the queue as well as job-level limits.

**LSB\_HCLOSE\_BY\_RES** : If res is down, host is closed with a message

Host is closed because RES is not available.

The status of the closed host is closed\_Adm. No new jobs are dispatched to this host, but currently running jobs are not suspended.

**RESERVE\_BY\_STARTTIME** : LSF selects the reservation that gives the job the earliest predicted start time.

By default, if multiple host groups are available for reservation, LSF chooses the largest possible reservation based on number of slots.

**SHORT\_EVENTFILE** : Compresses long host name lists when event records are written to lsb.events and lsb.acct for large parallel jobs. The short host string has the format:

*number\_of\_hosts\*real\_host\_name*

---

#### Tip:

When SHORT\_EVENTFILE is enabled, older daemons and commands (pre-LSF Version 7) cannot recognize the lsb.acct and lsb.events file format.

---

For example, if the original host list record is

```
6 "hostA" "hostA" "hostA" "hostA" "hostB" "hostC"
```

redundant host names are removed and the short host list record becomes

```
3 "4*hostA" "hostB" "hostC"
```

When LSF\_HPC\_EXTENSIONS="SHORT\_EVENTFILE" is set, and LSF reads the host list from lsb.events or lsb.acct, the compressed host list is expanded into a normal host list.

SHORT\_EVENTFILE affects the following events and fields:

- JOB\_START in lsb.events when a normal job is dispatched
  - numExHosts (%d)
  - execHosts (%s)
- JOB\_CHUNK in lsb.events when a job is inserted into a job chunk

- numExHosts (%d)
- execHosts (%s)
- JOB\_FORWARD in l sb. event s when a job is forwarded to a MultiCluster leased host
  - numReserHosts (%d)
  - reserHosts (%s)
- JOB\_FINISH record in l sb. acct
  - numExHosts (%d)
  - execHosts (%s)

SHORT\_PIDLIST : Shortens the output from bj obs to omit all but the first process ID (PID) for a job. bj obs displays only the first ID and a count of the process group IDs (PGIDs) and process IDs for the job.

Without SHORT\_PIDLIST, bj obs -l displays all the PGIDs and PIDs for the job. With SHORT\_PIDLIST set, bj obs -l displays a count of the PGIDs and PIDs.

TASK\_MEMLIMIT : Enables enforcement of a memory limit (bsub -M, bmod -M, or MEMLIMIT in l sb. queues) for individual tasks in a parallel job. If any parallel task exceeds the memory limit, LSF terminates the entire job.

TASK\_SWAPLIMIT: Enables enforcement of a virtual memory (swap) limit (bsub -v, bmod -v, or SWAPLIMIT in l sb. queues) for individual tasks in a parallel job. If any parallel task exceeds the swap limit, LSF terminates the entire job.

## Example JOB\_START events in lsb.events:

For a job submitted with

```
bsub -n 64 -R "span[ptile=32]" sleep 100
```

Without SHORT\_EVENTFILE, a JOB\_START event like the following would be logged in l sb. event s:

```
"JOB_START" "7.0" 1058989891 710 4 0 0 10.3 64 "hostA" "hostA" "hostA" "hostA" "hostA" "hostA"
"hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA"
"hostA" "hostA" "hostA" "u050" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA"
"hostA" "hostA" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB"
"hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB"
"hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" " " " " 0 " " 0
```

With SHORT\_EVENTFILE, a JOB\_START event would be logged in l sb. event s with the number of execution hosts (numExHosts field) changed from 64 to 2 and the execution host list (execHosts field) shortened to "32\*hostA" and "32\*hostB":

```
"JOB_START" "7.0" 1058998174 812 4 0 0 10.3 2 "32*hostA" "32*hostB" " " " " 0 " " 0 "
```

## Example JOB\_FINISH records in lsb.acct:

For a job submitted with

```
bsub -n 64 -R "span[ptile=32]" sleep 100
```

Without SHORT\_EVENTFILE, a JOB\_FINISH event like the following would be logged in l sb. acct:

```
"JOB_FINISH" "7.0" 1058990001 710 33054 33816578 64 1058989880 0 0 1058989891 "user1" "normal"
"span[ptile=32]" " " " " "hostA" "/scratch/user1/work" " " " " "1058989880.710" 0 64 "hostA"
"hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA"
"hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA"
"hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostA" "hostB" "hostB" "hostB" "hostB"
"hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB"
"hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB"
"hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB" "hostB"
0 -1 " " "default" 0 64 " " " " 0 4304 6024 " " " "
```

With `SHORT_EVENTFILE`, a `JOB_FINISH` event like the following would be logged in `lsb.acct` with the number of execution hosts (`numExHosts` field) changed from 64 to 2 and the execution host list (`execHosts` field) shortened to `"32*hostA"` and `"32*hostB"`:

```
"JOB_FINISH" "7.0" 1058998282 812 33054 33816578 64 1058998163 0 0 1058998174 "user1" "normal"
"span[ptile=32]" "" "" "hostA" "/scratch/user1/work" "" "" "" "1058998163.812" 0 2 "32*hostA"
"32*hostB" 64 10.3 "" "sleep 100" 0.039999 0 0 -1 0 0 0 0 0 0 -1 0 0 0 0 0 -1 "" "default"
0 64 "" "" 0 4304 6024 "" "" "" "" 0
```

## Example `bjobs -l` output without `SHORT_PIDLIST`:

`bjobs -l` displays all the PGIDs and PIDs for the job:

### `bjobs -l`

Job <109>, User <user3>, Project <default>, Status <RUN>, Queue <normal>, Inte

ractive mode, Command <./myjob.sh>

Mon Jul 21 20:54:44: Submitted from host <hostA>, CWD <\$HOME/LSF/jobs>

#### RUNLIMIT

10.0 min of hostA

#### STACKLIMIT CORELIMIT MEMLIMIT

5256 K 10000 K 5000 K

Mon Jul 21 20:54:51: Started on <hostA>;

Mon Jul 21 20:55:03: Resource usage collected.

MEM: 2 Mbytes; SWAP: 15 Mbytes

PGID: 256871; PIDs: 256871

PGID: 257325; PIDs: 257325 257500 257482 257501 257523

257525 257531

#### SCHEDULING PARAMETERS:

|           | r15s     | r1m | r15m      | ut | pg | io | ls | it | tmp | swp | mem |
|-----------|----------|-----|-----------|----|----|----|----|----|-----|-----|-----|
| loadSched | -        | -   | -         | -  | -  | -  | -  | -  | -   | -   | -   |
| loadStop  | -        | -   | -         | -  | -  | -  | -  | -  | -   | -   | -   |
|           | cpuspeed |     | bandwidth |    |    |    |    |    |     |     |     |
| loadSched | -        |     | -         |    |    |    |    |    |     |     |     |
| loadStop  | -        |     | -         |    |    |    |    |    |     |     |     |

<< Job <109> is done successfully. >>

## Example bjobs -l output with SHORT\_PIDLIST:

`bjobs -l` displays a count of the PGIDS and PIDs:

```

bjobs -l
Job <109>, User <user3>, Project <default>, Status <RUN>, Queue <normal>, Inte
ractive mode, Command <./myjob.sh>
Mon Jul 21 20:54:44: Submitted from host <hostA>, CWD <$HOME/LSF/jobs>

RUNLIMIT
10.0 min of hostA

STACKLIMIT CORELIMIT MEMLIMIT
5256 K    10000 K    5000 K

Mon Jul 21 20:54:51: Started on <hostA>;
Mon Jul 21 20:55:03: Resource usage collected.
MEM: 2 Mbytes; SWAP: 15 Mbytes
PGID(s): 256871: 1 PID, 257325: 7 PIDs

SCHEDULING PARAMETERS:
      r15s  r1m  r15m  ut      pg   io  ls   it   tmp  swp  mem
loadSched -   -   -   -     -   -   -   -   -   -   -
loadStop  -   -   -   -     -   -   -   -   -   -   -

      cpuspeed  bandwidth
loadSched      -           -
loadStop       -           -

```

## Default

Not defined

## LSF\_HPC\_NCPU\_COND

## Syntax

`LSF_HPC_NCPU_COND=and | or`

## Description

Defines how any two `LSF_HPC_NCPU_*` thresholds are combined.

## Default

or

## LSF\_HPC\_NCPU\_INCREMENT

## Syntax

`LSF_HPC_NCPU_INCREMENT=increment`

## Description

Defines the upper limit for the number of CPUs that are changed since the last checking cycle.

## Default

0

## LSF\_HPC\_NCPU\_INCR\_CYCLES

## Syntax

**LSF\_HPC\_NCPU\_INCR\_CYCLES**=*increment\_cycles*

## Description

Minimum number of consecutive cycles where the number of CPUs changed does not exceed LSF\_HPC\_NCPU\_INCREMENT. LSF checks total usable CPUs every 2 minutes.

## Default

1

## LSF\_HPC\_NCPU\_THRESHOLD

## Syntax

**LSF\_HPC\_NCPU\_THRESHOLD**=*threshold*

## Description

The percentage of total usable CPUs in the LSF partition of a SLURM cluster.

## Default

80

## LSF\_HPC\_PJL\_LOADENV\_TIMEOUT

## Syntax

**LSF\_HPC\_PJL\_LOADENV\_TIMEOUT**=*time\_seconds*

## Description

Timeout value in seconds for PJL to load or unload the environment. For example, set LSF\_HPC\_PJL\_LOADENV\_TIMEOUT to the number of seconds needed for IBM POE to load or unload adapter windows.

At job startup, the PJL times out if the first task fails to register with PAM within the specified timeout value. At job shutdown, the PJL times out if it fails to exit after the last Taskstarter termination report within the specified timeout value.

## Default

LSF\_HPC\_PJL\_LOADENV\_TIMEOUT=300

## LSF\_ID\_PORT

### Syntax

**LSF\_ID\_PORT**=*port\_number*

### Description

The network port number used to communicate with the authentication daemon when LSF\_AUTH is set to ident.

### Default

Not defined

## LSF\_INCLUDEDIR

### Syntax

**LSF\_INCLUDEDIR**=*directory*

### Description

Directory under which the LSF API header files `lsf.h` and `lsbatch.h` are installed.

### Default

LSF\_INDEP/include

### See also

LSF\_INDEP

## LSF\_INDEP

### Syntax

**LSF\_INDEP**=*directory*

### Description

Specifies the default top-level directory for all machine-independent LSF files.

This includes man pages, configuration files, working directories, and examples. For example, defining LSF\_INDEP as `/usr/share/lsf/mnt` places man pages in `/usr/share/lsf/mnt/man`, configuration files in `/usr/share/lsf/mnt/conf`, and so on.

The files in LSF\_INDEP can be shared by all machines in the cluster.

As shown in the following list, LSF\_INDEP is incorporated into other LSF environment variables.

- LSF\_SHAREDIR=\$LSF\_INDEP/work
- LSF\_CONFDIR=\$LSF\_INDEP/conf
- LSF\_INCLUDEDIR=\$LSF\_INDEP/include
- LSF\_MANDIR=\$LSF\_INDEP/man
- XLSF\_APPDIR=\$LSF\_INDEP/misc

## Default

`/usr/share/lsf/mnt`

## See also

LSF\_MACHDEP, LSB\_SHAREDDIR, LSF\_CONFDIR, LSF\_INCLUDEDIR, LSF\_MANDIR, XLSF\_APPDIR

## LSF\_INTERACTIVE\_STDERR

### Syntax

`LSF_INTERACTIVE_STDERR=y | n`

### Description

Separates `stderr` from `stdout` for interactive tasks and interactive batch jobs.

This is useful to redirect output to a file with regular operators instead of the `bsub -e err_file` and `-o out_file` options.

This parameter can also be enabled or disabled as an environment variable.

---

#### Caution:

If you enable this parameter globally in `lsf.conf`, check any custom scripts that manipulate `stderr` and `stdout`.

---

When this parameter is not defined or set to `n`, the following are written to `stdout` on the submission host for interactive tasks and interactive batch jobs:

- Job standard output messages
- Job standard error messages

The following are written to `stderr` on the submission host for interactive tasks and interactive batch jobs:

- LSF messages
- NIOS standard messages
- NIOS debug messages (if `LSF_NIOS_DEBUG=1` in `lsf.conf`)

When this parameter is set to `y`, the following are written to `stdout` on the submission host for interactive tasks and interactive batch jobs:

- Job standard output messages

The following are written to `stderr` on the submission host:

- Job standard error messages
- LSF messages
- NIOS standard messages
- NIOS debug messages (if `LSF_NIOS_DEBUG=1` in `lsf.conf`)

## Default

Not defined

## Notes

When this parameter is set, the change affects interactive tasks and interactive batch jobs run with the following commands:

- `bsub -I`
- `bsub -Ip`
- `bsub -Is`
- `lrun`
- `lsgun`
- `lsmake` (Platform LSF Make)
- `bsub pam` (Platform LSF HPC)

## Limitations

- **Pseudo-terminal:** Do not use this parameter if your application depends on `stderr` as a terminal. This is because LSF must use a non-pseudo-terminal connection to separate `stderr` from `stdout`.
- **Synchronization:** Do not use this parameter if you depend on messages in `stderr` and `stdout` to be synchronized and jobs in your environment are continuously submitted. A continuous stream of messages causes `stderr` and `stdout` to not be synchronized. This can be emphasized with parallel jobs. This situation is similar to that of `rsh`.
- **NIOS standard and debug messages:** NIOS standard messages, and debug messages (when `LSF_NIOS_DEBUG=1` in `lsf.conf` or as an environment variable) are written to `stderr`. NIOS standard messages are in the format `<<message>>`, which makes it easier to remove them if you wish. To redirect NIOS debug messages to a file, define `LSF_CMD_LOGDIR` in `lsf.conf` or as an environment variable.

## See also

`LSF_NIOS_DEBUG`, `LSF_CMD_LOGDIR`

## LSF\_LD\_SECURITY

### Syntax

`LSF_LD_SECURITY=y | n`

### Description

**LSF\_LD\_SECURITY:** When set, jobs submitted using `bsub -Is` or `bsub -Ip` cause the environment variables `LD_PRELOAD` and `LD_LIBRARY_PATH` to be removed from the job environment during job initialization to ensure enhanced security against users obtaining root privileges.

Two new environment variables are created (`LSF_LD_LIBRARY_PATH` and `LSF_LD_PRELOAD`) to allow `LD_PRELOAD` and `LD_LIBRARY_PATH` to be put back before the job runs.

### Default

N

## LSF\_LIBDIR

### Syntax

**LSF\_LIBDIR**=*directory*

### Description

Specifies the directory in which the LSF libraries are installed. Library files are shared by all hosts of the same type.

### Default

LSF\_MACHDEP/lib

## LSF\_LIC\_SCHED\_HOSTS

### Syntax

**LSF\_LIC\_SCHED\_HOSTS**=" *candidate\_host\_list*"

*candidate\_host\_list* is a space-separated list of hosts that are candidate LSF License Scheduler hosts.

### Description

The candidate License Scheduler host list is read by LIM on each host to check if the host is a candidate License Scheduler master host. If the host is on the list, LIM starts the License Scheduler daemon (bld) on the host.

## LSF\_LIC\_SCHED\_PREEMPT\_QUEUE

### Syntax

**LSF\_LIC\_SCHED\_PREEMPT\_QUEUE**=y | n

### Description

Set this parameter to requeue a job whose license is preempted by LSF License Scheduler. The job is killed and requeued instead of suspended.

If you set LSF\_LIC\_SCHED\_PREEMPT\_QUEUE, do not set LSF\_LIC\_SCHED\_PREEMPT\_SLOT\_RELEASE. If both these parameters are set, LSF\_LIC\_SCHED\_PREEMPT\_SLOT\_RELEASE is ignored.

### Default

N

### See also

LSF\_LIC\_SCHED\_PREEMPT\_SLOT\_RELEASE, LSF\_LIC\_SCHED\_PREEMPT\_STOP

## LSF\_LIC\_SCHED\_PREEMPT\_SLOT\_RELEASE

### Syntax

`LSF_LIC_SCHED_PREEMPT_SLOT_RELEASE=y | n`

### Description

Set this parameter to release the slot of a job that is suspended when its license is preempted by LSF License Scheduler.

If you set `LSF_LIC_SCHED_PREEMPT_SLOT_RELEASE`, do not set `LSF_LIC_SCHED_PREEMPT_REQUEUE`. If both these parameters are set, `LSF_LIC_SCHED_PREEMPT_SLOT_RELEASE` is ignored.

### Default

Y

### See also

`LSF_LIC_SCHED_PREEMPT_REQUEUE`, `LSF_LIC_SCHED_PREEMPT_STOP`

## LSF\_LIC\_SCHED\_PREEMPT\_STOP

### Syntax

`LSF_LIC_SCHED_PREEMPT_STOP=y | n`

### Description

Set this parameter to use job controls to stop a job that is preempted. When this parameter is set, a UNIX SIGSTOP signal is sent to suspend a job instead of a UNIX SIGTSTP.

To send a SIGSTOP signal instead of SIGTSTP, the following parameter in `l sb. queues` must also be set:

```
JOB_CONTROLS=SUSPEND[ SIGSTOP]
```

### Default

N

### See also

`LSF_LIC_SCHED_PREEMPT_SLOT_RELEASE`,  
`LSF_LIC_SCHED_PREEMPT_REQUEUE`

## LSF\_LIC\_SCHED\_STRICT\_PROJECT\_NAME

### Syntax

`LSF_LIC_SCHED_STRICT_PROJECT_NAME=y | n`

## Description

Enforces strict checking of the License Scheduler project name upon job submission or job modification (bsub or bmod). If the project named is misspelled (case sensitivity applies), the job is rejected.

If this parameter is not set or it is set to n, and if there is an error in the project name, the default project is used.

## Default

N

## LSF\_LICENSE\_ACCT\_PATH

## Syntax

**LSF\_LICENSE\_ACCT\_PATH**=*directory*

## Description

Specifies the location for the license accounting files. These include the license accounting files for LSF Family products.

Use this parameter to define the location of all the license accounting files. By defining this parameter, you can store the license accounting files for the LSF Family of products in the same directory for convenience.

## Default

Not defined. The license accounting files are stored in the default log directory for the particular product. For example, LSF stores its license audit file in the LSF system log file directory.

## See also

- LSF\_LOGDIR
- lsf.cluster\_name.license.acct
- bld.license.acct

## LSF\_LICENSE\_FILE

## Syntax

**LSF\_LICENSE\_FILE**=" *file\_name ... | port\_number@host\_name*  
[:*port\_number@host\_name ...*]"

## Description

Specifies one or more demo or FLEXlm permanent license files used by LSF.

The value for LSF\_LICENSE\_FILE can be either of the following:

- The full path name to the license file.

- UNIX example:

```
LSF_LICENSE_FILE=/usr/share/lsf/cluster1/conf/license.dat
```

- Windows examples:

```
LSF_LICENSE_FILE= C:\licenses\license.dat
```

```
LSF_LICENSE_FILE=\\HostA\licenses\license.dat
```

- For a permanent license, the name of the license server host and TCP port number used by the lmgrd daemon, in the format *port@host\_name*. For example:

```
LSF_LICENSE_FILE="1700@hostD"
```

- For a license with redundant servers, use a comma to separate the *port@host\_names*. The port number must be the same as that specified in the SERVER line of the license file. For example:

UNIX:

```
LSF_LICENSE_FILE="port@hostA:port@hostB:port@hostC"
```

Windows:

```
LSF_LICENSE_FILE="port@hostA;port@hostB;port@hostC"
```

- For a license with distributed servers, use a pipe to separate the *port@host\_names*. The port number must be the same as that specified in the SERVER line of the license file. For example:

```
LSF_LICENSE_FILE="port@hostA|port@hostB|port@hostC"
```

Multiple license files should be quoted and must be separated by a pipe character (|).

Windows example:

```
LSF_LICENSE_FILE="C:\licenses\license1|C:\licenses\license2|D:\mydir\license3"
```

Multiple files may be kept in the same directory, but each one must reference a different license server. When checking out a license, LSF searches the servers in the order in which they are listed, so it checks the second server when there are no more licenses available from the first server.

If this parameter is not defined, LSF assumes the default location.

## Default

If you installed LSF with a default installation, the license file is installed in the LSF configuration directory (LSF\_CONFDIR/license.dat).

If you installed LSF with a custom installation, you specify the license installation directory. The default is the LSF configuration directory (LSF\_SERVERDIR for the custom installation).

If you installed FLEXlm separately from LSF to manage other software licenses, the default FLEXlm installation puts the license file in the following location:

- UNIX: /usr/share/flexlm/licenses/license.dat
- Windows: C:\flexlm\license.dat

## LSF\_LICENSE\_MAINTENANCE\_INTERVAL

### Syntax

```
LSF_LICENSE_MAINTENANCE_INTERVAL=time_seconds
```

### Description

Specifies how often LSF checks the LSF licenses when starting or restarting the cluster. A small number could delay LSF. Valid values are from 5 to 300.

When this parameter is not set, the default value is used.

## Recommended value

Set `LSF_LICENSE_MAINTENANCE_INTERVAL` depending on your cluster size, system buffer size, license server, and cluster communication speed:

- If you have network delays or a small system buffer (less than 32 KB), set `LSF_LICENSE_MAINTENANCE` to the high end of the valid values (300).
- For a small cluster (fewer than 1000 hosts), specify `LSF_LICENSE_MAINTENANCE_INTERVAL` with 5-60 second value.
- For a large cluster (greater than 4000 hosts) with limited licenses, use the maximum value: 300 seconds.
- If you have slow cluster communication (for example, if you use a Web-based intranet), use the maximum value: 300 seconds.

## Default

5 seconds

## LSF\_LICENSE\_NOTIFICATION\_INTERVAL

### Syntax

`LSF_LICENSE_MAINTENANCE_INTERVAL=time_hours`

### Description

Specifies how often notification email is sent to the primary cluster administrator about overuse of LSF Family product licenses and LSF License Scheduler tokens.

## Recommended value

To avoid getting the same audit information more than once, set `LSF_LICENSE_NOTIFICATION_INTERVAL` greater than 24 hours.

## Example notification email

```
Subject: LSF license overuse LSF Administrator: Your cluster has experienced
license overuse. Platform Product License Name: LSF_MANAGER CLASS E license
usage: 0 in total; 8 in use (8 overused). Overuse Hosts: hostA Use limit
and lshosts -l or see /usr/opt/lsf7.0/log/lsf_cluster_7.0.license.acct file
for details. Please contact Platform Support at support@platform.com for
information about getting additional licenses.
```

## Default

24 hours

## See also

- `LSF_LICENSE_ACCT_PATH`
- `LSF_LOGDIR`
- `lsf.cluster_name.license.acct`
- `bld.license.acct`

## LSF\_LIM\_API\_NTRIES

### Syntax

**LSF\_LIM\_API\_NTRIES**=*integer*

### Description

Defines the number of times LSF commands will retry to communicate with the LIM API when LIM is not available. LSF\_LIM\_API\_NTRIES is ignored by LSF and EGO daemons and EGO commands. The LSF\_LIM\_API\_NTRIES environment variable, overrides the value of LSF\_LIM\_API\_NTRIES in `lsf.conf`.

### Valid values

1 to 65535

### Default

Not defined. LIM API exits without retrying.

## LSF\_LIM\_DEBUG

### Syntax

**LSF\_LIM\_DEBUG**=1 | 2

### Description

Sets LSF to debug mode.

If LSF\_LIM\_DEBUG is defined, LIM operates in single user mode. No security checking is performed, so LIM should not run as root.

LIM does not look in the services database for the LIM service port number. Instead, it uses port number 36000 unless LSF\_LIM\_PORT has been defined.

Specify 1 for this parameter unless you are testing LSF.

### Valid values

LSF\_LIM\_DEBUG=1

LIM runs in the background with no associated control terminal.

LSF\_LIM\_DEBUG=2

LIM runs in the foreground and prints error messages to `tty`.

### EGO parameter

EGO\_LIM\_DEBUG

### Default

Not defined

## See also

LSF\_RES\_DEBUG, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK,  
LSF\_LOGDIR

## LSF\_LIM\_IGNORE\_CHECKSUM

### Syntax

**LSF\_LIM\_IGNORE\_CHECKSUM=y | Y**

### Description

Configure LSF\_LIM\_IGNORE\_CHECKSUM=Y to ignore warning messages logged to `lim` log files on non-master hosts.

When LSF\_MASTER\_LIST is set, `lsadm in reconfi g` only restarts master candidate hosts (for example, after adding or removing hosts from the cluster). This can cause superfluous warning messages like the following to be logged in the `lim` log files for non-master hosts because `lim` on these hosts are not restarted after configuration change:

```
Aug 26 13:47:35 2006 9746 4 7.0 xdr_loadvector: Sender <10.225.36.46:9999>  
has a different configuration
```

### Default

Not defined.

## See also

LSF\_MASTER\_LIST

## LSF\_LIM\_PORT, LSF\_RES\_PORT, LSB\_MBD\_PORT, LSB\_SBD\_PORT

### Syntax

**LSF\_LIM\_PORT=*port\_number***

### Description

TCP service ports to use for communication with the LSF daemons.

If port parameters are not defined, LSF obtains the port numbers by looking up the LSF service names in the `/etc/services` file or the NIS (UNIX). If it is not possible to modify the services database, you can define these port parameters to set the port numbers.

## EGO parameter

EGO\_LIM\_PORT

### Default

On UNIX, the default is to get port numbers from the services database.

On Windows, these parameters are mandatory.

Default port number values are:

- LSF\_LIM\_PORT=7869
- LSF\_RES\_PORT=6878
- LSB\_MBD\_PORT=6881
- LSB\_SBD\_PORT=6882

## LSF\_LOAD\_USER\_PROFILE

### Syntax

LSF\_LOAD\_USER\_PROFILE=local | roaming

### Description

When running jobs on Windows hosts, you can specify whether a user profile should be loaded. Use this parameter if you have jobs that need to access user-specific resources associated with a user profile.

Local and roaming user profiles are Windows features. For more information about them, check Microsoft documentation.

- Local: LSF loads the Windows user profile from the local execution machine (the host on which the job runs).

---

#### Note:

If the user has logged onto the machine before, the profile of that user is used. If not, the profile for the default user is used

- Roaming: LSF loads a roaming user profile if it has been set up. If not, the local user profile is loaded instead.

### Default

Not defined. No user profiles are loaded when jobs run on Windows hosts.

## LSF\_LOCAL\_RESOURCES

### Syntax

LSF\_LOCAL\_RESOURCES="*resource ...*"

### Description

Defines instances of local resources residing on the slave host.

- For numeric resources, defined name-value pairs:  
" [resourcemap *value*\**resource\_name*] "
- For Boolean resources, the value is the resource name in the form:  
" [resource *resource\_name*] "

When the slave host calls the master host to add itself, it also reports its local resources. The local resources to be added must be defined in `lsf.shared`.

If the same resource is already defined in `lsf.shared` as default or all, it cannot be added as a local resource. The shared resource overrides the local one.

---

#### Tip:

LSF\_LOCAL\_RESOURCES is usually set in the `slave.config` file during installation. If LSF\_LOCAL\_RESOURCES are already defined in a local `lsf.conf` on the slave host, `lsfinstall` does not add resources you define in LSF\_LOCAL\_RESOURCES in `slave.config`. You should not have duplicate LSF\_LOCAL\_RESOURCES entries in `lsf.conf`. If local resources are defined more than once, only the last definition is valid.

---

### Important:

Resources must already be mapped to hosts in the ResourceMap section of `lsf.cluster.cluster_name`. If the ResourceMap section does not exist, local resources are not added.

---

## Example

```
LSF_LOCAL_RESOURCES="[resourcemap 1*verilog] [resource linux]"
```

## EGO parameter

EGO\_LOCAL\_RESOURCES

## Default

Not defined

## LSF\_LOG\_MASK

## Syntax

**LSF\_LOG\_MASK**=*message\_log\_level*

## Description

Specifies the logging level of error messages for LSF daemons, except LIM, which is controlled by Platform EGO.

For example:

```
LSF_LOG_MASK=LOG_DEBUG
```

If EGO is enabled in the LSF cluster, and EGO\_LOG\_MASK is not defined, LSF uses the value of LSF\_LOG\_MASK for LIM, PIM, and MELIM. EGO `vemkd` and `pem` components continue to use the EGO default values. If EGO\_LOG\_MASK is defined, and EGO is enabled, then EGO value is taken.

To specify the logging level of error messages for LSF commands, use LSF\_CMD\_LOG\_MASK. To specify the logging level of error messages for LSF batch commands, use LSB\_CMD\_LOG\_MASK.

On UNIX, this is similar to `syslog`. All messages logged at the specified level or higher are recorded; lower level messages are discarded. The LSF\_LOG\_MASK value can be any log priority symbol that is defined in `syslog.h` (see `syslog`).

The log levels in order from highest to lowest are:

- LOG\_EMERG
- LOG\_ALERT
- LOG\_CRIT
- LOG\_ERR
- LOG\_WARNING
- LOG\_NOTICE
- LOG\_INFO
- LOG\_DEBUG
- LOG\_DEBUG1
- LOG\_DEBUG2
- LOG\_DEBUG3

The most important LSF log messages are at the LOG\_ERR or LOG\_WARNING level. Messages at the LOG\_INFO and LOG\_DEBUG level are only useful for debugging.

Although message log level implements similar functionality to UNIX syslog, there is no dependency on UNIX syslog. It works even if messages are being logged to files instead of syslog.

LSF logs error messages in different levels so that you can choose to log all messages, or only log messages that are deemed critical. The level specified by LSF\_LOG\_MASK determines which messages are recorded and which are discarded. All messages logged at the specified level or higher are recorded, while lower level messages are discarded.

For debugging purposes, the level LOG\_DEBUG contains the fewest number of debugging messages and is used for basic debugging. The level LOG\_DEBUG3 records all debugging messages, and can cause log files to grow very large; it is not often used. Most debugging is done at the level LOG\_DEBUG2.

In versions earlier than LSF 4.0, you needed to restart the daemons after setting LSF\_LOG\_MASK in order for your changes to take effect.

LSF 4.0 implements dynamic debugging, which means you do not need to restart the daemons after setting a debugging environment variable.

## EGO parameter

EGO\_LOG\_MASK

## Default

LOG\_WARNING

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD, LSB\_DEBUG\_NQS, LSB\_TIME\_CMD, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_DEBUG\_LIM, LSB\_DEBUG\_MBD, LSF\_DEBUG\_RES, LSB\_DEBUG\_SBD, LSB\_DEBUG\_SCH, LSF\_LOG\_MASK, LSF\_LOGDIR, LSF\_TIME\_CMD

## LSF\_LOG\_MASK\_WIN

### Syntax

**LSF\_LOG\_MASK\_WIN**=*message\_log\_level*

## Description

Allows you to reduce the information logged to the LSF Windows event log files. Messages of lower severity than the specified level are discarded.

For all LSF files, the types of messages saved depends on LSF\_LOG\_MASK, so the threshold for the Windows event logs is either LSF\_LOG\_MASK or LSF\_LOG\_MASK\_WIN, whichever is higher. LSF\_LOG\_MASK\_WIN is ignored if LSF\_LOG\_MASK is set to a higher level.

The LSF event log files for Windows are:

- `lim.log. host_name`
- `res.log. host_name`
- `sbatchd.log. host_name`
- `mbatchd.log. host_name`
- `pi m.log. host_name`

The log levels you can specify for this parameter, in order from highest to lowest, are:

- LOG\_ERR
- LOG\_WARNING
- LOG\_INFO
- LOG\_NONE (LSF does not log Windows events)

## Default

LOG\_ERR

## See also

LSF\_LOG\_MASK

## LSF\_LOGDIR

### Syntax

**LSF\_LOGDIR**=*directory*

## Description

Defines the LSF system log file directory. Error messages from all servers are logged into files in this directory. To effectively use debugging, set LSF\_LOGDIR to a directory such as `/tmp`. This can be done in your own environment from the shell or in `lsf.conf`.

## Windows

LSF\_LOGDIR is required on Windows if you wish to enable logging.

You must also define LSF\_LOGDIR\_USE\_WIN\_REG=*n*.

If you define LSF\_LOGDIR without defining LSF\_LOGDIR\_USE\_WIN\_REG=*n*, LSF logs error messages into files in the default local directory specified in one of the following Windows registry keys:

- On Windows 2000, Windows XP, and Windows 2003:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Platform Computing Corporation\LSF
\cluster_name\LSF_LOGDIR
```

- On Windows XP x64 and Windows 2003 x64:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Platform Computing Corporation\LSF
\cluster_name\LSF_LOGDIR
```

If a server is unable to write in the LSF system log file directory, LSF attempts to write to the following directories in the following order:

- LSF\_TMPDIR if defined
- %TMP% if defined
- %TEMP% if defined
- System directory, for example, c: \windows

## UNIX

If a server is unable to write in this directory, the error logs are created in /tmp on UNIX.

If LSF\_LOGDIR is not defined, syslog is used to log everything to the system log using the LOG\_DAEMON facility. The syslog facility is available by default on most UNIX systems. The /etc/syslog.conf file controls the way messages are logged and the files they are logged to. See the man pages for the syslogd daemon and the syslog function for more information.

## Default

Not defined. On UNIX, log messages go to syslog. On Windows, no logging is performed.

## See also

LSB\_CMD\_LOG\_MASK, LSB\_CMD\_LOGDIR, LSB\_DEBUG, LSB\_DEBUG\_CMD, LSB\_TIME\_CMD, LSF\_CMD\_LOGDIR, LSF\_CMD\_LOG\_MASK, LSF\_LOG\_MASK, LSF\_LOGDIR\_USE\_WIN\_REG, LSF\_TIME\_CMD

## Files

- lim.log. *host\_name*
- res.log. *host\_name*
- sbatchd.log. *host\_name*
- sbatchdc.log. *host\_name* (when LSF\_DAEMON\_WRAP=Y)
- mbatchd.log. *host\_name*
- eventd.log. *host\_name*
- pim.log. *host\_name*

## LSF\_LOGDIR\_USE\_WIN\_REG

### Syntax

**LSF\_LOGDIR\_USE\_WIN\_REG=n | N**

### Description

Windows only.

If set, LSF logs error messages into files in the directory specified by LSF\_LOGDIR in lsf.conf.

Use this parameter to enable LSF to save log files in a different location from the default local directory specified in the Windows registry.

If not set, or if set to any value other than N or n, LSF logs error messages into files in the default local directory specified in one of the following Windows registry keys:

- On Windows 2000, Windows XP, and Windows 2003:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Platform Computing Corporation\LSF
\cluster_name\LSF_LOGDIR
```

- On Windows XP x64 and Windows 2003 x64:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Platform Computing Corporation\LSF
\cluster_name\LSF_LOGDIR
```

## Default

Not set.

LSF uses the default local directory specified in the Windows registry.

## See also

LSF\_LOGDIR

## LSF\_LOGFILE\_OWNER

### Syntax

```
LSF_LOGFILE_OWNER="user_name"
```

### Description

Specifies an owner for the LSF log files other than the default, the owner of `lsf.conf`. To specify a Windows user account, include the domain name in uppercase letters (`DOMAIN_NAME\user_name`).

## Default

Not set. The LSF Administrator with root privileges is the owner of LSF log files.

## LSF\_LSLOGIN\_SSH

### Syntax

```
LSF_LSLOGIN_SSH=YES | yes
```

### Description

Enables SSH to secure communication between hosts and during job submission.

SSH is used when running any of the following:

- Remote log on to a lightly loaded host (`lsl ogi n`)
- An interactive job (`bsub -IS | -ISp | ISs`)
- An X-window job (`bsub -IX`)
- An externally submitted job that is interactive or X-window (`esub`)

## Default

Not set. LSF uses `rlogin` to authenticate users.

## LSF\_MACHDEP

### Syntax

**LSF\_MACHDEP**=*directory*

### Description

Specifies the directory in which machine-dependent files are installed. These files cannot be shared across different types of machines.

In clusters with a single host type, LSF\_MACHDEP is usually the same as LSF\_INDEP. The machine dependent files are the user commands, daemons, and libraries. You should not need to modify this parameter.

As shown in the following list, LSF\_MACHDEP is incorporated into other LSF variables.

- LSF\_BINDIR=\$LSF\_MACHDEP/bin
- LSF\_LIBDIR=\$LSF\_MACHDEP/lib
- LSF\_SERVERDIR=\$LSF\_MACHDEP/etc
- XLSF\_UIDDIR=\$LSF\_MACHDEP/lib/uid

### Default

`/usr/share/lsf`

### See also

LSF\_INDEP

## LSF\_MANDIR

### Syntax

**LSF\_MANDIR**=*directory*

### Description

Directory under which all man pages are installed.

The man pages are placed in the man1, man3, man5, and man8 subdirectories of the LSF\_MANDIR directory. This is created by the LSF installation process, and you should not need to modify this parameter.

Man pages are installed in a format suitable for BSD-style man commands.

For most versions of UNIX and Linux, you should add the directory LSF\_MANDIR to your MANPATH environment variable. If your system has a man command that does not understand MANPATH, you should either install the man pages in the /usr/man directory or get one of the freely available man programs.

### Default

`LSF_INDEP/man`

## LSF\_MASTER\_LIST

### Syntax

```
LSF_MASTER_LIST="host_name ..."
```

### Description

Required. Defines a list of hosts that are candidates to become the master host for the cluster.

Listed hosts must be defined in `lsf.cluster.cluster_name`.

Host names are separated by spaces.

---

#### Tip:

On UNIX and Linux, master host candidates should share LSF configuration and binaries. On Windows, configuration files are shared, but not binaries.

---

Starting in LSF 7, `LSF_MASTER_LIST` *must* be defined in `lsf.conf`.

If EGO is enabled, `LSF_MASTER_LIST` can only be defined in `lsf.conf`. `EGO_MASTER_LIST` can only be defined in `ego.conf`. `EGO_MASTER_LIST` cannot be defined in `lsf.conf`. `LSF_MASTER_LIST` cannot be defined in `ego.conf`.

LIM reads `EGO_MASTER_LIST` wherever it is defined. If both `LSF_MASTER_LIST` and `EGO_MASTER_LIST` are defined, the value of `EGO_MASTER_LIST` in `ego.conf` is taken. To avoid errors, you should make sure that the value of `LSF_MASTER_LIST` matches the value of `EGO_MASTER_LIST`, or define only `EGO_MASTER_LIST`.

If EGO is disabled, `ego.conf` not loaded and the value of `LSF_MASTER_LIST` defined in `lsf.conf` is taken.

When you run `lsadm n reconfi g` to reconfigure the cluster, only the master LIM candidates read `lsf.shared` and `lsf.cluster.cluster_name` to get updated information. The elected master LIM sends configuration information to slave LIMs.

If you have a large number of non-master hosts, you should configure `LSF_LIM_IGNORE_CHECKSUM=Y` to ignore warning messages like the following logged to `lim log` files on non-master hosts.

```
Aug 26 13:47:35 2006 9746 4 7.0 xdr_loadvector: Sender <10.225.36.46:9999>
has a different configuration
```

## Interaction with LSF\_SERVER\_HOSTS

You can use the same list of hosts, or a subset of the master host list defined in `LSF_MASTER_LIST`, in `LSF_SERVER_HOSTS`. If you include the primary master host in `LSF_SERVER_HOSTS`, you should define it as the last host of the list.

If `LSF_ADD_CLIENTS` is defined in `install.conf` at installation, `lsfinstall` automatically appends the hosts in `LSF_MASTER_LIST` to the list of hosts in `LSF_SERVER_HOSTS` so that the primary master host is last. For example:

```
LSF_MASTER_LIST="lsfmaster hostE"
```

```
LSF_SERVER_HOSTS="hostB hostC hostD hostE lsfmaster"
```

The value of `LSF_SERVER_HOSTS` is not changed during upgrade.

## EGO parameter

EGO\_MASTER\_LIST

### Default

Defined at installation

### See also

LSF\_LIM\_IGNORE\_CHECKSUM

## LSF\_MASTER\_NSLOOKUP\_TIMEOUT

### Syntax

**LSF\_MASTER\_NSLOOKUP\_TIMEOUT**=*time\_milliseconds*

### Description

Timeout in milliseconds that the master LIM waits for DNS host name lookup.

If LIM spends a lot of time calling DNS to look up a host name, LIM appears to hang.

This parameter is used by master LIM only. Only the master LIM detects this parameter and enable the DNS lookup timeout.

### Default

Not defined. No timeout for DNS lookup

### See also

LSF\_LIM\_IGNORE\_CHECKSUM

## LSF\_MAX\_TRY\_ADD\_HOST

### Syntax

**LSF\_MAX\_TRY\_ADD\_HOST**=*integer*

### Description

When a slave LIM on a dynamically added host sends an add host request to the master LIM, but master LIM cannot add the host for some reason, the slave LIM tries again.

LSF\_MAX\_TRY\_ADD\_HOST specifies how many times the slave LIM retries the add host request before giving up.

### Default

20

## LSF\_MC\_NON\_PRIVILEGED\_PORTS

### Syntax

**LSF\_MC\_NON\_PRIVILEGED\_PORTS**=*y* | *Y*

## Description

MultiCluster only. If this parameter is enabled in one cluster, it must be enabled in all clusters. Specify Y to make LSF daemons use non-privileged ports for communication across clusters.

## Compatibility

This disables privileged port daemon authentication, which is a security feature. If security is a concern, you should use `eauth` for LSF daemon authentication (see `LSF_AUTH_DAEMONS` in `lsf.conf`).

## Default

Not defined. LSF daemons use privileged port authentication

## LSF\_MONITOR\_LICENSE\_TOOL

### Syntax

`LSF_MONITOR_LICENSE_TOOL=y | Y`

### Description

Specify Y to enable data collection by `lim` for the command option `lsadmin lsflic`.

### Default

Not defined. `lim` ignores requests from `lsadmin`, closing the channel.

## LSF\_MISC

### Syntax

`LSF_MISC=directory`

### Description

Directory in which miscellaneous machine independent files, such as example source programs and scripts, are installed.

### Default

`LSF_CONFDIR/misc`

## LSF\_NIOS\_DEBUG

### Syntax

`LSF_NIOS_DEBUG=1`

### Description

Turns on NIOS debugging for interactive jobs.

If `LSF_NIOS_DEBUG=1`, NIOS debug messages are written to standard error.

This parameter can also be defined as an environment variable.

When `LSF_NIOS_DEBUG` and `LSF_CMD_LOGDIR` are defined, NIOS debug messages are logged in `ni os. log. host_name` in the location specified by `LSF_CMD_LOGDIR`.

If `LSF_NIOS_DEBUG` is defined, and the directory defined by `LSF_CMD_LOGDIR` is inaccessible, NIOS debug messages are logged to `/tmp/ni os. log. host_name` instead of `stderr`.

On Windows, NIOS debug messages are also logged to the temporary directory.

## Default

Not defined

## See also

`LSF_CMD_LOGDIR`, `LSF_CMD_LOG_MASK`, `LSF_LOG_MASK`, `LSF_LOGDIR`

# LSF\_NIOS\_JOBSTATUS\_INTERVAL

## Syntax

`LSF_NIOS_JOBSTATUS_INTERVAL=time_minutes`

## Description

Applies only to interactive batch jobs.

Time interval at which NIOS polls `mbatchd` to check if a job is still running. Used to retrieve a job's exit status in the case of an abnormal exit of NIOS, due to a network failure for example.

Use this parameter if you run interactive jobs and you have scripts that depend on an exit code being returned.

When this parameter is not defined and a network connection is lost, `mbatchd` cannot communicate with NIOS and the return code of a job is not retrieved.

When this parameter is defined, before exiting, NIOS polls `mbatchd` on the interval defined by `LSF_NIOS_JOBSTATUS_INTERVAL` to check if a job is still running. NIOS continues to poll `mbatchd` until it receives an exit code or `mbatchd` responds that the job does not exist (if the job has already been cleaned from memory for example).

If an exit code cannot be retrieved, NIOS generates an error message and the code -11.

## Valid values

Any integer greater than zero

## Default

Not defined

## Notes

Set this parameter to large intervals such as 15 minutes or more so that performance is not negatively affected if interactive jobs are pending for too long. NIOS always calls `mbatchd` on the defined interval to confirm that a job is still pending and this may add load to `mbatchd`.

## See also

Environment variable `LSF_NIOS_PEND_TIMEOUT`

## LSF\_NIOS\_MAX\_TASKS

### Syntax

`LSF_NIOS_MAX_TASKS=integer`

### Description

Specifies the maximum number of NIOS tasks.

### Default

Not defined

## LSF\_NIOS\_RES\_HEARTBEAT

### Syntax

`LSF_NIOS_RES_HEARTBEAT=time_minutes`

### Description

Applies only to interactive non-parallel batch jobs.

Defines how long NIOS waits before sending a message to RES to determine if the connection is still open.

Use this parameter to ensure NIOS exits when a network failure occurs instead of waiting indefinitely for notification that a job has been completed. When a network connection is lost, RES cannot communicate with NIOS and as a result, NIOS does not exit.

When this parameter is defined, if there has been no communication between RES and NIOS for the defined period of time, NIOS sends a message to RES to see if the connection is still open. If the connection is no longer available, NIOS exits.

### Valid values

Any integer greater than zero

### Default

Not defined

### Notes

The time you set this parameter to depends how long you want to allow NIOS to wait before exiting. Typically, it can be a number of hours or days. Too low a number may add load to the system.

## LSF\_NON\_PRIVILEGED\_PORTS

### Syntax

`LSF_NON_PRIVILEGED_PORTS=y | Y`

## Description

Disables privileged ports usage.

By default, LSF daemons and clients running under root account use privileged ports to communicate with each other. Without `LSF_NON_PRIVILEGED_PORTS` defined, and if `LSF_AUTH` is not defined in `lsf.conf`, LSF daemons check privileged port of request message to do authentication.

If `LSF_NON_PRIVILEGED_PORTS=Y` is defined, LSF clients (LSF commands and daemons) do not use privileged ports to communicate with daemons and LSF daemons do not check privileged ports of incoming requests to do authentication.

## LSF\_PAM\_APPL\_CHKPNT

### Syntax

`LSF_PAM_APPL_CHKPNT=Y | N`

### Description

When set to Y, allows PAM to function together with application checkpointing support.

### Default

Y

## LSF\_PAM\_CLEAN\_JOB\_DELAY

### Syntax

`LSF_PAM_CLEAN_JOB_DELAY=time_seconds`

### Description

The number of seconds LSF waits before killing a parallel job with failed tasks. Specifying `LSF_PAM_CLEAN_JOB_DELAY` implies that if any parallel tasks fail, the entire job should exit without running the other tasks in the job. The job is killed if any task exits with a non-zero exit code.

Specify a value greater than or equal to zero (0).

Applies only to PAM jobs.

### Default

Undefined: LSF kills the job immediately

## LSF\_PAM\_HOSTLIST\_USE

### Syntax

`LSF_PAM_HOSTLIST_USE=unique`

### Description

Used to start applications that use both OpenMP and MPI.

lsf.conf

## Valid values

```
unique
```

## Default

Not defined

## Notes

At job submission, LSF reserves the correct number of processors and PAM starts only 1 process per host. For example, to reserve 32 processors and run on 4 processes per host, resulting in the use of 8 hosts:

```
bsub -n 32 -R "span[ptile=4]" pam yourOpenMPJob
```

## Where defined

This parameter can alternatively be set as an environment variable. For example:

```
setenv LSF_PAM_HOSTLIST_USE unique
```

## LSF\_PAM\_PLUGINDIR

### Syntax

```
LSF_PAM_PLUGINDIR=path
```

### Description

The path to libpamvcl.so. Used with Platform LSF HPC.

### Default

Path to LSF\_LIBDIR

## LSF\_PAM\_USE\_ASH

### Syntax

```
LSF_PAM_USE_ASH=y | Y
```

### Description

Enables LSF to use the SGI IRIX Array Session Handles (ASH) to propagate signals to the parallel jobs.

See the IRIX system documentation and the array\_session(5) man page for more information about array sessions.

### Default

Not defined

## LSF\_PIM\_INFODIR

### Syntax

```
LSF_PIM_INFODIR=path
```

## Description

The path to where PIM writes the `pi m. i n f o. host_name` file.

Specifies the path to where the process information is stored. The process information resides in the file `pi m. i n f o. host_name`. The PIM also reads this file when it starts so that it can accumulate the resource usage of dead processes for existing process groups.

## EGO parameter

EGO\_PIM\_INFODIR

## Default

Not defined. The system uses `/tmp`.

## LSF\_PIM\_SLEEPTIME

### Syntax

**LSF\_PIM\_SLEEPTIME**=*time\_seconds*

## Description

The reporting period for PIM.

PIM updates the process information every 15 minutes unless an application queries this information. If an application requests the information, PIM updates the process information every `LSF_PIM_SLEEPTIME` seconds. If the information is not queried by any application for more than 5 minutes, the PIM reverts back to the 15 minute update period.

## EGO parameter

EGO\_PIM\_SLEEPTIME

## Default

15

## LSF\_PIM\_SLEEPTIME\_UPDATE

### Syntax

**LSF\_PIM\_SLEEPTIME\_UPDATE**=*y* | *n*

## Description

UNIX only.

Use this parameter to improve job throughput and reduce a job's start time if there are many jobs running simultaneously on a host. This parameter reduces communication traffic between `sbatchd` and PIM on the same host.

When this parameter is not defined or set to `n`, `sbatchd` queries PIM as needed for job process information.

When this parameter is defined, `sbatchd` does not query PIM immediately as it needs information; `sbatchd` only queries PIM every `LSF_PIM_SLEEPTIME` seconds.

## Limitations

When this parameter is defined:

- sbatchd may be intermittently unable to retrieve process information for jobs whose run time is smaller than LSF\_PIM\_SLEEPTIME.
- It may take longer to view resource usage with `bj obs -l`.

## EGO parameter

EGO\_PIM\_SLEEPTIME\_UPDATE

## Default

Not defined

## LSF\_POE\_TIMEOUT\_BIND

### Syntax

**LSF\_POE\_TIMEOUT\_BIND**=*time\_seconds*

### Description

Specifies the time in seconds for the `poe_w` wrapper to keep trying to set up a server socket to listen on.

`poe_w` is the wrapper for the IBM `poe` driver program.

LSF\_POE\_TIMEOUT\_BIND can also be set as an environment variable for `poe_w` to read.

### Default

120 seconds

## LSF\_POE\_TIMEOUT\_SELECT

### Syntax

**LSF\_POE\_TIMEOUT\_SELECT**=*time\_seconds*

### Description

Specifies the time in seconds for the `poe_w` wrapper to wait for connections from the `pmd_w` wrapper. `pmd_w` is the wrapper for `pmd` (IBM PE Partition Manager Daemon).

LSF\_POE\_TIMEOUT\_SELECT can also be set as an environment variable for `poe_w` to read.

### Default

160 seconds

## LSF\_RES\_ACCT

### Syntax

**LSF\_RES\_ACCT**=*time\_milliseconds* | 0

## Description

If this parameter is defined, RES logs information for completed and failed tasks by default (see `lsf.acct`).

The value for `LSF_RES_ACCT` is specified in terms of consumed CPU time (milliseconds). Only tasks that have consumed more than the specified CPU time are logged.

If this parameter is defined as `LSF_RES_ACCT=0`, then all tasks are logged.

For those tasks that consume the specified amount of CPU time, RES generates a record and appends the record to the task log file `lsf.acct.host_name`. This file is located in the `LSF_RES_ACCTDIR` directory.

If this parameter is not defined, the LSF administrator must use the `lsadmi n` command (see `lsadmi n`) to turn task logging on after RES has started.

## Default

Not defined

## See also

`LSF_RES_ACCTDIR`

## LSF\_RES\_ACCTDIR

## Syntax

`LSF_RES_ACCTDIR=directory`

## Description

The directory in which the RES task log file `lsf.acct.host_name` is stored.

If `LSF_RES_ACCTDIR` is not defined, the log file is stored in the `/tmp` directory.

## Default

(UNIX) `/tmp`

(Windows) `C:\temp`

## See also

`LSF_RES_ACCT`

## LSF\_RES\_ACTIVE\_TIME

## Syntax

`LSF_RES_ACTIVE_TIME=time_seconds`

## Description

Time in seconds before LIM reports that RES is down.

## Minimum value

10 seconds

## Default

90 seconds

## LSF\_RES\_CLIENT\_TIMEOUT

### Syntax

**LSF\_RES\_CLIENT\_TIMEOUT**=*time\_minutes*

### Description

Specifies in minutes how long an application RES waits for a new task before exiting.

---

**Caution:**

If you use the LSF API to run remote tasks and you define this parameter with timeout, the remote execution of the new task fails (for example, `ls_rtask()`).

---

### Default

The parameter is not set; the application RES waits indefinitely for new task to come until client tells it to quit.

## LSF\_RES\_CONNECT\_RETRY

### Syntax

**LSF\_RES\_CONNECT\_RETRY**=*integer* / 0

### Description

The number of attempts by RES to reconnect to NIOS.

If `LSF_RES_CONNECT_RETRY` is not defined, the default value is used.

### Default

0

### See also

`LSF_NIOS_RES_HEARTBEAT`

## LSF\_RES\_DEBUG

### Syntax

**LSF\_RES\_DEBUG**=1 / 2

### Description

Sets RES to debug mode.

If `LSF_RES_DEBUG` is defined, the Remote Execution Server (RES) operates in single user mode. No security checking is performed, so RES should not run as root. RES does not look in the services database for the RES service port number. Instead, it uses port number 36002 unless `LSF_RES_PORT` has been defined.

Specify 1 for this parameter unless you are testing RES.

## Valid values

`LSF_RES_DEBUG=1`

RES runs in the background with no associated control terminal.

`LSF_RES_DEBUG=2`

RES runs in the foreground and prints error messages to `tty`.

## Default

Not defined

## See also

`LSF_LIM_DEBUG`, `LSF_CMD_LOGDIR`, `LSF_CMD_LOG_MASK`, `LSF_LOG_MASK`,  
`LSF_LOGDIR`

## LSF\_RES\_PORT

See `LSF_LIM_PORT`, `LSF_RES_PORT`, `LSB_MBD_PORT`, `LSB_SBD_PORT`.

## LSF\_RES\_RLIMIT\_UNLIM

### Syntax

`LSF_RES_RLIMIT_UNLIM=cpu | fsize | data | stack | core | vmem`

### Description

By default, RES sets the hard limits for a remote task to be the same as the hard limits of the local process. This parameter specifies those hard limits which are to be set to unlimited, instead of inheriting those of the local process.

Valid values are `cpu`, `fsize`, `data`, `stack`, `core`, and `vmem`, for CPU, file size, data size, stack, core size, and virtual memory limits, respectively.

### Example

The following example sets the CPU, core size, and stack hard limits to be unlimited for all remote tasks:

```
LSF_RES_RLIMIT_UNLIM="cpu core stack"
```

### Default

Not defined

## LSF\_RES\_TIMEOUT

### Syntax

**LSF\_RES\_TIMEOUT**=*time\_seconds*

### Description

Timeout when communicating with RES.

### Default

15

## LSF\_ROOT\_REX

### Syntax

**LSF\_ROOT\_REX**=*local*

### Description

UNIX only.

Allows root remote execution privileges (subject to identification checking) on remote hosts, for both interactive and batch jobs. Causes RES to accept requests from the superuser (root) on remote hosts, subject to identification checking.

If LSF\_ROOT\_REX is not defined, remote execution requests from user root are refused.

### Theory

Sites that have separate root accounts on different hosts within the cluster should not define LSF\_ROOT\_REX. Otherwise, this setting should be based on local security policies.

The `lsf.conf` file is host-type specific and not shared across different platforms. You must make sure that `lsf.conf` for all your host types are changed consistently.

### Default

Not defined. Root execution is not allowed.

### See also

LSF\_TIME\_CMD, LSF\_AUTH

## LSF\_RSH

### Syntax

**LSF\_RSH**=*command* [*command\_options*]

### Description

Specifies shell commands to use when the following LSF commands require remote execution:

- `badmi n hstart up`
- `bpeek`

- `lsadmin limstartup`
- `lsadmin resstartup`
- `lsfrestart`
- `lsfshutdown`
- `lsfstartup`
- `lsrcpu`

By default, `rsh` is used for these commands. Use `LSF_RSH` to enable support for `ssh`.

## EGO parameter

`EGO_RSH`

## Default

Not defined

## Example

To use an `ssh` command before trying `rsh` for LSF commands, specify:

```
LSF_RSH="ssh -o 'PasswordAuthentication no' -o 'StrictHostKeyChecking no' "
```

`ssh` options such as `PasswordAuthentication` and `StrictHostKeyChecking` can also be configured in the global `SSH_ETC/ssh_config` file or `$HOME/.ssh/config`.

## See also

`ssh`, `ssh_config`

## LSF\_SECUREDIR

### Syntax

`LSF_SECUREDIR=path`

### Description

Windows only; mandatory if using `lsf.sudoers`.

Path to the directory that contains the file `lsf.sudoers` (shared on an NTFS file system).

## LSF\_SERVER\_HOSTS

### Syntax

`LSF_SERVER_HOSTS="host_name ..."`

### Description

Defines one or more server hosts that the client should contact to find a Load Information Manager (LIM). LSF server hosts are hosts that run LSF daemons and provide loading-sharing services. Client hosts are hosts that only run LSF commands or applications but do not provide services to any hosts.

---

#### **Important:**

`LSF_SERVER_HOSTS` is required for non-shared slave hosts.

Use this parameter to ensure that commands execute successfully when no LIM is running on the local host, or when the local LIM has just started. The client contacts the LIM on one of the LSF\_SERVER\_HOSTS and execute the command, provided that at least one of the hosts defined in the list has a LIM that is up and running.

If LSF\_SERVER\_HOSTS is not defined, the client tries to contact the LIM on the local host.

The host names in LSF\_SERVER\_HOSTS must be enclosed in quotes and separated by white space. For example:

```
LSF_SERVER_HOSTS="hostA hostD hostB"
```

The parameter string can include up to 4094 characters for UNIX or 255 characters for Windows.

## Interaction with LSF\_MASTER\_LIST

Starting in LSF 7, LSF\_MASTER\_LIST must be defined in `lsf.conf`. You can use the same list of hosts, or a subset of the master host list, in LSF\_SERVER\_HOSTS. If you include the primary master host in LSF\_SERVER\_HOSTS, you should define it as the last host of the list.

If LSF\_ADD\_CLIENTS is defined in `install.config` at installation, `lsfinstall` automatically appends the hosts in LSF\_MASTER\_LIST to the list of hosts in LSF\_SERVER\_HOSTS so that the primary master host is last. For example:

```
LSF_MASTER_LIST="lsfmaster hostE"
```

```
LSF_SERVER_HOSTS="hostB hostC hostD hostE lsfmaster"
```

```
LSF_ADD_CLIENTS="clientHostA"
```

The value of LSF\_SERVER\_HOSTS is not changed during upgrade.

## Default

Not defined

## See also

LSF\_MASTER\_LIST

## LSF\_SERVERDIR

## Syntax

```
LSF_SERVERDIR=directory
```

## Description

Directory in which all server binaries and shell scripts are installed.

These include `lim`, `res`, `nios`, `sbatchd`, `mbatchd`, and `mbschd`. If you use `elim`, `eauth`, `eexec`, `esub`, etc, they are also installed in this directory.

## Default

LSF\_MACHDEP/etc

## See also

LSB\_ECHKPNT\_METHOD\_DIR

## LSF\_SHELL\_AT\_USERS

### Syntax

```
LSF_SHELL_AT_USERS="user_name user_name ..."
```

### Description

Applies to `l st csh` only. Specifies users who are allowed to use `@` for host redirection. Users not specified with this parameter cannot use host redirection in `l st csh`. To specify a Windows user account, include the domain name in uppercase letters (`DOMAIN_NAME\user_name`).

If this parameter is not defined, all users are allowed to use `@` for host redirection in `l st csh`.

### Default

Not defined

## LSF\_SHIFT\_JIS\_INPUT

### Syntax

```
LSF_SHIFT_JIS_INPUT=y | n
```

### Description

Enables LSF to accept Shift-JIS character encoding for job information (for example, user names, queue names, job names, job group names, project names, commands and arguments, `esub` parameters, external messages, etc.)

### Default

n

## LSF\_SLURM\_DISABLE\_CLEANUP

### Syntax

```
LSF_SLURM_DISABLE_CLEANUP=y | Y
```

### Description

Disables cleanup of non-LSF jobs running in a SLURM LSF partition on a SLURM cluster.

By default, only LSF jobs are allowed to run within a SLURM LSF partition. LSF periodically cleans up any jobs submitted outside of LSF. This clean up period is defined through `LSB_RLA_UPDATE`.

For example, the following `srun` job is not submitted through LSF, so it is terminated:

```
srun -n 4 -p lsf sleep 100000
```

```
srun: error: n13: task[0-1]: Terminated
```

```
srun: Terminating job
```

If `LSF_SLURM_DISABLE_CLEANUP=Y` is set, this job would be allowed to run.

## Default

Not defined

## LSF\_SLURM\_TMPDIR

### Syntax

**LSF\_SLURM\_TMPDIR=***path*

### Description

Specifies the LSF HPC tmp directory for SLURM clusters. The default LSF\_TMPDIR /tmp cannot be shared across nodes, so LSF\_SLURM\_TMPDIR must specify a path that is accessible on all SLURM nodes.

## Default

/hptc\_cluster/lsf/tmp

## LSF\_STRICT\_CHECKING

### Syntax

**LSF\_STRICT\_CHECKING=Y**

### Description

If set, enables more strict checking of communications between LSF daemons and between LSF commands and daemons when LSF is used in an untrusted environment, such as a public network like the Internet.

If you enable this parameter, you must enable it in the entire cluster, as it affects all communications within LSF. If it is used in a MultiCluster environment, it must be enabled in all clusters, or none. Ensure that all binaries and libraries are upgraded to LSF Version 7, including LSF\_BINDIR, LSF\_SERVERDIR and LSF\_LIBDIR directories, if you enable this parameter.

If your site uses any programs that use the LSF base and batch APIs, or LSF MPI (Message Passing Interface), they need to be recompiled using the LSF Version 7 APIs before they can work properly with this option enabled.

---

#### **Important:**

You must shut down the entire cluster before enabling or disabling this parameter.

If LSF\_STRICT\_CHECKING is defined, and your cluster has slave hosts that are dynamically added, LSF\_STRICT\_CHECKING must be configured in the local lsf.conf on all slave hosts.

---

## Valid value

Set to Y to enable this feature.

## Default

Not defined. LSF is secure in trusted environments.

## LSF\_STRICT\_RESREQ

### Syntax

```
LSF_STRICT_RESREQ=Y | N
```

### Description

When `LSF_STRICT_RESREQ=Y`, the resource requirement selection string must conform to the stricter resource requirement syntax described in *Administering Platform LSF*. The strict resource requirement syntax only applies to the select section. It does not apply to the other resource requirement sections (order, rusage, same, span, or cu).

When `LSF_STRICT_RESREQ=Y` in `lsf.conf`, LSF rejects resource requirement strings where an rusage section contains a non-consumable resource.

When `LSF_STRICT_RESREQ=N`, the default resource requirement selection string evaluation is performed.

## Default

N

## LSF\_STRIP\_DOMAIN

### Syntax

```
LSF_STRIP_DOMAIN=domain_suffix[:domain_suffix ...]
```

### Description

(Optional) If all of the hosts in your cluster can be reached using short host names, you can configure LSF to use the short host names by specifying the portion of the domain name to remove. If your hosts are in more than one domain or have more than one domain name, you can specify more than one domain suffix to remove, separated by a colon (:).

For example, given this definition of `LSF_STRIP_DOMAIN`,

```
LSF_STRIP_DOMAIN=.foo.com:.bar.com
```

LSF accepts `hostA`, `hostA.foo.com`, and `hostA.bar.com` as names for host `hostA`, and uses the name `hostA` in all output. The leading period `.` is required.

Example:

```
LSF_STRIP_DOMAIN=.platform.com:.generic.com
```

In the above example, LSF accepts `hostA`, `hostA.platform.com`, and `hostA.generic.com` as names for `hostA`, and uses the name `hostA` in all output.

Setting this parameter only affects host names displayed through LSF, it does not affect DNS host lookup.

## EGO parameter

```
EGO_STRIP_DOMAIN
```

## Default

Not defined

## LSF\_TIME\_CMD

### Syntax

**LSF\_TIME\_CMD**=*timing\_level*

### Description

The timing level for checking how long LSF commands run. Time usage is logged in milliseconds. Specify a positive integer.

## Default

Not defined

## See also

LSB\_TIME\_MBD, LSB\_TIME\_SBD, LSB\_TIME\_CMD, LSF\_TIME\_LIM, LSF\_TIME\_RES

## LSF\_TIME\_LIM

### Syntax

**LSF\_TIME\_LIM**=*timing\_level*

### Description

The timing level for checking how long LIM routines run.  
Time usage is logged in milliseconds. Specify a positive integer.

## EGO parameter

EGO\_TIME\_LIM

## Default

Not defined

## See also

LSB\_TIME\_CMD, LSB\_TIME\_MBD, LSB\_TIME\_SBD, LSF\_TIME\_RES

## LSF\_TIME\_RES

### Syntax

**LSF\_TIME\_RES**=*timing\_level*

### Description

The timing level for checking how long RES routines run.  
Time usage is logged in milliseconds. Specify a positive integer.

LSF\_TIME\_RES is not supported on Windows.

## Default

Not defined

## See also

LSB\_TIME\_CMD, LSB\_TIME\_MBD, LSB\_TIME\_SBD, LSF\_TIME\_LIM

## LSF\_TMPDIR

### Syntax

**LSF\_TMPDIR**=*directory*

### Description

Specifies the path and directory for temporary job output.

When LSF\_TMPDIR is defined in `lsf.conf`, LSF creates a temporary directory under the directory specified by LSF\_TMPDIR on the execution host when a job is started and sets the temporary directory environment variable (TMPDIR) for the job.

The name of the temporary directory has the following format:

```
$LSF_TMPDIR/job_ID.tmpdir
```

On UNIX, the directory has the permission 0700 and is owned by the execution user.

After adding LSF\_TMPDIR to `lsf.conf`, use `badm in hrestart all` to reconfigure your cluster.

If LSB\_SET\_TMPDIR= Y, the environment variable TMPDIR will be set equal to the path specified by LSF\_TMPDIR.

If the path specified by LSF\_TMPDIR does not exist, the value of TMPDIR is set to the default path `/tmp/job_ID.tmpdir`.

### Valid values

Specify any valid path up to a maximum length of 256 characters. The 256 character maximum path length includes the temporary directories and files that the system creates as jobs run. The path that you specify for LSF\_TMPDIR should be as short as possible to avoid exceeding this limit.

### UNIX

Specify an absolute path. For example:

```
LSF_TMPDIR=/usr/share/lsf_tmp
```

### Windows

Specify a UNC path or a path with a drive letter. For example:

```
LSF_TMPDIR=\\HostA\temp\lsf_tmp
```

```
LSF_TMPDIR=D:\temp\lsf_tmp
```

## Temporary directory for tasks launched by blaunch

By default, LSF creates a temporary directory for a job only on the first execution host. If `LSF_TMPDIR` is set in `lsf.conf`, the path of the job temporary directory on the first execution host is set to `LSF_TMPDIR/job_ID.tmpdir`.

If `LSB_SET_TMPDIR=Y`, the environment variable `TMPDIR` will be set equal to the path specified by `LSF_TMPDIR`.

Tasks launched through the `blaunch` distributed application framework make use of the LSF temporary directory specified by `LSF_TMPDIR`:

- When the environment variable `TMPDIR` is set on the first execution host, the `blaunch` framework propagates this environment variable to all execution hosts when launching remote tasks
- The job `RES` or the task `RES` creates the directory specified by `TMPDIR` if it does not already exist before starting the job
- The directory created by the job `RES` or task `RES` has permission `0700` and is owned by the execution user
- If the `TMPDIR` directory was created by the task `RES`, LSF deletes the temporary directory and its contents when the task is complete
- If the `TMPDIR` directory was created by the job `RES`, LSF will delete the temporary directory and its contents when the job is done
- If the `TMPDIR` directory is on a shared file system, it is assumed to be shared by all the hosts allocated to the `blaunch` job, so LSF *does not* remove `TMPDIR` directories created by the job `RES` or task `RES`

## Default

By default, `LSF_TMPDIR` is not enabled. If `LSF_TMPDIR` is not specified in `lsf.conf`, this parameter is defined as follows:

- On UNIX: `$TMPDIR/job_ID.tmpdir` or `/tmp/job_ID.tmpdir`
- On Windows: `%TMP%`, `%TEMP%`, or `%SystemRoot%`

## LSF\_ULDB\_DOMAIN

### Syntax

`LSF_ULDB_DOMAIN="domain_name ..."`

### Description

`LSF_ULDB_DOMAIN` specifies the name of the LSF domain in the ULDB domain directive. A domain definition of name *domain\_name* must be configured in the SGI IRIX `joblimit.in` input file.

Used with IRIX User Limits Database (ULDB). Configures LSF so that jobs submitted to a host with the IRIX job limits option installed are subject to the job limits configured in the IRIX User Limits Database (ULDB).

The ULDB contains job limit information that system administrators use to control access to a host on a per user basis. The job limits in the ULDB override the system default values for both job limits and process limits. When a ULDB domain is configured, the limits are enforced as IRIX job limits.

If the ULDB domain specified in `LSF_ULDB_DOMAIN` is not valid or does not exist, LSF uses the limits defined in the domain named `batch`. If the `batch` domain does not exist, then the system default limits are set.

When an LSF job is submitted, an IRIX job is created, and the job limits in the ULDB are applied.

Next, LSF resource usage limits are enforced for the IRIX job under which the LSF job is running. LSF limits override the corresponding IRIX job limits. The ULDB limits are used for any LSF limits that are not defined. If the job reaches the IRIX job limits, the action defined in the IRIX system is used.

IRIX job limits in the ULDB apply only to batch jobs.

See the IRIX resource administration documentation for information about configuring ULDB domains in the `limit.in` file.

## LSF resource usage limits controlled by ULDB

- **PROESSLIMIT**: Corresponds to `IRIX_JLIMIT_NUMPROC`; `fork()` fails, but the existing processes continue to run
- **MEMLIMIT**: Corresponds to `JLIMIT_RSS`; Resident pages above the limit become prime swap candidates
- **DATALIMIT**: Corresponds to `LIMIT_DATA`; `malloc()` calls in the job fail with `errno` set to `ENOMEM`
- **CPULIMIT**: Corresponds to `JLIMIT_CPU`; IRIX sends `SIGXCPU` signal to job, then after the grace period expires, sends `SIGINT`, `SIGTERM`, and `SIGKILL`
- **FILELIMIT**: No corresponding IRIX limit; use process limit `RLIMIT_FSIZE`
- **STACKLIMIT**: No corresponding IRIX limit; use process limit `RLIMIT_STACK`
- **CORELIMIT**: No corresponding IRIX limit; use process limit `RLIMIT_CORE`
- **SWAPLIMIT**: Corresponds to `JLIMIT_VMEM`; use process limit `RLIMIT_VMEM`

## Increasing the default MEMLIMIT for ULDB

In some pre-defined LSF queues, such as `normal`, the default `MEMLIMIT` is set to 5000 (5 MB). However, if ULDB is enabled (`LSF_ULDB_DOMAIN` is defined) the `MEMLIMIT` should be set greater than 8000 in `lsb.queues`.

### Default

Not defined

## LSF\_UNIT\_FOR\_LIMITS

### Syntax

`LSF_UNIT_FOR_LIMITS=unit`

### Description

Enables scaling of large units in resource usage limits.

When set, `LSF_UNIT_FOR_LIMITS` applies cluster-wide to limits at the job-level (`bsub`), queue-level (`lsb.queues`), and application level (`lsb.applications`).

The limit unit specified by `LSF_UNIT_FOR_LIMITS` also applies to limits modified with `bmod`, and the display of resource usage limits in query commands (`bacct`, `bapp`, `bhist`, `bhosts`, `bjobs`, `bqueues`, `lslod`, and `lshosts`).

---

### Important:

Before changing the units of your resource usage limits, you should completely drain the cluster of all workload. There should be no running, pending, or finished jobs in the system.

---

In a MultiCluster environment, you should configure the same unit for all clusters.

## Example

A job is submitted with `bsub -M 100` and `LSF_UNIT_FOR_LIMITS=MB`; the memory limit for the job is 100 MB rather than the default 100 KB.

## Valid values

*unit* indicates the unit for the resource usage limit, one of:

- KB (kilobytes)
- MB (megabytes)
- GB (gigabytes)
- TB (terabytes)
- PB (petabytes)
- EB (exabytes)

## Default

KB

## LSF\_USE\_HOSTEQUIV

### Syntax

`LSF_USE_HOSTEQUIV=y | Y`

### Description

(UNIX only; optional)

If `LSF_USE_HOSTEQUIV` is defined, `RES` and `mbatchd` call the `ruserok()` function to decide if a user is allowed to run remote jobs.

The `ruserok()` function checks in the `/etc/hosts.equiv` file and the user's `$HOME/.rhosts` file to decide if the user has permission to execute remote jobs.

If `LSF_USE_HOSTEQUIV` is not defined, all normal users in the cluster can execute remote jobs on any host.

If `LSF_ROOT_REX` is set, `root` can also execute remote jobs with the same permission test as for normal users.

## Default

Not defined

## See also

LSF\_ROOT\_REX

## LSF\_USER\_DOMAIN

### Syntax

**LSF\_USER\_DOMAIN**=*domain\_name:domain\_name:domain\_name...*

### Description

Enables the UNIX/Windows user account mapping feature, which allows cross-platform job submission and execution in a mixed UNIX/Windows environment. LSF\_USER\_DOMAIN specifies one or more Windows domains that LSF either strips from the user account name when a job runs on a UNIX host, or adds to the user account name when a job runs on a Windows host.

---

#### Important:

Configure LSF\_USER\_DOMAIN immediately after you install LSF; changing this parameter in an existing cluster requires that you verify and possibly reconfigure service accounts, user group memberships, and user passwords.

---

Specify one or more Windows domains, separated by a colon (:). You can enter an unlimited number of Windows domains. A period (.) specifies a local account, not a domain.

### Examples

```
LSF_USER_DOMAIN=BUSINESS
```

```
LSF_USER_DOMAIN=BUSINESS:ENGINEERING:SUPPORT
```

## Default

The default depends on your LSF installation:

- If you upgrade a cluster to LSF version 7, the default is the existing value of LSF\_USER\_DOMAIN, if defined
- For a new cluster, this parameter is not defined, and UNIX/Windows user account mapping is not enabled

## LSF\_VPLUGIN

### Syntax

**LSF\_VPLUGIN**=*path*

### Description

The full path to the vendor MPI library `libxmpi.so`. Used with Platform LSF HPC.

For PAM to access the SGI MPI `libxmpi.so` library, the file permission mode must be 755 (-rwxr-xr-x).

## Examples

- HP MPI: `LSF_VPLUGIN=/opt/mpi/lib/pal.1/libmpirm.sl`
- SGI MPI: `LSF_VPLUGIN=/usr/lib32/libxmpi.so`
- SGI Linux (64-bit x-86 Linux 2.6, glibc 2.3.): `LSF_VPLUGIN=/usr/lib32/libxmpi.so:/usr/lib/libxmpi.so:/usr/lib64/libxmpi.so`

## Default

Not defined

## MC\_PLUGIN\_REMOTE\_RESOURCE

### Syntax

**MC\_PLUGIN\_REMOTE\_RESOURCE=y**

### Description

MultiCluster job forwarding model only. By default, the submission cluster does not consider remote resources. Define `MC_PLUGIN_REMOTE_RESOURCE=y` in the submission cluster to allow consideration of remote resources.

---

#### Note:

When `MC_PLUGIN_REMOTE_RESOURCE` is defined, only the following resource requirements are supported: `-R "type==type_name"`, `-R "same[type]"` and `-R "defined(resource_name)"`

---

## Default

Not defined. The submission cluster does not consider remote resources.

## XLSF\_APPDIR

### Syntax

**XLSF\_APPDIR=directory**

### Description

(UNIX only; optional) Directory in which X application default files for LSF products are installed.

The LSF commands that use X look in this directory to find the application defaults. Users do not need to set environment variables to use the Platform LSF X applications. The application default files are platform-independent.

## Default

`LSF_INDEP/misc`

## XLSF\_UIDDIR

### Syntax

**XLSF\_UIDDIR**=*directory*

### Description

(UNIX only) Directory in which Motif User Interface Definition files are stored. These files are platform-specific.

### Default

LSF\_LIBDIR/ui d

# lsf.licensescheduler

The `lsf.licensescheduler` file contains Platform LSF License Scheduler configuration information. All sections except `ProjectGroup` are required.

The command `bl params` displays configuration information from this file.

## Changing lsf.licensescheduler configuration

After making any changes to `lsf.licensescheduler`, run the following commands:

- `bl admin reconfig` to reconfigure `bl d`
- `badmin mbdrestart` to restart `mbatchd`

## Parameters section

### Description

Required. Defines License Scheduler configuration parameters.

### Parameters section structure

The Parameters section begins and ends with the lines `Begin Parameters` and `End Parameters`. Each subsequent line describes one configuration parameter. All parameters are mandatory.

```
Begin Parameters
ADMIN=lsadmin
HOSTS=hostA hostB hostC
LMSTAT_PATH=/etc/flxlm/bin
LM_STAT_INTERVAL=30
PORT=9581
End Parameters
```

### Parameters

- ADMIN
- AUTH
- DISTRIBUTION\_POLICY\_VIOLATION\_ACTION
- ENABLE\_INTERACTIVE
- HOSTS
- LIB\_RECVTIMEOUT
- LM\_REMOVE\_INTERVAL
- LM\_STAT\_INTERVAL
- LMSTAT\_PATH
- LS\_DEBUG\_BLD
- LS\_LOG\_MASK
- LS\_MAX\_TASKMAN\_SESSIONS
- LS\_PREEMPT\_PEER
- PORT

- BLC\_HEARTBEAT\_FACTOR

## ADMIN

### Syntax

**ADMIN**=*user\_name* ...

### Description

Defines the License Scheduler administrator using a valid UNIX user account. You can specify multiple accounts.

## AUTH

### Syntax

**AUTH**=Y

### Description

Enables License Scheduler user authentication for projects for taskman jobs.

## DISTRIBUTION\_POLICY\_VIOLATION\_ACTION

### Syntax

**DISTRIBUTION\_POLICY\_VIOLATION\_ACTION**=(**PERIOD** *reporting\_period* **CMD** *reporting\_command*)

*reporting\_period*

Specify the keyword **PERIOD** with a positive integer representing the interval (a multiple of **LM\_STAT\_INTERVAL** periods) at which License Scheduler checks for distribution policy violations.

*reporting\_command*

Specify the keyword **CMD** with the directory path and command that License Scheduler runs when reporting a violation.

### Description

Optional. Defines how License Scheduler handles distribution policy violations. Distribution policy violations are caused by non-LSF workloads; LSF License Scheduler explicitly follows its distribution policies.

License Scheduler reports a distribution policy violation when the total number of licenses given to the LSF workload, both free and in use, is less than the LSF workload distribution specified in **WORKLOAD\_DISTRIBUTION**. If License Scheduler finds a distribution policy violation, it creates or overwrites the **LSF\_LOGDIR/**

**bl d. vi ol at i on. service\_domain\_name. l og file** and runs the user command specified by the **CMD** keyword.

## Example

The LicenseServer1 service domain has a total of 80 licenses, and its workload distribution and enforcement is configured as follows:

```

Begin Parameter
...
DISTRIBUTION_POLICY_VIOLATION_ACTION=(PERIOD 5 CMD /bin/mycmd)
...
End Parameter
Begin Feature
NAME=ApplicationX
DISTRIBUTION=LicenseServer1(Lp1 1 Lp2 2)
WORKLOAD_DISTRIBUTION=LicenseServer1(LSF 8 NON_LSF 2)
End Feature

```

According to this configuration, 80% of the available licenses, or 64 licenses, are available to the LSF workload. License Scheduler checks the service domain for a violation every five scheduling cycles, and runs the `/bin/mycmd` command if it finds a violation.

If the current LSF workload license usage is 50 and the number of free licenses is 10, the total number of licenses assigned to the LSF workload is 60. This is a violation of the workload distribution policy because this is less than the specified LSF workload distribution of 64 licenses.

## ENABLE\_INTERACTIVE

### Syntax

```
ENABLE_INTERACTIVE=Y
```

### Description

Optional. Globally enables one share of the licenses for interactive tasks.

---

#### Tip:

By default, `ENABLE_INTERACTIVE` is not set. License Scheduler allocates licenses equally to each cluster and does not distribute licenses for interactive tasks.

---

## HOSTS

### Syntax

```
HOSTS=host_name.domain_name ...
```

### Description

Defines License Scheduler hosts, including License Scheduler candidate hosts.

Specify a fully qualified host name such as `hostX.mycompany.com`. You can omit the domain name if all your License Scheduler clients run in the same DNS domain.

## LIB\_RECVTIMEOUT

### Syntax

**LIB\_RECVTIMEOUT**=*seconds*

### Description

Specifies a timeout value in seconds for communication between LSF License Scheduler and LSF.

### Default

0 seconds

## LM\_REMOVE\_INTERVAL

### Syntax

**LM\_REMOVE\_INTERVAL**=*seconds*

### Description

Specifies the minimum time a job must have a license checked out before `l mremove` can remove the license. `l mremove` causes `l mgrd` and vendor daemons to close the TCP connection with the application. They then retry the license checkout.

### Default

180 seconds

## LM\_STAT\_INTERVAL

### Syntax

**LM\_STAT\_INTERVAL**=*seconds*

### Description

Defines a time interval between calls that License Scheduler makes to collect license usage information from FLEXlm license management.

### Default

60 seconds

## LMSTAT\_PATH

### Syntax

**LMSTAT\_PATH**=*path*

### Description

Defines the full path to the location of the FLEXlm command `l mstat`.

## LS\_DEBUG\_BLD

### Syntax

```
LS_DEBUG_BLD=log_class
```

### Description

Sets the debugging log class for the LSF License Schedulerbld daemon.

Specifies the log class filtering to be applied to bld. Messages belonging to the specified log class are recorded. Not all debug message are controlled by log class.

LS\_DEBUG\_BLD sets the log class and is used in combination with MASK, which sets the log level. For example:

```
LS_LOG_MASK=LOG_DEBUG LS_DEBUG_BLD="LC_TRACE"
```

To specify multiple log classes, use a space-separated list enclosed in quotation marks. For example:

```
LS_DEBUG_BLD="LC_TRACE"
```

You need to restart the bld daemon after setting LS\_DEBUG\_BLD for your changes to take effect.

If you use the command `bladmin blddebug` to temporarily change this parameter without changing `lsf.licensescheduler`, you do not need to restart the daemons.

### Valid values

Valid log classes are:

- LC\_AUTH - Log authentication messages
- LC\_COMM - Log communication messages
- LC\_FLEX - Log everything related to FLEX\_STAT or FLEX\_EXEC Macrovision APIs
- LC\_LICENSE - Log license management messages (LC\_LICENSE is also supported for backward compatibility)
- LC\_PREEMPT - Log license preemption policy messages
- LC\_RESREQ - Log resource requirement messages
- LC\_TRACE - Log significant program walk steps
- LC\_XDR - Log everything transferred by XDR

### Valid values

Valid log classes are the same as for LS\_DEBUG\_CMD.

### Default

Not defined.

## LS\_ENABLE\_MAX\_PREEMPT

### Syntax

```
LS_ENABLE_MAX_PREEMPT=Y
```

## Description

Enables maximum preemption time checking for `taskman` jobs.

When `LS_ENABLE_MAX_PREEMPT` is disabled, preemption times for `taskman` job are not checked regardless of the value of parameters `LS_MAX_TASKMAN_PREEMPT` in `lsf.licensescheduler` and `MAX_JOB_PREEMPT` in `lsb.queues`, `lsb.applications`, or `lsb.params`.

## Default

N

## LS\_LOG\_MASK

## Syntax

**LS\_LOG\_MASK**=*message\_log\_level*

## Description

Specifies the logging level of error messages for LSF License Scheduler daemons. If `LS_LOG_MASK` is not defined in `lsf.licensescheduler`, the value of `LSF_LOG_MASK` in `lsf.conf` is used. If neither `LS_LOG_MASK` nor `LSF_LOG_MASK` is defined, the default is `LOG_WARNING`.

For example:

```
LS_LOG_MASK=LOG_DEBUG
```

The log levels in order from highest to lowest are:

- LOG\_WARNING
- LOG\_DEBUG
- LOG\_DEBUG1
- LOG\_DEBUG2
- LOG\_DEBUG3

The most important License Scheduler log messages are at the `LOG_WARNING` level. Messages at the `LOG_DEBUG` level are only useful for debugging.

Although message log level implements similar functionality to UNIX `syslog`, there is no dependency on UNIX `syslog`. It works even if messages are being logged to files instead of `syslog`.

License Scheduler logs error messages in different levels so that you can choose to log all messages, or only log messages that are deemed critical. The level specified by `LS_LOG_MASK` determines which messages are recorded and which are discarded. All messages logged at the specified level or higher are recorded, while lower level messages are discarded.

For debugging purposes, the level `LOG_DEBUG` contains the fewest number of debugging messages and is used for basic debugging. The level `LOG_DEBUG3` records all debugging messages, and can cause log files to grow very large; it is not often used. Most debugging is done at the level `LOG_DEBUG2`.

## Default

LOG\_WARNING

## LS\_MAX\_TASKMAN\_PREEMPT

### Syntax

**LS\_MAX\_TASKMAN\_PREEMPT**=*integer*

### Description

Defines the maximum number of times `taskman` jobs can be preempted.

Maximum preemption time checking for all jobs is enabled by `LS_ENABLE_MAX_PREEMPT`.

### Default

unlimited

## LS\_MAX\_TASKMAN\_SESSIONS

### Syntax

**LS\_MAX\_TASKMAN\_SESSIONS**=*integer*

### Description

Defines the maximum number of `taskman` jobs that run simultaneously. This prevents system-wide performance issues that occur if there are a large number of `taskman` jobs running in License Scheduler.

## LS\_PREEMPT\_PEER

### Syntax

**LS\_PREEMPT\_PEER**=Y

### Description

Enables bottom-up license token preemption in hierarchical project group configuration. License Scheduler attempts to preempt tokens from the closest projects in the hierarchy first. This balances token ownership from the bottom up.

### Default

Not defined. Token preemption in hierarchical project groups is top down.

## PORT

### Syntax

**PORT**=*integer*

### Description

Defines the TCP listening port used by License Scheduler hosts, including candidate License Scheduler hosts. Specify any non-privileged port number.

## BLC\_HEARTBEAT\_FACTOR

### Syntax

**BLC\_HEARTBEAT\_FACTOR**=*integer*

### Description

Enables bld to detect bl collect failure. Defines the number of times that bld receives no response from a license collector daemon (bl collect) before bld resets the values for that collector to zero. Each license usage reported to bld by the collector is treated as a heartbeat.

### Default

3

## Clusters section

### Description

Required. Lists the clusters that can use License Scheduler.

When configuring clusters for a WAN, the Clusters section of the master cluster must define its slave clusters.

### Clusters section structure

The Clusters section begins and ends with the lines `Begin Clusters` and `End Clusters`. The second line is the column heading, `CLUSTERS`. Subsequent lines list participating clusters, one name per line:

```
Begin Clusters
```

```
CLUSTERS
```

```
cluster1
```

```
cluster2
```

```
End Clusters
```

## CLUSTERS

Defines the name of each participating LSF cluster. Specify using one name per line.

## ServiceDomain section

### Description

Required. Defines License Scheduler service domains as groups of physical license server hosts that serve a specific network.

### ServiceDomain section structure

Define a section for each License Scheduler service domain.

This example shows the structure of the section:

```
Begin ServiceDomain
```

```
NAME=DesignCenterB
```

```
LIC_SERVERS=((1888@hostD) (1888@hostE))
```

```
LIC_COLLECTOR=CenterB
```

```
End ServiceDomain
```

## Parameters

- NAME
- LIC\_SERVERS
- LIC\_COLLECTOR
- LM\_STAT\_INTERVAL

## NAME

Defines the name of the service domain.

## LIC\_SERVERS

### Syntax

```
LIC_SERVERS=([(host_name | port_number@host_name |( port_number@host_name
port_number@host_name port_number@host_name)] ...)
```

## Description

Defines the FLEXlm license server hosts that make up the License Scheduler service domain. For each FLEXlm license server host, specify the number of the port that FLEXlm uses, then the at symbol (@), then the name of the host. If FLEXlm uses the default port on a host, you can specify the host name without the port number. Put one set of parentheses around the list, and one more set of parentheses around each host, unless you have redundant servers (three hosts sharing one license file). If you have redundant servers, the parentheses enclose all three hosts.

## Examples

- One FLEXlm license server host:  

```
LIC_SERVERS=((1700@hostA))
```
- Multiple FLEXlm license server hosts with unique license.dat files:  

```
LIC_SERVERS=((1700@hostA) (1700@hostB) (1700@hostC))
```
- Redundant FLEXlm license server hosts sharing the same license.dat file:  

```
LIC_SERVERS=((1700@hostD 1700@hostE 1700@hostF))
```

## LIC\_COLLECTOR

### Syntax

```
LIC_COLLECTOR=licence_collector_name
```

## Description

Optional. Defines a name for the license collector daemon (blcollect) to use in each service domain. blcollect collects license usage information from FLEXlm and passes it to the

License Scheduler daemon (bl d). It improves performance by allowing you to distribute license information queries on multiple hosts.

You can only specify one collector per service domain, but you can specify one collector to serve multiple service domains. Each time you run `bl collect`, you must specify the name of the collector for the service domain. You can use any name you want.

## Default

Undefined. The License Scheduler daemon uses one license collector daemon for the entire cluster.

## LM\_STAT\_INTERVAL

### Syntax

`LM_STAT_INTERVAL=seconds`

### Description

Defines a time interval between calls that License Scheduler makes to collect license usage information from FLEXlm license management.

The value specified for a service domain overrides the global value defined in the Parameters section. Each service domain definition can specify a different value for this parameter.

## Default

Undefined: License Scheduler applies the global value.

## Feature section

### Description

Required. Defines license distribution policies.

## Feature section structure

Define a section for each feature managed by License Scheduler.

```
Begin Feature
```

```
NAME=vcs
```

```
FLEX_NAME=vcs
```

```
DISTRIBUTION=1 anserver1 (Lp1 1 Lp2 4/6)
```

```
1 anserver2 (Lp3 1 Lp4 10/8)
```

```
wanserver (Lp1 1 Lp2 1 Lp3 1 Lp4 1)
```

```
End Feature
```

## Parameters

- NAME
- FLEX\_NAME
- DISTRIBUTION
- ALLOCATION
- GROUP

- GROUP\_DISTRIBUTION
- LOCAL\_TO
- LS\_FEATURE\_PERCENTAGE
- NON\_SHARED\_DISTRIBUTION
- PREEMPT\_RESERVE
- SERVICE\_DOMAINS
- WORKLOAD\_DISTRIBUTION
- ENABLE\_DYNAMIC\_RUSAGE
- DYNAMIC
- LM\_REMOVE\_INTERVAL
- ENABLE\_MINJOB\_PREEMPTION

## NAME

Required. Defines the token name—the name used by License Scheduler and LSF to identify the license feature.

Normally, license token names should be the same as the FLEXlm Licensing feature names, as they represent the same license. However, LSF does not support names that start with a number, or names containing a dash or hyphen character (-), which may be used in the FLEXlm Licensing feature name.

## FLEX\_NAME

Optional. Defines the feature name—the name used by FLEXlm to identify the type of license. You only need to specify this parameter if the License Scheduler token name is not identical to the FLEXlm feature name.

FLEX\_NAME allows the NAME parameter to be an alias of the FLEXlm feature name. For feature names that start with a number or contain a dash (-), you must set both NAME and FLEX\_NAME, where FLEX\_NAME is the actual FLEXlm Licensing feature name, and NAME is an arbitrary license token name you choose.

For example

```
Begin Feature
FLEX_NAME=201-AppZ
NAME=AppZ201
DISTRIBUTION=LanServer1(Lp1 1 Lp2 1)
End Feature
```

## DISTRIBUTION

### Syntax

**DISTRIBUTION**=[*service\_domain\_name*([*project\_name* *number\_shares*/*number\_licenses\_owned*] ... [default] )] ...

*service\_domain\_name*

Specify a License Scheduler service domain (described in the ServiceDomain section) that distributes the licenses.

*project\_name*

Specify a License Scheduler project (described in the Projects section) that is allowed to use the licenses.

*number\_shares*

Specify a positive integer representing the number of shares assigned to the project.

The number of shares assigned to a project is only meaningful when you compare it to the number assigned to other projects, or to the total number assigned by the service domain. The total number of shares is the sum of the shares assigned to each project.

*number\_licenses\_owned*

Optional. Specify a slash (/) and a positive integer representing the number of licenses that the project owns.

default

A reserved keyword that represents the default License Scheduler project if the job submission does not specify a project (bsub -Lp).

Default includes all projects that have not been defined in the PROJECTS section of lsf.licensescheduler. Jobs that belong to projects that are defined in lsf.licensescheduler do not get a share of the tokens when the project is not explicitly defined in the distribution.

## Description

Required if GROUP\_DISTRIBUTION is not defined. Defines the distribution policies for the license. The name of each service domain is followed by its distribution policy, in parentheses. The distribution policy determines how the licenses available in each service domain are distributed among the clients.

The distribution policy is a space-separated list with each project name followed by its share assignment. The share assignment determines what fraction of available licenses is assigned to each project, in the event of competition between projects. Optionally, the share assignment is followed by a slash and the number of licenses owned by that project. License ownership enables a preemption policy. (In the event of competition between projects, projects that own licenses preempt jobs. Licenses are returned to the owner immediately.)

GROUP\_DISTRIBUTION and DISTRIBUTION are mutually exclusive. If they are both defined in the same feature, the License Scheduler daemon returns an error and ignores this feature.

## Examples

```
DISTRIBUTION=wanserver (Lp1 1 Lp2 1 Lp3 1 Lp4 1)
```

In this example, the service domain named wanserver shares licenses equally among four License Scheduler projects. If all projects are competing for a total of eight licenses, each project is entitled to two licenses at all times. If all projects are competing for only two licenses in total, each project is entitled to a license half the time.

```
DISTRIBUTION=lanserver1 (Lp1 1 Lp2 2/6)
```

In this example, the service domain named lanserver1 allows Lp1 to use one third of the available licenses and Lp2 can use two thirds of the licenses. However, Lp2 is always entitled to six licenses, and can preempt another project to get the licenses immediately if they are needed. If the projects are competing for a total of 12 licenses, Lp2 is entitled to eight licenses (six on demand, and two more as soon as they are free). If the projects are competing for only

six licenses in total, Lp2 is entitled to all of them, and Lp1 can only use licenses when Lp2 does not need them.

## ALLOCATION

### Syntax

**ALLOCATION**=*project\_name* (*cluster\_name* [*number\_shares*] ... ) ...

*cluster\_name*

Specify LSF cluster names that licenses are to be allocated to.

*project\_name*

Specify a License Scheduler project (described in the PROJECTS section) that is allowed to use the licenses.

*number\_shares*

Specify a positive integer representing the number of shares assigned to the cluster.

The number of shares assigned to a cluster is only meaningful when you compare it to the number assigned to other clusters. The total number of shares is the sum of the shares assigned to each cluster.

### Description

Defines the allocation of license features across clusters and between LSF jobs and non-LSF interactive jobs.

ALLOCATION ignores the global setting of the ENABLE\_INTERACTIVE parameter because ALLOCATION is configured for the license feature.

You can configure the allocation of license shares to:

- Change the share number between clusters for a feature
- Limit the scope of license usage and change the share number between LSF jobs and interactive tasks for a feature

---

#### Tip:

To manage interactive (non-LSF) tasks in License Scheduler projects, you require the LSF Task Manager, `taskman`. The Task Manager utility is supported by License Scheduler. For more information about `taskman`, contact Platform.

---

### Default

Undefined. If ENABLE\_INTERACTIVE is not set, each cluster receives one share, and interactive tasks receive no shares.

Each example contains two clusters and 12 licenses of a specific feature.

## Example 1

ALLOCATION is not configured. The ENABLE\_INTERACTIVE parameter is not set.

```
Begin Parameters
```

```
...
```

```
ENABLE_INTERACTIVE=n
```

```
...
```

```
End Parameters
```

```
Begin Feature
```

```
NAME=ApplicationX
```

```
DISTRIBUTION=LicenceServer1 (Lp1 1)
```

```
End Feature
```

Six licenses are allocated to each cluster. No licenses are allocated to interactive tasks.

## Example 2

ALLOCATION is not configured. The ENABLE\_INTERACTIVE parameter is set.

```
Begin Parameters
```

```
...
```

```
ENABLE_INTERACTIVE=y
```

```
...
```

```
End Parameters
```

```
Begin Feature
```

```
NAME=ApplicationX
```

```
DISTRIBUTION=LicenceServer1 (Lp1 1)
```

```
End Feature
```

Four licenses are allocated to each cluster. Four licenses are allocated to interactive tasks.

## Example 3

In the following example, the ENABLE\_INTERACTIVE parameter does not affect the ALLOCATION configuration of the feature.

ALLOCATION is configured. The ENABLE\_INTERACTIVE parameter is set.

```
Begin Parameters
```

```
...
```

```
ENABLE_INTERACTIVE=y
```

```
...
```

```
End Parameters
```

```
Begin Feature
```

```
NAME=ApplicationY
```

```
DISTRIBUTION=LicenceServer1 (Lp2 1)
```

```
ALLOCATION=Lp2(cluster1 1 cluster2 0 interactive 1)
```

```
End Feature
```

The ENABLE\_INTERACTIVE setting is ignored. Licenses are shared equally between cluster1 and interactive tasks. Six licenses of ApplicationY are allocated to cluster1. Six licenses are allocated to interactive tasks.

## Example 4

In the following example, the ENABLE\_INTERACTIVE parameter does not affect the ALLOCATION configuration of the feature.

ALLOCATION is configured. The ENABLE\_INTERACTIVE parameter is not set.

```
Begin Parameters
```

```
...
```

```
ENABLE_INTERACTIVE=n
```

```
...
```

```
End Parameters
```

```
Begin Feature
```

```
NAME=ApplicationZ
```

```
DISTRIBUTION=LicenseServer1 (Lp1 1)
```

```
ALLOCATION=Lp1(cluster1 0 cluster2 1 interactive 2)
```

```
End Feature
```

The ENABLE\_INTERACTIVE setting is ignored. Four licenses of ApplicationZ are allocated to cluster2. Eight licenses are allocated to interactive tasks.

## GROUP

### Syntax

```
GROUP=[group_name(project_name... )] ...
```

*group\_name*

Specify a name for a group of projects.

*project\_name*

Specify a License Scheduler project (described in the PROJECTS section) that is allowed to use the licenses. The project must appear in the DISTRIBUTION.

A project should only belong to one group.

### Description

Optional. Defines groups of projects and specifies the name of each group. The groups defined here are used for group preemption and replace single projects with group projects.

This parameter is ignored if GROUP\_DISTRIBUTION is also defined.

## GROUP\_DISTRIBUTION

### Syntax

```
GROUP_DISTRIBUTION=top_level_hierarchy_name
```

*top\_level\_hierarchy\_name*

Specify the name of the top level hierarchical group.

## Description

Required if DISTRIBUTION is not defined. Defines the name of the hierarchical group containing the distribution policy attached to this feature.

GROUP\_DISTRIBUTION and DISTRIBUTION are mutually exclusive. If they are both defined in the same feature, the License Scheduler daemon returns an error and ignores this feature.

If GROUP is also defined, it is ignored in favour of GROUP\_DISTRIBUTION.

## Example

The following example shows the GROUP\_DISTRIBUTION parameter hierarchical scheduling for the top-level hierarchical group named groups. The SERVICE\_DOMAINS parameter defines a list of service domains that provide tokens for the group.

```
Begin Feature
NAME = myjob2
GROUP_DISTRIBUTION = groups
SERVICE_DOMAINS = LanServer wanServer
End Feature
```

## LOCAL\_TO

### Syntax

**LOCAL\_TO**=*cluster\_name* | *location\_name*(*cluster\_name* [*cluster\_name* ...])

### Description

Configures token locality for the license feature. You must configure different feature sections for same feature based on their locality. By default, If LOCAL\_TO is not defined, the feature is available to all clients and is not restricted by geographical location. When LOCAL\_TO is configured, for a feature, License Scheduler treats license features served to different locations as different token names, and distributes the tokens to projects according the distribution and allocation policies for the feature.

LOCAL\_TO allows you to limit features from different service domains to specific clusters, so License Scheduler only grants tokens of a feature to jobs from clusters that are entitled to them.

For example, if your license servers restrict the serving of license tokens to specific geographical locations, use LOCAL\_TO to specify the locality of a license token if any feature cannot be shared across all the locations. This avoids having to define different distribution and allocation policies for different service domains, and allows hierarchical group configurations.

License Scheduler manages features with different localities are different resources. Use `blinfo` and `blstat` to see the different resource information for the features depending on their cluster locality.

License features with different localities must be defined in different feature sections. The same Service Domain can appear only once in the configuration for a given license feature.

A configuration like `LOCAL_TO=Site1(clusterA clusterB)` configures the feature for more than one cluster.

A configuration like `LOCAL_TO=clusterA` configures locality for only one cluster. This is the same as `LOCAL_TO=clusterA(clusterA)`.

Cluster names must be the names of clusters defined in the Clusters section of `lsf.licensescheduler`.

## Examples

```
Begin Feature
NAME = hspace
DISTRIBUTION = SD1 (Lp1 1 Lp2 1)
LOCAL_TO = siteUS(clusterA clusterB)
End Feature
```

```
Begin Feature
NAME = hspace
DISTRIBUTION = SD2 (Lp1 1 Lp2 1)
LOCAL_TO = clusterA
End Feature
```

```
Begin Feature
NAME = hspace
DISTRIBUTION = SD3 (Lp1 1 Lp2 1) SD4 (Lp1 1 Lp2 1)
End Feature
```

Or use the hierarchical group configuration (GROUP\_DISTRIBUTION):

```
Begin Feature
NAME = hspace
GROUP_DISTRIBUTION = group1
SERVICE_DOMAINS = SD1
LOCAL_TO = siteUS(clusterA clusterB)
End Feature
```

```
Begin Feature
NAME = hspace
GROUP_DISTRIBUTION = group1
SERVICE_DOMAINS = SD2
LOCAL_TO = clusterA
End Feature
```

```
Begin Feature
NAME = hspace
GROUP_DISTRIBUTION = group1
SERVICE_DOMAINS = SD3 SD4
End Feature
```

## Default

Not defined. The feature is available to all clusters and interactive jobs, and is not restricted by cluster.

## LS\_FEATURE\_PERCENTAGE

### Syntax

```
LS_FEATURE_PERCENTAGE=Y | N
```

### Description

Configures license ownership in percentages instead of absolute numbers. When not combined with hierarchical projects, affects DISTRIBUTED and NON\_SHARED\_DISTRIBUTION values only. When using hierarchical projects, percentage is applied to OWNERSHIP, LIMITS, and NON\_SHARED values.

### Example 1

```
Begin Feature
LS_FEATURE_PERCENTAGE = Y
DISTRIBUTION = LanServer (p1 1 p2 1 p3 1/20)
...
End Feature
```

The service domain LanServer shares licenses equally among three License Scheduler projects. P3 is always entitled to 20% of the total licenses, and can preempt another project to get the licenses immediately if they are needed.

### Example 2

With LS\_FEATURE\_PERCENTAGE=Y in feature section and using hierarchical project groups:

```
Begin ProjectGroup
GROUP      SHARES  OWNERSHIP  LIMITS  NON_SHARED
(R (A p4)) (1 1)   ()         ()      ()
(A (B p3)) (1 1)   (- 10)    (- 20)  ()
(B (p1 p2)) (1 1)   (30 -)    ()      (- 5)
End ProjectGroup
```

Project p1 owns 30% of the total licenses, and project p3 owns 10% of total licenses. P3's LIMITS is 20% of total licenses, and p2's NON\_SHARED is 5%.

## Default

N (Ownership is not configured with percentages but with absolute numbers.)

## NON\_SHARED\_DISTRIBUTION

### Syntax

**NON\_SHARED\_DISTRIBUTION**=*service\_domain\_name* ([*project\_name* *number\_non\_shared\_licenses*] ... ) ...

*service\_domain\_name*

Specify a License Scheduler service domain (described in the ServiceDomain section) that distributes the licenses.

*project\_name*

Specify a License Scheduler project (described in the Projects section) that is allowed to use the licenses.

*number\_non\_shared\_licenses*

Specify a positive integer representing the number of non-shared licenses that the project owns.

### Description

Optional. Defines non-shared licenses. Non-shared licenses are not shared with other license projects. They are available only to that project.

Use `blinfo -a` to display NON\_SHARED\_DISTRIBUTION information.

### Example

```
Begin Feature
NAME=f1 # total 15 on LanServer and 15 on WanServer
FLEX_NAME=VCS- RUNTIME
DISTRIBUTION=LanServer(Lp1 4 Lp2 1) WanServer (Lp1 1 Lp2 1/3)
NON_SHARED_DISTRIBUTION=LanServer(Lp1 10) WanServer (Lp1 5 Lp2 3)
PREEMPT_RESERVE=Y
End Feature
```

In this example:

- 10 non-shared licenses are defined for the Lp1 project on LanServer
- 5 non-shared licenses are defined for the Lp1 project on WanServer
- 3 non-shared licenses are defined for the Lp2 project on WanServer

The remaining licenses are distributed as follows:

- LanServer: The remaining 5 (15-10=5) licenses on LanServer is distributed to the Lp1 and Lp2 projects with a 4:1 ratio.
- WanServer: The remaining 7 (15-5-3=7) licenses on WanServer is distributed to the Lp1 and Lp2 projects with a 1:1 ratio. If Lp2 uses fewer than 6 (3 privately owned+ 3 owned) licenses, then a job in the Lp2 can preempt Lp1 jobs.

## PREEMPT\_LSF

### Syntax

**PREEMPT\_LSF=Y**

### Description

Optional. With the flex grid interface integration installed, enables on-demand preemption of LSF jobs for important non-managed workload. This guarantees that important non-managed jobs do not fail because of lack of licenses.

### Default

LSF workload is not preemptable

## PREEMPT\_RESERVE

### Syntax

**PREEMPT\_RESERVE=Y**

### Description

Optional. Enables License Scheduler to preempt either licenses that are reserved or already in use by other projects. The number of jobs must be greater than the number of licenses owned.

### Default

Y: reserved licenses are preemptable

## SERVICE\_DOMAINS

### Syntax

**SERVICE\_DOMAINS=***service\_domain\_name* ...

*service\_domain\_name*

Specify the name of the service domain.

### Description

Required if GROUP\_DISTRIBUTION is defined. Specifies the service domains that provide tokens for this feature.

## WORKLOAD\_DISTRIBUTION

### Syntax

**WORKLOAD\_DISTRIBUTION=**[*service\_domain\_name*(**LSF** *lsf\_distribution* [/ *enforced\_distribution*] **NON\_LSF** *non\_lsf\_distribution*)] ...

*service\_domain\_name*

Specify a License Scheduler service domain (described in the ServiceDomain section) that distributes the licenses.

*lsf\_distribution*

Specify the share of licenses dedicated to LSF workloads. The share of licenses dedicated to LSF workloads is a ratio of *lsf\_distribution:non\_lsf\_distribution*.

*enforced\_distribution*

Optional. Specify a slash (/) and a positive integer representing the enforced number of licenses.

*non\_lsf\_distribution*

Specify the share of licenses dedicated to non-LSF workloads. The share of licenses dedicated to non-LSF workloads is a ratio of *non\_lsf\_distribution:lsf\_distribution*.

## Description

Optional. Defines the distribution given to each LSF and non-LSF workload within the specified service domain.

Use `blinfo -a` to display `WORKLOAD_DISTRIBUTION` configuration.

## Example 1

```
Begin Feature
NAME=ApplicationX
DISTRIBUTION=LicenceServer1(Lp1 1 Lp2 2)
WORKLOAD_DISTRIBUTION=LicenceServer1(LSF 8 NON_LSF 2)
End Feature
```

On the `LicenceServer1` domain, the available licenses are dedicated in a ratio of 8:2 for LSF and non-LSF workloads. This means that 80% of the available licenses are dedicated to the LSF workload, and 20% of the available licenses are dedicated to the non-LSF workload.

If `LicenceServer1` has a total of 80 licenses, this configuration indicates that 64 licenses are dedicated to the LSF workload, and 16 licenses are dedicated to the non-LSF workload.

## Example 2

```
Begin Feature
NAME=ApplicationX
DISTRIBUTION=LicenceServer1(Lp1 1 Lp2 2)
WORKLOAD_DISTRIBUTION=LicenceServer1(LSF 8/40 NON_LSF 2)
End Feature
```

On the `LicenceServer1` domain, the available licenses are dedicated in a ratio of 8:2 for LSF and non-LSF workloads, with an absolute maximum of 40 licenses dedicated to the LSF workload. This means that 80% of the available licenses, up to a maximum of 40, are dedicated to the LSF workload, and the remaining licenses are dedicated to the non-LSF workload.

If `LicenceServer1` has a total of 40 licenses, this configuration indicates that 32 licenses are dedicated to the LSF workload, and eight licenses are dedicated to the non-LSF workload. However, if `LicenceServer1` has a total of 80 licenses, only 40 licenses are dedicated to the LSF workload, and the remaining 40 licenses are dedicated to the non-LSF workload.

## ENABLE\_DYNAMIC\_RUSAGE

### Syntax

**ENABLE\_DYNAMIC\_RUSAGE=Y**

### Description

Enforces license distribution policies for class-C license features.

When set, `ENABLE_DYNAMIC_RUSAGE` enables all class-C license checkouts to be considered managed checkout, instead of unmanaged (or OTHERS).

## DYNAMIC

### Syntax

**DYNAMIC=Y**

### Description

If you specify `DYNAMIC=Y`, you must specify a duration in an `rusage` resource requirement for the feature. This enables License Scheduler to treat the license as a dynamic resource and prevents License Scheduler from scheduling tokens for the feature when they are not available, or reserving license tokens when they should actually be free.

## LM\_REMOVE\_INTERVAL

### Syntax

**LM\_REMOVE\_INTERVAL=*seconds***

### Description

Specifies the minimum time a job must have a license checked out before `l mremove` can remove the license. `l mremove` causes `l mgrd` and vendor daemons to close the TCP connection with the application. They then retry the license checkout.

The value specified for a feature overrides the global value defined in the Parameters section. Each feature definition can specify a different value for this parameter.

### Default

Undefined: License Scheduler applies the global value.

## ENABLE\_MINJOB\_PREEMPTION

### Syntax

**ENABLE\_MINJOB\_PREEMPTION=Y**

### Description

Minimizes the overall number of preempted jobs by enabling job list optimization. For example, for a job that requires 10 licenses, License Scheduler preempts one job that uses 10 or more licenses rather than 10 jobs that each use one license.

## Default

Undefined: License Scheduler does not optimize the job list when selecting jobs to preempt.

## FeatureGroup section

### Description

Optional. Collects license features into groups. Put FeatureGroup sections after Feature sections in `lsf.licensescheduler`.

### FeatureGroup section structure

The FeatureGroup section begins and ends with the lines `Begin FeatureGroup` and `End FeatureGroup`. Feature group definition consists of a unique name and a list of features contained in the feature group.

### Example

```
Begin FeatureGroup
NAME = Synposys
FEATURE_LIST = ASTRO VCS_Runtime_Net Hsim Hspice
End FeatureGroup
Begin FeatureGroup
NAME = Cadence
FEATURE_LIST = Encounter NCSim NCVerilog
End FeatureGroup
```

### Parameters

- NAME
- FEATURE\_LIST

### NAME

Required. Defines the name of the feature group. The name must be unique.

### FEATURE\_LIST

Required. Lists the license features contained in the feature group. The feature names in FEATURE\_LIST must already be defined in Feature sections. Feature names cannot be repeated in the FEATURE\_LIST of one feature group. The FEATURE\_LIST cannot be empty. Different feature groups can have the same features in their FEATURE\_LIST.

## ProjectGroup section

### Description

Optional. Defines the hierarchical relationships of projects.

The hierarchical groups can have multiple levels of grouping. You can configure a tree-like scheduling policy, with the leaves being the license projects that jobs can belong to. Each project group in the tree has a set of values, including shares, limits, ownership and non-shared, or exclusive, licenses.

Use `blstat -G` to view the hierarchical dynamic license information.

Use `blinfo -G` to view the hierarchical configuration.

## ProjectGroup section structure

Define a section for each hierarchical group managed by License Scheduler.

The keywords `GROUP`, `SHARES`, `OWNERSHIP`, `LIMIT`, and `NON_SHARED` are required. The keyword `PRIORITY` is optional. Empty brackets are allowed only for `OWNERSHIP`, `LIMIT`, and `PRIORITY`. `SHARES` must be specified.

```

Begin
  ProjectGroupGROUP SHARES OWNERSHIP LIMITS NON_SHARED PRIORITY
(root(A B C)) (1 1 1) () () () (3 2 -)
(A (P1 D)) (1 1) () () () (3 5)
(B (P4 P5)) (1 1) () () () ()
(C (P6 P7 P8)) (1 1 1) () () () (8 3 0)
(D (P2 P3)) (1 1) () () () (2 1)
End ProjectGroup

```

## Parameters

- `GROUP`
- `SHARES`
- `OWNERSHIP`
- `LIMITS`
- `NON_SHARED`
- `PRIORITY`
- `DESCRIPTION`

## GROUP

Defines the project names in the hierarchical grouping and its relationships. Each entry specifies the name of the hierarchical group and its members.

For better readability, you should specify the projects in the order from the root to the leaves as in the example.

Specify the entry as follows:

*(group (member ...))*

## SHARES

Required. Defines the shares assigned to the hierarchical group member projects. Specify the share for each member, separated by spaces, in the same order as listed in the `GROUP` column.

## OWNERSHIP

Defines the level of ownership of the hierarchical group member projects. Specify the ownership for each member, separated by spaces, in the same order as listed in the `GROUP` column.

You can only define `OWNERSHIP` for hierarchical group member projects, not hierarchical groups. Do not define `OWNERSHIP` for the top level (root) project group. Ownership of a given internal node is the sum of the ownership of all child nodes it directly governs.

A dash (-) is equivalent to a zero, which means there are no owners of the projects. You can leave the parentheses empty () if desired.

## Valid values

A positive integer between the NON\_SHARED and LIMITS values defined for the specified hierarchical group.

- If defined as less than NON\_SHARED, OWNERSHIP is set to NON\_SHARED.
- If defined as greater than LIMITS, OWNERSHIP is set to LIMITS.

## LIMITS

Defines the maximum number of licenses that can be used at any one time by the hierarchical group member projects. Specify the maximum number of licenses for each member, separated by spaces, in the same order as listed in the GROUP column.

A dash (-) is equivalent to INFINIT\_INT, which means there is no maximum limit and the project group can use as many licenses as possible.

You can leave the parentheses empty () if desired.

## NON\_SHARED

Defines the number of licenses that the hierarchical group member projects use exclusively. Specify the number of licenses for each group or project, separated by spaces, in the same order as listed in the GROUP column.

A dash (-) is equivalent to a zero, which means there are no licenses that the hierarchical group member projects use exclusively.

Normally, the total number of non-shared licenses should be less than the total number of license tokens available. License tokens may not be available to project groups if the total non-shared licenses for all groups is greater than the number of shared tokens available.

For example, feature p4\_4 is configured as follows, with a total of 4 tokens:

```
Begin Feature NAME =p4_4 # total token value is 4 GROUP_DISTRIBUTION=final
SERVICE_DOMAINS=LanServer End Feature
```

The correct configuration is:

| GROUP           | SHARES | OWNERSHIP | LIMITS | NON_SHARED |
|-----------------|--------|-----------|--------|------------|
| (final (G2 G1)) | (1 1)  | ()        | ()     | (2 0)      |
| (G1 (AP2 AP1))  | (1 1)  | ()        | ()     | (1 1)      |

## Valid values

Any positive integer up to the LIMITS value defined for the specified hierarchical group.

If defined as greater than LIMITS, NON\_SHARED is set to LIMITS.

## PRIORITY

Optional. Defines the priority assigned to the hierarchical group member projects. Specify the priority for each member, separated by spaces, in the same order as listed in the GROUP column.

“0” is the lowest priority, and a higher number specifies a higher priority. This column overrides the default behavior. Instead of preempting based on the accumulated inuse usage

of each project, the projects are preempted according to the specified priority from lowest to highest.

By default, priorities are evaluated top down in the project group hierarchy. The priority of a given node is first decided by the priority of the parent groups. When two nodes have the same priority, priority is determined by the accumulated inuse usage of each project at the time the priorities are evaluated. Specify `LS_PREEMPT_PEER=Y` in the `Parametersr` section to enable bottom-up license token preemption in hierarchical project group configuration.

A dash (-) is equivalent to a zero, which means there is no priority for the project. You can leave the parentheses empty () if desired.

Use `blinfo -G` to view hierarchical project group priority information.

## Priority of default project

If not explicitly configured, the default project has the priority of 0. You can override this value by explicitly configuring the default project in `Projects` section with the chosen priority value.

## DESCRIPTION

Optional. Description of the project group.

The text can include any characters, including white space. The text can be extended to multiple lines by ending the preceding line with a backslash (\). The maximum length for the text is 64 characters.

Use `blinfo -G` to view hierarchical project group description.

## Projects section

### Description

Required. Lists the License Scheduler projects.

### Projects section structure

The `Projects` section begins and ends with the lines `Begin Projects` and `End Projects`. The second line consists of the required column heading `PROJECTS` and the optional column heading `PRI OR I TY`. Subsequent lines list participating projects, one name per line.

## Examples

The following example lists the projects without defining the priority:

```
Begin Projects PROJECTS Lp1 Lp2 Lp3 Lp4 ... End Projects
```

The following example lists the projects and defines the priority of each project:

```

Begin Projects
PROJECTS      PRIORITY
Lp1           3
Lp2           4
Lp3           2
Lp4           1
default      0
...
End Projects

```

## Parameters

- PROJECTS
- PRIORITY
- DESCRIPTION

## PROJECTS

Defines the name of each participating project. Specify using one name per line.

## PRIORITY

Optional. Defines the priority for each project where “0” is the lowest priority, and the higher number specifies a higher priority. This column overrides the default behavior. Instead of preempting in order the projects are listed under PROJECTS based on the accumulated inuse usage of each project, the projects are preempted according to the specified priority from lowest to highest.

When 2 projects have the same priority number configured, the first project listed has higher priority, like LSF queues.

Use `bl info -Lp` to view project priority information.

## Priority of default project

If not explicitly configured, the default project has the priority of 0. You can override this value by explicitly configuring the default project in Projects section with the chosen priority value.

## DESCRIPTION

Optional. Description of the project.

The text can include any characters, including white space. The text can be extended to multiple lines by ending the preceding line with a backslash (\). The maximum length for the text is 64 characters.

Use `bl info -Lp` to view the project description.

## Automatic time-based configuration

Variable configuration is used to automatically change LSF License Scheduler license token distribution policy configuration based on time windows. You define automatic configuration changes in `lsf.licensescheduler` by using if-else constructs and time expressions in the Feature section. After you change the file, check the configuration with the `bl admin`

ckconfi g command, and restart License Scheduler the cluster with the bl adm i n reconfi g command.

The expressions are evaluated by License Scheduler every 10 minutes based on the bl d start time. When an expression evaluates true, License Scheduler dynamically changes the configuration based on the associated configuration statements. Reconfiguration is done in real time without restarting bl d, providing continuous system availability.

## Example

```
Begin Feature
NAME = f1
#i f time(5: 16: 30- 1: 8: 30 20: 00- 8: 30)
DI STRI BUTI ON=Lan(P1 2/5 P2 1)
#el i f time(3: 8: 30- 3: 18: 30)
DI STRI BUTI ON=Lan(P3 1)
#el se
DI STRI BUTI ON=Lan(P1 1 P2 2/5)
#endi f
End Feature
```

# lsf.shared

The `lsf.shared` file contains common definitions that are shared by all load sharing clusters defined by `lsf.cluster.cluster_name` files. This includes lists of cluster names, host types, host models, the special resources available, and external load indices, including indices required to submit jobs using JSDL files.

This file is installed by default in the directory defined by `LSF_CONFDIR`.

## Changing lsf.shared configuration

After making any changes to `lsf.shared`, run the following commands:

- `lsadmin reconfig` to reconfigure LIM
- `badmin mbdrestart` to restart mbatchd

## Cluster section

(Required) Lists the cluster names recognized by the LSF system

## Cluster section structure

The first line must contain the mandatory keyword `ClusterName`. The other keyword is optional.

The first line must contain the mandatory keyword `ClusterName` and the keyword `Servers` in a `MultiCluster` environment.

Each subsequent line defines one cluster.

## Example Cluster section

```
Begin Cluster
ClusterName Servers
cluster1      hostA
cluster2      hostB
End Cluster
```

## ClusterName

Defines all cluster names recognized by the LSF system.

All cluster names referenced anywhere in the LSF system must be defined here. The file names of cluster-specific configuration files must end with the associated cluster name.

By default, if `MultiCluster` is installed, all clusters listed in this section participate in the same `MultiCluster` environment. However, individual clusters can restrict their `MultiCluster` participation by specifying a subset of clusters at the cluster level (`lsf.cluster.cluster_name RemoteClusters` section).

## Servers

`MultiCluster` only. List of hosts in this cluster that LIMs in remote clusters can connect to and obtain information from.

For other clusters to work with this cluster, one of these hosts must be running `mbatchd`.

## HostType section

(Required) Lists the valid host types in the cluster. All hosts that can run the same binary executable are in the same host type.

---

### Caution:

If you remove NTX86, NTX64, or NTIA64 from the HostType section, the functionality of `lspasswd.exe` is affected. The `lspasswd` command registers a password for a Windows user account.

---

## HostType section structure

The first line consists of the mandatory keyword `TYPENAME`.

Subsequent lines name valid host types.

## Example HostType section

```
Begin HostType
TYPENAME
SOL64
SOLSPARC
LI NUX86LI NUXPPC
LI NUX64
NTX86
NTX64
NTIA64
End HostType
```

## TYPENAME

Host type names are usually based on a combination of the hardware name and operating system. If your site already has a system for naming host types, you can use the same names for LSF.

## HostModel section

(Required) Lists models of machines and gives the relative CPU scaling factor for each model. All hosts of the same relative speed are assigned the same host model.

LSF uses the relative CPU scaling factor to normalize the CPU load indices so that jobs are more likely to be sent to faster hosts. The CPU factor affects the calculation of job execution time limits and accounting. Using large or inaccurate values for the CPU factor can cause confusing results when CPU time limits or accounting are used.

## HostModel section structure

The first line consists of the mandatory keywords `MODELNAME`, `CPUFACTOR`, and `ARCHITECTURE`.

Subsequent lines define a model and its CPU factor.

## Example HostModel section

```

Begin HostModel MODELNAME CPUFACTOR ARCHITECTURE
PC400 13.0 (i86pc_400 i686_400)
PC450 13.2 (i86pc_450 i686_450)
Sparc5F 3.0 (SUNWSPARCstation5_170_sparc)
Sparc20 4.7 (SUNWSPARCstation20_151_sparc)
Ultra5S 10.3 (SUNWUltra5_270_sparcv9 SUNWUltra510_270_sparcv9)
End HostModel

```

## ARCHITECTURE

(Reserved for system use only) Indicates automatically detected host models that correspond to the model names.

## CPUFACTOR

Though it is not required, you would typically assign a CPU factor of 1.0 to the slowest machine model in your system and higher numbers for the others. For example, for a machine model that executes at twice the speed of your slowest model, a factor of 2.0 should be assigned.

## MODELNAME

Generally, you need to identify the distinct host types in your system, such as MIPS and SPARC first, and then the machine models within each, such as SparcIPC, Sparc1, Sparc2, and Sparc10.

## About automatically detected host models and types

When you first install LSF, you do not necessarily need to assign models and types to hosts in `lsf.cluster.cluster_name`. If you do not assign models and types to hosts in `lsf.cluster.cluster_name`, LIM automatically detects the model and type for the host.

If you have versions earlier than LSF 4.0, you may have host models and types already assigned to hosts. You can take advantage of automatic detection of host model and type also.

Automatic detection of host model and type is useful because you no longer need to make changes in the configuration files when you upgrade the operating system or hardware of a host and reconfigure the cluster. LSF will automatically detect the change.

## Mapping to CPU factors

Automatically detected models are mapped to the short model names in `lsf.shared` in the ARCHITECTURE column. Model strings in the ARCHITECTURE column are only used for mapping to the short model names.

Example `lsf.shared` file:

```

Begin HostModel
MODELNAME CPUFACTOR ARCHITECTURE
SparcU5 5.0 (SUNWUltra510_270_sparcv9)
PC486 2.0 (i486_33 i486_66)
PowerPC 3.0 (PowerPC12 PowerPC16 PowerPC31)
End HostModel

```

If an automatically detected host model cannot be matched with the short model name, it is matched to the best partial match and a warning message is generated.

If a host model cannot be detected or is not supported, it is assigned the DEFAULT model name and an error message is generated.

## Naming convention

Models that are automatically detected are named according to the following convention:

*hardware\_platform* [*\_processor\_speed* [*\_processor\_type*]]

where:

- *hardware\_platform* is the only mandatory component
- *processor\_speed* is the optional clock speed and is used to differentiate computers within a single platform
- *processor\_type* is the optional processor manufacturer used to differentiate processors with the same speed
- Underscores ( `_` ) between *hardware\_platform*, *processor\_speed*, *processor\_type* are mandatory.

## Resource section

Optional. Defines resources (must be done by the LSF administrator).

## Resource section structure

The first line consists of the keywords. RESOURCENAME and DESCRIPTION are mandatory. The other keywords are optional. Subsequent lines define resources.

## Example Resource section

Begin Resource

| RESOURCENAME | TYPE    | INTERVAL | INCREASING | CONSUMABLE | DESCRIPTION                    | # Keywords |
|--------------|---------|----------|------------|------------|--------------------------------|------------|
| patchrev     | Numeric | ()       | Y          | ()         | (Patch revision)               |            |
| specman      | Numeric | ()       | N          | ()         | (Specman)                      |            |
| switch       | Numeric | ()       | Y          | N          | (Network Switch)               |            |
| rack         | String  | ()       | ()         | ()         | (Server room rack)             |            |
| owner        | String  | ()       | ()         | ()         | (Owner of the host)            |            |
| elimres      | Numeric | 10       | Y          | ()         | (elim generated index)         |            |
| ostype       | String  | ()       | ()         | ()         | (Operating system and version) |            |
| lmhostid     | String  | ()       | ()         | ()         | (FlexLM's lmhostid)            |            |
| limversion   | String  | ()       | ()         | ()         | (Version of LIM binary)        |            |

End Resource

## RESOURCENAME

The name you assign to the new resource. An arbitrary character string.

- A resource name cannot begin with a number.
- A resource name cannot contain any of the following characters:

: . ( ) [ + - \* / ! & | < > @ =

- A resource name cannot be any of the following reserved names:  

```
cpu cpuf io logins ls idle maxmem maxswp maxtmp type model status it
mem ncpus define_ncpus_cores define_ncpus_procs
define_ncpus_threads ndisks pg r15m r15s r1m swap swp tmp ut
```
- To avoid conflict with `inf` and `nan` keywords in 3rd-party libraries, resource names should not begin with `inf` or `nan` (upper case or lower case). Resource requirement strings, such as `-R "infra"` or `-R "nano"` will cause an error. Use `-R "defined(infxx)"` or `-R "defined(nanxx)"`, to specify these resource names.
- Resource names are case sensitive
- Resource names can be up to 39 characters in length
- For Solaris machines, the keyword `int` is reserved and cannot be used.

## TYPE

The type of resource:

- Boolean—Resources that have a value of 1 on hosts that have the resource and 0 otherwise.
- Numeric—Resources that take numerical values, such as all the load indices, number of processors on a host, or host CPU factor.
- String—Resources that take string values, such as host type, host model, host status.

## Default

If TYPE is not given, the default type is Boolean.

## INTERVAL

Optional. Applies to dynamic resources only.

Defines the time interval (in seconds) at which the resource is sampled by the ELIM.

If INTERVAL is defined for a numeric resource, it becomes an external load index.

## Default

If INTERVAL is not given, the resource is considered static.

## INCREASING

Applies to numeric resources only.

If a larger value means greater load, INCREASING should be defined as Y. If a smaller value means greater load, INCREASING should be defined as N.

## CONSUMABLE

Explicitly control if a resource is consumable. Applies to static or dynamic numeric resources.

Static and dynamic numeric resources can be specified as consumable. CONSUMABLE is optional. The defaults for the consumable attribute are:

- Built-in indicies:
  - The following are consumable: `r15s`, `r1m`, `r15m`, `ut`, `pg`, `io`, `ls`, `it`, `tmp`, `swp`, `mem`.
  - All other built-in static resources are not consumable. (e.g., `ncpus`, `ndisks`, `maxmem`, `maxswp`, `maxtmp`, `cpuf`, `type`, `model`, `status`, `rexpri`, `server`, `hname`).

- External shared resources:
  - All numeric resources are consumable.
  - String and boolean resources are not consumable.

You should only specify consumable resources in the `rusage` section of a resource requirement string. Non-consumable resources are ignored in `rusage` sections.

A non-consumable resource should not be releasable. Non-consumable numeric resource should be able to used in `order`, `select` and `same` sections of a resource requirement string.

When `LSF_STRICT_RESREQ=Y` in `lsf.conf`, LSF rejects resource requirement strings where an `rusage` section contains a non-consumable resource.

## DESCRIPTION

Brief description of the resource.

The information defined here will be returned by the `ls_info()` API call or printed out by the `lsinfo` command as an explanation of the meaning of the resource.

## RELEASE

Applies to numeric shared resources only, such as floating licenses.

Controls whether LSF releases the resource when a job using the resource is suspended. When a job using a shared resource is suspended, the resource is held or released by the job depending on the configuration of this parameter.

Specify `N` to hold the resource, or specify `Y` to release the resource.

## Default

Y

# lsf.sudoers

## About lsf.sudoers

The `lsf.sudoers` file is an optional file to configure security mechanisms. It is not installed by default.

You use `lsf.sudoers` to set the parameter `LSF_EAUTH_KEY` to configure a key for `eauth` to encrypt and decrypt user authentication data.

On UNIX, you also use `lsf.sudoers` to grant permission to users other than root to perform certain operations as root in LSF, or as a specified user.

These operations include:

- LSF daemon startup/shutdown
- User ID for LSF authentication
- User ID for LSF pre- and post-execution commands.
- User ID for external LSF executables

If `lsf.sudoers` does not exist, only root can perform these operations in LSF on UNIX.

On UNIX, this file is located in `/etc`.

There is one `lsf.sudoers` file per host.

On Windows, this file is located in the directory specified by the parameter `LSF_SECUREDIR` in `lsf.conf`.

## Changing lsf.sudoers configuration

After making any changes to `lsf.sudoers`, run `badmi n reconfi g` to reload the configuration files.

## lsf.sudoers on UNIX

In LSF, certain operations such as daemon startup can only be performed by root. The `lsf.sudoers` file grants root privileges to specific users or user groups to perform these operations.

### Location

`lsf.sudoers` must be located in `/etc` on each host.

### Permissions

`lsf.sudoers` must have permission 600 and be readable and writable only by root.

## lsf.sudoers on Windows

The `lsf.sudoers` file is shared over an NTFS network, not duplicated on every Windows host.

By default, LSF installs `lsf.sudoers` in the `%SYSTEMROOT%` directory.

The location of `lsf.sudoers` on Windows must be specified by `LSF_SECUREDIR` in `lsf.conf`. You must configure the `LSF_SECUREDIR` parameter in `lsf.conf` if using `lsf.sudoers` on Windows.

## Windows permissions

---

### Restriction:

The owner of `lsf.sudoers` on Windows be **Administrators**. If not, eauth may not work.

The permissions on `lsf.sudoers` for Windows are:

#### Workgroup Environment

- Local Admins (W)
- Everyone (R)

#### Domain Environment

- Domain Admins (W)
- Everyone (R)

## File format

The format of `lsf.sudoers` is very similar to that of `lsf.conf`.

Each entry can have one of the following forms:

- NAME=VALUE
- NAME=
- NAME= "STRING1 STRING2 . . ."

The equal sign = must follow each NAME even if no value follows and there should be no space beside the equal sign.

NAME describes an authorized operation.

VALUE is a single string or multiple strings separated by spaces and enclosed in quotation marks.

Lines starting with a pound sign (#) are comments and are ignored. Do not use `#if` as this is reserved syntax for time-based configuration.

## Example lsf.sudoers File

```
LSB_PRE_POST_EXEC_USER=user100
```

```
LSF_STARTUP_PATH=/usr/share/lsf/etc
```

```
LSF_STARTUP_USERS="user1 user10 user55"
```

## Creating and modifying lsf.sudoers

You can create and modify `lsf.sudoers` with a text editor.

After you modify `lsf.sudoers`, you must run `badm in hrest art al l` to restart all sbatchds in the cluster with the updated configuration.

## Parameters

- LSB\_PRE\_POST\_EXEC\_USER
- LSF\_EAUTH\_KEY
- LSF\_EAUTH\_USER
- LSF\_EEXEC\_USER
- LSF\_EGO\_ADMIN\_PASSWD
- LSF\_EGO\_ADMIN\_USER
- LSF\_LOAD\_PLUGINS

- LSF\_STARTUP\_PATH
- LSF\_STARTUP\_USERS

## LSB\_PRE\_POST\_EXEC\_USER

### Syntax

**LSB\_PRE\_POST\_EXEC\_USER**=*user\_name*

### Description

Specifies the UNIX user account under which pre- and post-execution commands run. This parameter applies only to pre- and post-execution commands configured at the application and queue levels; pre-execution commands defined at the job level with `bsub -E` run under the account of the user who submits the job.

You can specify only one user account. If the pre-execution or post-execution commands perform privileged operations that require root permissions on UNIX hosts, specify a value of `root`.

If you configure this parameter as `root`, the `LD_PRELOAD` and `LD_LIBRARY_PATH` variables are removed from the pre-execution, post-execution, and `eexec` environments for security purposes.

### Default

Not defined. Pre-execution and post-execution commands run under the user account of the user who submits the job.

## LSF\_EAUTH\_KEY

### Syntax

**LSF\_EAUTH\_KEY**=*key*

### Description

Applies to UNIX, Windows, and mixed UNIX/Windows clusters.

Specifies the key that `eauth` uses to encrypt and decrypt user authentication data. Defining this parameter enables increased security at your site. The key must contain at least six characters and must use only printable characters.

For UNIX, you must edit the `lsf.sudoers` file on all hosts within the cluster and specify the same encryption key. For Windows, you must edit the shared `lsf.sudoers` file.

### Default

Not defined. The `eauth` executable encrypts and decrypts authentication data using an internal key.

## LSF\_EAUTH\_USER

### Syntax

**LSF\_EAUTH\_USER**=*user\_name*

### Description

UNIX or Linux only.

Specifies the UNIX or Linux user account under which the external authentication executable `eauth` runs.

## Default

Not defined. The `eauth` executable runs under the account of the primary LSF administrator.

## LSF\_EEXEC\_USER

### Syntax

**LSF\_EEXEC\_USER**=*user\_name*

### Description

UNIX or Linux only.

Specifies the UNIX or Linux user account under which the external executable `eexec` runs.

## Default

Not defined. The `eexec` executable runs under root or the account of the user who submitted the job.

## LSF\_EGO\_ADMIN\_PASSWORD

### Syntax

**LSF\_EGO\_ADMIN\_PASSWORD**=*password*

### Description

When the EGO Service Controller (EGOSC) is configured to control LSF daemons, enables UNIX and Windows users to bypass the additional login required to start `res` and `sbatchd`. Bypassing the EGO administrator login enables the use of scripts to automate system startup.

Specify the Admin EGO cluster administrator password as clear text. You must also define the `LSF_EGO_ADMIN_USER` parameter.

## Default

Not defined. With EGOSC daemon control enabled, the `lsadm` and `lsbadmin` startup subcommands invoke the `egosh user logon` command to prompt for the Admin EGO cluster administrator credentials.

## LSF\_EGO\_ADMIN\_USER

### Syntax

**LSF\_EGO\_ADMIN\_USER**=Admin

### Description

When the EGO Service Controller (EGOSC) is configured to control LSF daemons, enables UNIX and Windows users to bypass the additional login required to start `res` and `sbatchd`. Bypassing the EGO administrator login enables the use of scripts to automate system startup.

Specify the Admin EGO cluster administrator account. You must also define the `LSF_EGO_ADMIN_PASSWORD` parameter.

## Default

Not defined. With EGOSC daemon control enabled, the `lsadm` and `lsbadmin` startup subcommands invoke the `egosh user logon` command to prompt for the Admin EGO cluster administrator credentials.

## LSF\_LOAD\_PLUGINS

### Syntax

`LSF_LOAD_PLUGINS=y | Y`

### Description

If defined, LSF loads plugins from `LSB_LSBDIR`. Used for Kerberos authentication and to enable the LSF cpuset plugin for IRIX.

## Default

Not defined. LSF does not load plugins.

## LSF\_STARTUP\_PATH

### Syntax

`LSF_STARTUP_PATH=path`

### Description

UNIX only. Enables the LSF daemon startup control feature when `LSF_STARTUP_USERS` is also defined. Define both parameters when you want to allow users other than root to start LSF daemons.

Specifies the absolute path name of the directory in which the LSF daemon binary files (`lim`, `res`, `sbatchd`, and `mbatchd`) are installed. LSF daemons are usually installed in the path specified by `LSF_SERVERDIR` defined in the `cshrc.lsf`, `profile.lsf` or `lsf.conf` files.

---

#### Important:

For security reasons, you should move the LSF daemon binary files to a directory other than `LSF_SERVERDIR` or `LSF_BINDIR`. The user accounts specified by `LSF_STARTUP_USERS` can start any binary in the `LSF_STARTUP_PATH`.

---

## Default

Not defined. Only the root user account can start LSF daemons.

## LSF\_STARTUP\_USERS

### Syntax

`LSF_STARTUP_USERS=all_admins | "user_name..."`

### Description

UNIX only. Enables the LSF daemon startup control feature when `LSF_STARTUP_PATH` is also defined. Define both parameters when you want to allow users other than root to start

LSF daemons. On Windows, the Platform services admin group is equivalent to LSF\_STARTUP\_USERS.

On UNIX hosts, by default only root can start LSF daemons. To manually start LSF daemons, a user runs the commands `lsadmi n` and `badmi n`, which have been installed as `setuid root`. LSF\_STARTUP\_USERS specifies a list of user accounts that can successfully run the commands `lsadmi n` and `badmi n` to start LSF daemons.

### all\_admins

- Allows all UNIX users defined as LSF administrators in the file `lsf.cluster.cluster_name` to start LSF daemons as root by running the `lsadmi n` and `badmi n` commands.
- Not recommended due to the security risk of a non-root LSF administrator adding to the list of administrators in the `lsf.cluster.cluster_name` file.
- Not required for Windows hosts because all users with membership in the Platform services admin group can start LSF daemons.

### "user\_name..."

- Allows the specified user accounts to start LSF daemons by running the `lsadmi n` and `badmi n` commands.
- Separate multiple user names with a space.
- For a single user, do not use quotation marks.

## Default

Not defined. Only the root user account can start LSF daemons.

## See also

LSF\_STARTUP\_PATH

# lsf.task

Users should not have to specify a resource requirement each time they submit a job. LSF supports the concept of a task list. This chapter describes the files used to configure task lists: `lsf.task`, `lsf.task.cluster_name`, and `.lsftask`.

## Changing task list configuration

After making any changes to the task list files, run the following commands:

- `lsadmin reconfig` to reconfigure LIM
- `badmin reconfig` to reload the configuration files

## About task lists

A task list is a list in LSF that keeps track of the default resource requirements for different applications and task eligibility for remote execution.

The term task refers to an application name. With a task list defined, LSF automatically supplies the resource requirement of the job whenever users submit a job unless one is explicitly specified at job submission.

LSF takes the job's command name as the task name and uses that name to find the matching resource requirement for the job from the task list. If a task does not have an entry in the task list, LSF assumes the default resource requirement; that is, a host that has the same host type as the submission host will be chosen to run the job.

An application listed in a task file is considered for load sharing by its placement in either the local tasks or remote tasks list.

- A local task is typically an application or command that it does not make sense to run remotely such as `ls`.
- A remote task is an application or command that can be run on another machine in the LSF cluster. The `compress` command is an example of a remote task.

Some applications require resources other than the default. LSF can store resource requirements for specific applications in remote task list files, so that LSF automatically chooses candidate hosts that have the correct resources available.

For frequently used commands and software packages, the LSF administrator can set up cluster-wide resource requirements that apply to all users in the cluster.

Users can modify and add to these requirements by setting up additional resource requirements that apply only to their own jobs.

## Cluster-wide resource requirements

The resource requirements of applications are stored in the remote task list file.

LSF automatically picks up a job's default resource requirement string from the remote task list files, unless you explicitly override the default by specifying the resource requirement string on the command line.

## User-level resource requirements

You may have applications that you need to control yourself. Perhaps your administrator did not set them up for load sharing for all users, or you need a non-standard setup. You can use LSF commands to find out resource names available in your system, and tell LSF about the needs of your applications. LSF stores the resource requirements for you from then on.

You can specify resource requirements when tasks are added to the user's remote task list. If the task to be added is already in the list, its resource requirements are replaced.

```
lsrtasks + myjob/swap>=100 && cpu
```

This adds myjob to the remote tasks list with its resource requirements.

## Task files

There are 3 task list files that can affect a job:

- `lsf.task` — system-wide defaults apply to all LSF users, even across multiple clusters if MultiCluster is installed
- `lsf.task.cluster_name` — cluster-wide defaults apply to all users in the cluster
- `$HOME/.lsftask` — user-level defaults apply to a single user. This file lists applications to be added to or removed from the default system lists for your jobs. Resource requirements specified in this file override those in the system lists.

The clusterwide task file is used to augment the systemwide file. The user's task file is used to augment the systemwide and clusterwide task files.

LSF combines the systemwide, clusterwide, and user-specific task lists for each user's view of the task list. In cases of conflicts, such as different resource requirements specified for the same task in different lists, the clusterwide list overrides the systemwide list, and the user-specific list overrides both.

### LSF\_CONFDIR/lsf.task

Systemwide task list applies to all clusters and all users.

This file is used in a MultiCluster environment.

### LSF\_CONFDIR/lsf.task.cluster\_name

Clusterwide task list applies to all users in the same cluster.

### \$HOME/.lsftask

User task list, one per user, applies only to the specific user. This file is automatically created in the user's home directory whenever a user first updates his task lists using the `lsrtasks` or `lsltasks` commands. For details about task eligibility lists, see the `ls_task(3)` API reference man page.

## Permissions

Only the LSF administrator can modify the systemwide task list (`lsf.task`) and the clusterwide task list (`lsf.task.cluster_name`).

A user can modify his own task list (`.lsftask`) with the `lsrtasks` and `lsltasks` commands.

## Format of task files

Each file consists of two sections, Local Tasks and RemoteTasks. For example:

```

Begin LocalTasks
ps
hostname
uname
crontab
End LocalTasks
Begin RemoteTasks
+ "newjob/mem>25"
+ "verilog/select[type==any && swp>100]"
make/cpu
nroff/-
End RemoteTasks

```

Tasks are listed one per line. Each line in a section consists of a task name, and, for the RemoteTasks section, an optional resource requirement string separated by a slash (/).

A plus sign (+) or a minus sign (-) can optionally precede each entry. If no + or - is specified, + is assumed.

A + before a task name means adding a new entry (if non-existent) or replacing an entry (if already existent) in the task list. A - before a task name means removing an entry from the application's task lists if it was already created by reading higher level task files.

## LocalTasks section

The section starts with `Begin LocalTasks` and ends with `End LocalTasks`.

This section lists tasks that are not eligible for remote execution, either because they are trivial tasks or because they need resources on the local host.

## RemoteTasks section

The section starts with `Begin RemoteTasks` and ends with `End RemoteTasks`.

This section lists tasks that are eligible for remote execution. You can associate resource requirements with each task name.

See *Administering Platform LSF* for information about resource requirement strings. If the resource requirement string is not specified for a remote task, the default is `select [type==local] order[r15s:pg]`.

# setup.config

## About setup.config

The `setup.config` file contains options for Platform LSF License Scheduler installation and configuration for systems without Platform LSF. You only need to edit this file if you are installing License Scheduler as a standalone product without LSF.

## Template location

A template `setup.config` is included in the License Scheduler installation script tar file and is located in the directory created when you uncompress and extract the installation script tar file. Edit the file and uncomment the options you want in the template file. Replace the example values with your own settings to specify the options for your new License Scheduler installation.

---

### Important:

The sample values in the `setup.config` template file are examples only. They are not default installation values.

---

After the License Scheduler installation, the `setup.config` containing the options you specified is located in `LS_TOP/7.0/install/`.

## Format

Each entry in `setup.config` has the form:

```
NAME="STRING1 STRING2 ..."
```

The equal sign = must follow each NAME even if no value follows and there should be no spaces around the equal sign.

A value that contains multiple strings separated by spaces must be enclosed in quotation marks.

Blank lines and lines starting with a pound sign (#) are ignored.

## Parameters

- LS\_ADMIN
- LS\_HOSTS
- LS\_LICENSE\_FILE
- LS\_LMSTAT\_PATH
- LS\_TOP

## LS\_ADMIN

### Syntax

```
LS_ADMIN="user_name [user_name ...]"
```

### Description

Lists the License Scheduler administrators. The first user account name in the list is the primary License Scheduler administrator.

The primary License Scheduler administrator account is typically named `lsadmin`.

---

**Caution:**

You should *not* configure the root account as the primary License Scheduler administrator.

---

## Valid Values

User accounts for License Scheduler administrators must exist on all hosts using License Scheduler prior to installation.

## Example

```
LS_ADMINS="lsadmin user1 user2"
```

## Default

The user running the License Scheduler installation script.

## LS\_HOSTS

### Syntax

```
LS_HOSTS="host_name [host_name ... ]"
```

## Description

Defines a list of hosts that are candidates to become License Scheduler master hosts. Provide at least one host from which the License Scheduler daemon will run.

## Valid Values

Any valid License Scheduler host name.

## Example

```
LS_HOSTS="host_name1 host_name2"
```

## Default

The local host in which the License Scheduler installation script is running.

## LS\_LICENSE\_FILE

### Syntax

```
LS_LICENSE_FILE="/path/license_file"
```

## Description

Defines the full path to, and name of the License Scheduler license file.

## Valid Values

Any valid file name and directory path.

## Example

```
LS_LICENSE_FILE="/usr/share/ls/conf/license.dat"
```

## Default

`$LS_TOP/conf/license.dat`

## LS\_LMSTAT\_PATH

### Syntax

```
LS_LMSTAT_PATH="/path"
```

### Description

Defines the full path to the `lmstat` program. License Scheduler uses `lmstat` to gather the FLEXlm license information for scheduling. This path does not include the name of the `lmstat` program itself.

### Example

```
LS_LMSTAT_PATH="/usr/bin"
```

## Default

The installation script attempts to find a working copy of `lmstat` on the current system. If it is unsuccessful, the path is set as blank (`""`).

## LS\_TOP

### Syntax

```
LS_TOP="/path"
```

### Description

Defines the full path to the top level License Scheduler installation directory.

### Valid Values

Must be an absolute path to a shared directory that is accessible to all hosts using License Scheduler. Cannot be the root directory (`/`).

### Recommended Value

The file system containing `LS_TOP` must have enough disk space for all host types (approximately 300 MB per host type).

### Example

```
LS_TOP="/usr/share/lis"
```

## Default

None — required variable

# slave.config

## About slave.config

Dynamically added LSF hosts that will not be master candidates are *slave hosts*. Each dynamic slave host has its own LSF binaries and local `lsf.conf` and shell environment scripts (`cshrc.lsf` and `profile.lsf`). You must install LSF on each slave host.

The `slave.config` file contains options for installing and configuring a slave host that can be dynamically added or removed.

Use `lsfinstall -s -f slave.config` to install LSF using the options specified in `slave.config`.

## Template location

A template `slave.config` is located in the installation script directory created when you extract the LSF installation script tar file. Edit the file and uncomment the options you want in the template file. Replace the example values with your own settings to specify the options for your new LSF installation.

---

### Important:

The sample values in the `slave.config` template file are examples only. They are not default installation values.

---

## Format

Each entry in `slave.config` has the form:

```
NAME="STRING1 STRING2 ..."
```

The equal sign = must follow each NAME even if no value follows and there should be no spaces around the equal sign.

A value that contains multiple strings separated by spaces must be enclosed in quotation marks.

Blank lines and lines starting with a pound sign (#) are ignored.

## Parameters

- EGO\_DAEMON\_CONTROL
- ENABLE\_EGO
- EP\_BACKUP
- LSF\_ADMINS
- LSF\_LIM\_PORT
- LSF\_SERVER\_HOSTS
- LSF\_TARDIR
- LSF\_LOCAL\_RESOURCES
- LSF\_TOP

## EGO\_DAEMON\_CONTROL

### Syntax

```
EGO_DAEMON_CONTROL="Y" | "N"
```

## Description

Enables Platform EGO to control LSF res and sbatchd. Set the value to "Y" if you want EGO Service Controller to start res and sbatchd, and restart if they fail.

All hosts in the cluster must use the same value for this parameter (this means the value of EGO\_DAEMON\_CONTROL in this file must be the same as the specification for EGO\_DAEMON\_CONTROL in `install.config`).

To avoid conflicts, leave this parameter undefined if you use a script to start up LSF daemons.

---

### Note:

If you specify EGO\_ENABLE="N", this parameter is ignored.

---

## Example

```
EGO_DAEMON_CONTROL="N"
```

## Default

N (res and sbatchd are started manually)

## ENABLE\_EGO

## Syntax

```
ENABLE_EGO="Y" | "N"
```

## Description

Enables Platform EGO functionality in the LSF cluster.

ENABLE\_EGO="Y" causes `lsfi nstal l` to uncomment LSF\_EGO\_ENVDIR and sets LSF\_ENABLE\_EGO="Y" in `lsf.conf`.

ENABLE\_EGO="N" causes `lsfi nstal l` to comment out LSF\_EGO\_ENVDIR and sets LSF\_ENABLE\_EGO="N" in `lsf.conf`.

Set the value to "N" if you do not want to take advantage of the following LSF features that depend on EGO:

- LSF daemon control by EGO Service Controller
- EGO-enabled SLA scheduling
- Platform Management Console (PMC)
- LSF reporting

## Default

Y (EGO is enabled in the LSF cluster)

## EP\_BACKUP

## Syntax

```
EP_BACKUP="Y" | "N"
```

## Description

Enables backup and rollback for enhancement packs. Set the value to "N" to disable backups when installing enhancement packs (you will not be able to roll back to the previous patch level after installing an EP, but you will still be able to roll back any fixes installed on the new EP).

You may disable backups to speed up install time, to save disk space, or because you have your own methods to back up the cluster.

## Default

Y (backup and rollback are fully enabled)

## LSF\_ADMINS

### Syntax

```
LSF_ADMINS="user_name [ user_name ... ]"
```

## Description

Required. List of LSF administrators.

The first user account name in the list is the primary LSF administrator. It cannot be the root user account.

Typically this account is named `lsfadmin`. It owns the LSF configuration files and log files for job events. It also has permission to reconfigure LSF and to control batch jobs submitted by other users. It typically does not have authority to start LSF daemons. Usually, only root has permission to start LSF daemons.

All the LSF administrator accounts must exist on all hosts in the cluster before you install LSF. Secondary LSF administrators are optional.

## Valid Values

Existing user accounts

## Example

```
LSF_ADMINS="lsfadmin user1 user2"
```

## Default

None—required variable

## LSF\_LIM\_PORT

### Syntax

```
LSF_LIM_PORT="port_number"
```

## Description

TCP service port for slave host.

Use the same port number as `LSF_LIM_PORT` in `lsf.conf` on the master host.

## Default

7869

## LSF\_SERVER\_HOSTS

### Syntax

```
LSF_SERVER_HOSTS="host_name [host_name ...]"
```

### Description

Required for non-shared slave host installation. This parameter defines a list of hosts that can provide host and load information to client hosts. If you do not define this parameter, clients will contact the master LIM for host and load information. List of LSF server hosts in the cluster to be contacted.

Recommended for large clusters to decrease the load on the master LIM. Do not specify the master host in the list. Client commands will query the LIMs on the LSF\_SERVER\_HOSTS, which off-loads traffic from the master LIM.

Define this parameter to ensure that commands execute successfully when no LIM is running on the local host, or when the local LIM has just started.

You should include the list of hosts defined in LSF\_MASTER\_LIST in `lsf.conf`; specify the primary master host last. For example:

```
LSF_MASTER_LIST="lsfmaster hostE"
```

```
LSF_SERVER_HOSTS="hostB hostC hostD hostE lsfmaster"
```

Specify a list of host names two ways:

- Host names separated by spaces
- Name of a file containing a list of host names, one host per line.

### Valid Values

Any valid LSF host name

### Examples

List of host names:

```
LSF_SERVER_HOSTS="hosta hostb hostc hostd"
```

Host list file:

```
LSF_SERVER_HOSTS=:lsf_server_hosts
```

The file `lsf_server_hosts` contains a list of hosts:

```
hosta hostb hostc hostd
```

## Default

None

## LSF\_TARDIR

### Syntax

```
LSF_TARDIR="lpath"
```

slave.config

## Description

Full path to the directory containing the LSF distribution tar files.

## Example

```
LSF_TARDIR="/usr/local/lsf_distribution"
```

## Default

The parent directory of the current working directory. For example, if `lsfi nst all` is running under `usr/share/lsf_distribution/lsf_lsfi nst all` the LSF\_TARDIR default value is `usr/share/lsf_distribution`.

## LSF\_LOCAL\_RESOURCES

### Syntax

```
LSF_LOCAL_RESOURCES="resource ..."
```

### Description

Defines instances of local resources residing on the slave host.

- For numeric resources, define name-value pairs:  

```
"[resourcemap value*resource_name]"
```
- For Boolean resources, define the resource name in the form:  

```
"[resource resource_name]"
```

When the slave host calls the master host to add itself, it also reports its local resources. The local resources to be added must be defined in `lsf.shared`.

If the same resource is already defined in `lsf.shared` as default or all, it cannot be added as a local resource. The shared resource overrides the local one.

---

#### Tip:

LSF\_LOCAL\_RESOURCES is usually set in the `slave.config` file during installation. If LSF\_LOCAL\_RESOURCES are already defined in a local `lsf.conf` on the slave host, `lsfi nst all` does not add resources you define in LSF\_LOCAL\_RESOURCES in `slave.config`. You should not have duplicate LSF\_LOCAL\_RESOURCES entries in `lsf.conf`. If local resources are defined more than once, only the last definition is valid.

---

#### Important:

Resources must already be mapped to hosts in the ResourceMap section of `lsf.cluster.cluster_name`. If the ResourceMap section does not exist, local resources are not added.

## Example

```
LSF_LOCAL_RESOURCES="[resourcemap 1*verilog] [resource linux]"
```

## Default

None

## LSF\_TOP

## Syntax

```
LSF_TOP="/path"
```

## Description

Required. Full path to the top-level LSF installation directory.

---

**Important:**

You must use the same path for every slave host you install.

## Valid value

The path to LSF\_TOP cannot be the root directory (/).


## Example

```
LSF_TOP="/usr/local/lsf"
```

## Default

None—required variable

slave.config



# Environment Variables



# Environment variables

## Environment variables set for job execution

LSF transfers most environment variables between submission and execution hosts.

Environment variables related to file names and job spooling directories support paths that contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows.

Environment variables related to command names and job names can contain up to 4094 characters for UNIX and Linux, or up to 255 characters for Windows.

In addition to environment variables inherited from the user environment, LSF also sets several other environment variables for batch jobs:

- **LSB\_ERRORFILE:** Name of the error file specified with a `bsub -e`.
- **LSB\_JOBID:** job ID assigned by LSF.
- **LSB\_JOBINDEX:** Index of the job that belongs to a job array.
- **LSB\_CHKPNT\_DIR:** This variable is set each time a checkpointed job is submitted. The value of the variable is *chkpnt\_dir/job\_Id*, a subdirectory of the checkpoint directory that is specified when the job is submitted. The subdirectory is identified by the job ID of the submitted job.
- **LSB\_HOSTS:** The list of hosts that are used to run the batch job. For sequential jobs, this is only one host name. For parallel jobs, this includes multiple host names.
- **LSB\_RESIZABLE:** Indicates that a job is resizable or auto-resizable.
- **LSB\_QUEUE:** The name of the queue the job is dispatched from.
- **LSB\_JOBNAME:** Name of the job.
- **LSB\_RESTART:** Set to 'Y' if the job is a restarted job or if the job has been migrated. Otherwise this variable is not defined.
- **LSB\_EXIT\_PRE\_ABORT:** Set to an integer value representing an exit status. A pre-execution command should exit with this value if it wants the job to be aborted instead of requeued or executed.
- **LSB\_EXIT\_REQUEUE:** Set to the `REQUEUE_EXIT_VALUES` parameter of the queue. This variable is not defined if `REQUEUE_EXIT_VALUES` is not configured for the queue.
- **LSB\_INTERACTIVE:** Set to 'Y' if the job is submitted with the `-I` option. Otherwise, it is not defined.
- **LS\_JOBPID:** Set to the process ID of the job.
- **LS\_SUBCWD:** This is the directory on the submission when the job was submitted. This is different from `PWD` only if the directory is not shared across machines or when the execution account is different from the submission account as a result of account mapping.
- **LSB\_BIND\_JOB:** Set to the value of binding option. But when the binding option is `USER`, `LSB_BIND_JOB` is set to the real binding decision of end user.

---

### Note:

If the binding option is `Y`, `LSB_BIND_JOB` is set to `BALANCE`.

If the binding option is `N`, `LSB_BIND_JOB` is set to `NONE`.

---

- **LSB\_BIND\_CPU\_LIST:** Set to the actual CPU list used when the job is sequential job and single host parallel job.

If the job is a multi-host parallel job, `LSB_BIND_CPU_LIST` is set to the value in submission environment variable `$LSB_USER_BIND_CPU_LIST`. If there is no such

submission environment variable in user's environment, `LSB_BIND_CPU_LIST` is set to an empty string.

## Environment variables for notification command

The following environment variables apply only to the notification command environment:

- `LSB_RESIZE_NOTIFY_OK`: A notification command should exit with this variable if the allocation resize notification command succeeds.

LSF updates the job allocation to reflect the new allocation.

- `LSB_RESIZE_NOTIFY_FAIL`: A notification command should exit with this variable if the allocation resize notification command fails.

For an allocation grow event, LSF schedules the pending allocation request.

For an allocation shrink event, LSF fails the release request.

- `LSB_RESIZE_EVENT = grow | shrink`: Indicates why the notification command was called. Grow means add more resources to an existing allocation. Shrink means remove some resources from existing allocation.
- `LSB_RESIZE_HOSTS = hostA numA hostB numB ... hostZ numZ`: Lists the additional slots for a grow event, or the released slots for a shrink event.

## Environment variable reference

|                                      |                                       |                                        |
|--------------------------------------|---------------------------------------|----------------------------------------|
| <code>BSUB_BLOCK</code>              | <code>BSUB_CHK_RESREQ</code>          |                                        |
| <code>BSUB_QUIET</code>              | <code>BSUB_QUIET2</code>              |                                        |
| <code>BSUB_STDERR</code>             | <code>CLEARCASE_DRIVE</code>          | <code>CLEARCASE_MOUNTDIR</code>        |
| <code>CLEARCASE_ROOT</code>          | <code>ELIM_ABORT_VALUE</code>         | <code>LM_LICENSE_FILE</code>           |
| <code>LS_EXEC_T</code>               | <code>LS_JOBPID</code>                | <code>LS_LICENSE_SERVER_feature</code> |
| <code>LS_SUBCWD</code>               | <code>LSB_CHKPNT_DIR</code>           | <code>LSB_DEBUG</code>                 |
| <code>LSB_DEBUG_CMD</code>           | <code>LSB_DEBUG_MBD</code>            | <code>LSB_DEBUG_NQS</code>             |
| <code>LSB_DEBUG_SBD</code>           | <code>LSB_DEBUG_SCH</code>            | <code>LSB_DEFAULT_JOBGROUP</code>      |
| <code>LSB_DEFAULTPROJECT</code>      | <code>LSB_DEFAULTQUEUE</code>         | <code>LSB_DJOB_COMMFAIL_ACTION</code>  |
| <code>LSB_DJOB_ENV_SCRIPT</code>     | <code>LSB_ECHKPNT_METHOD</code>       | <code>LSB_ECHKPNT_METHOD_DIR</code>    |
| <code>LSB_ECHKPNT_KEEP_OUTPUT</code> | <code>LSB_ERESTART_USRCMD</code>      | <code>LSB_EXEC_RUSAGE</code>           |
| <code>LSB_EXECHOSTS</code>           | <code>LSB_EXIT_IF_CWD_NOTEXIST</code> | <code>LSB_EXIT_PRE_ABORT</code>        |
| <code>LSB_EXIT_REQUEUE</code>        | <code>LSB_FRAMES</code>               | <code>LSB_HOSTS</code>                 |
| <code>LSB_INTERACTIVE</code>         | <code>LSB_JOB_INCLUDE_POSTPROC</code> | <code>LSB_JOBEXIT_INFO</code>          |
| <code>LSB_JOBEXIT_STAT</code>        | <code>LSB_JOBFILENAME</code>          | <code>LSB_JOBGROUP</code>              |
| <code>LSB_JOBID</code>               | <code>LSB_JOBINDEX</code>             | <code>LSB_JOBINDEX_STEP</code>         |
| <code>LSB_JOBNAME</code>             | <code>LSB_JOBPEND</code>              | <code>LSB_JOBPGIDS</code>              |

|                                 |                            |                        |
|---------------------------------|----------------------------|------------------------|
| LSB_JOBPIIDS                    | LSB_MAILSIZE               | LSB_MCPU_HOSTS         |
| LSB_NQS_PORT                    | LSB_NTRIES                 | LSB_OLD_JOBID          |
| LSB_OUTPUT_TARGETFAILED         | LSB_QUEUE                  | LSB_REMOTEINDEX        |
| LSB_REMOTEJID                   | LSB_RESIZABLE              | LSB_RESIZE_NOTIFY_OK   |
| LSB_RESIZE_NOTIFY_FAIL          | LSB_RESTART_PGID           | LSB_RESTART            |
| LSB_RESTART_PID                 | LSB_RTASK_GONE_ACTION      | LSB_SUB_APP_NAME       |
| LSB_SUB_CLUSTER                 | LSB_SUB_COMMAND_LINE       | LSB_SUB_EXTSCHED_PARAM |
| LSB_SUB_JOB_ACTION_WARNING_TIME | LSB_SUB_JOB_WARNING_ACTION | LSB_SUB_PARM_FILE      |
| LSB_SUCCESS_EXIT_VALUES         | LSB_SUSP_REASONS           | LSB_SUSP_SUBREASONS    |
| LSB_UNIXGROUP                   | LSB_USER_BIND_CPU_LIST     | LSB_USER_BIND_JOB      |
|                                 | LSF_CMD_LOGDIR             | LSF_DEBUG_CMD          |
| LSF_DEBUG_LIM                   | LSF_DEBUG_RES              | LSF_EAUTH_AUX_DATA     |
| LSF_EAUTH_AUX_PASS              | LSF_EAUTH_CLIENT           | LSF_EAUTH_SERVER       |
| LSF_EAUTH_UID                   | LSF_EXECUTE_DOMAIN         | LSF_INTERACTIVE_STDERR |
| LSF_INVOKE_CMD                  | LSF_JOB_STARTER            | LSF_LD_PRELOAD         |
| LSF_LD_LIBRARY_PATH             | LSF_LIM_API_NTRIES         | LSF_LIM_DEBUG          |
| LSF_LOGDIR                      | LSF_MASTER                 | LSF_NIOS_DEBUG         |
| LSF_NIOS_DIE_CMD                | LSF_NIOS_IGNORE_SIGWINDOW  | LSF_NIOS_PEND_TIMEOUT  |
| LSF_NIOS_PORT_RANGE             | LSF_RESOURCES              | LSF_TS_LOGON_TIME      |
| LSF_USE_HOSTEQUIV               | LSF_USER_DOMAIN            |                        |

## BSUB\_BLOCK

### Description

If set, tells NIOS that it is running in batch mode.

### Default

Not defined

### Notes

If you submit a job with the `-K` option of `bsub`, which is synchronous execution, then `BSUB_BLOCK` is set. Synchronous execution means you have to wait for the job to finish before you can continue.

## Where defined

Set internally

## See also

The -K option of bsub

## BSUB\_CHK\_RESREQ

### Syntax

**BSUB\_CHK\_RESREQ=*any\_value***

### Description

When `BSUB_CHK_RESREQ` is set, `bsub` checks the syntax of the resource requirement selection string without actually submitting the job for scheduling and dispatch. Use `BSUB_CHK_RESREQ` to check the compatibility of your existing resource requirement select strings against the stricter syntax enabled by `LSF_STRICT_RESREQ=y` in `lsf.conf`. `LSF_STRICT_RESREQ` does not need to be set to check the resource requirement selection string syntax.

`bsub` only checks the select section of the resource requirement. Other sections in the resource requirement string are not checked.

### Default

Not defined

## Where defined

From the command line

## Example

`BSUB_CHK_RESREQ=1`

## BSUB\_QUIET

### Syntax

**BSUB\_QUIET=*any\_value***

### Description

Controls the printing of information about job submissions. If set, `bsub` will not print any information about job submission. For example, it will not print `<Job is submitted to default queue <normal>, nor <Waiting for dispatch>`.

### Default

Not defined

## Where defined

From the command line

## Example

```
BSUB_QUIET=1
```

## BSUB\_QUIET2

### Syntax

**BSUB\_QUIET2=any\_value**

### Description

Suppresses the printing of information about job completion when a job is submitted with the `bsub -K` option.

If set, `bsub` will not print information about job completion to `stdout`. For example, when this variable is set, the message `<<Job is finished>>` will not be written to `stdout`.

If `BSUB_QUIET` and `BSUB_QUIET2` are both set, no job messages will be printed to `stdout`.

### Default

Not defined

## Where defined

From the command line

## Example

```
BSUB_QUIET2=1
```

## BSUB\_STDERR

### Syntax

**BSUB\_STDERR=y**

### Description

Redirects LSF messages for `bsub` to `stderr`.

By default, when this parameter is not set, LSF messages for `bsub` are printed to `stdout`.

When this parameter is set, LSF messages for `bsub` are redirected to `stderr`.

### Default

Not defined

## Where defined

From the command line on UNIX. For example, in `csh`:

```
setenv BSUB_STDERR Y
```

From the Control Panel on Windows, as an environment variable

## CLEARCASE\_DRIVE

### Syntax

```
CLEARCASE_DRIVE=drive_letter:
```

### Description

Optional, Windows only.

Defines the virtual drive letter for a Rational ClearCase view to the drive. This is useful if you wish to map a Rational ClearCase view to a virtual drive as an alias.

If this letter is unavailable, Windows attempts to map to another drive. Therefore, CLEARCASE\_DRIVE only defines the default drive letter to which the Rational ClearCase view is mapped, not the final selected drive letter. However, the PATH value is automatically updated to the final drive letter if it is different from CLEARCASE\_DRIVE.

### Notes:

CLEARCASE\_DRIVE is case insensitive.

### Where defined

From the command line

### Example

```
CLEARCASE_DRIVE=F:
```

```
CLEARCASE_DRIVE=f:
```

### See also

CLEARCASE\_MOUNTDIR, CLEARCASE\_ROOT

## CLEARCASE\_MOUNTDIR

### Syntax

```
CLEARCASE_MOUNTDIR=path
```

### Description

Optional.

Defines the Rational ClearCase mounting directory.

### Default

```
/vobs
```

## Notes:

CLEARCASE\_MOUNTDIR is used if any of the following conditions apply:

- A job is submitted from a UNIX environment but run in a Windows host.
- The Rational ClearCase mounting directory is not the default /vobs

## Where defined

From the command line

## Example

```
CLEARCASE_MOUNTDIR=/myvobs
```

## See also

CLEARCASE\_DRIVE, CLEARCASE\_ROOT

## CLEARCASE\_ROOT

### Syntax

```
CLEARCASE_ROOT=path
```

### Description

The path to the Rational ClearCase view.

In Windows, this path must define an absolute path starting with the default ClearCase drive and ending with the view name without an ending backslash (\).

### Notes

CLEARCASE\_ROOT must be defined if you want to submit a batch job from a ClearCase view.

For interactive jobs, use `bsub -I` to submit the job.

## Where defined

In the job starter, or from the command line

## Example

In UNIX:

```
CLEARCASE_ROOT=/view/myview
```

In Windows:

```
CLEARCASE_ROOT=F:\myview
```

## See also

CLEARCASE\_DRIVE, CLEARCASE\_MOUNTDIR, LSF\_JOB\_STARTER

## ELIM\_ABORT\_VALUE

### Syntax

**ELIM\_ABORT\_VALUE**

### Description

Used when writing an `elim` executable to test whether the `elim` should run on a particular host. If the host does not have or share any of the resources listed in the environment variable `LSF_RESOURCES`, your `elim` should exit with `$ELIM_ABORT_VALUE`.

When the MELIM finds an `elim` that exited with `ELIM_ABORT_VALUE`, the MELIM marks the `elim` and does not restart it on that host.

### Where defined

Set by the master `elim` (MELIM) on the host when the MELIM invokes the `elim` executable

## LM\_LICENSE\_FILE

### Syntax

**LM\_LICENSE\_FILE=***file\_name*

### Description

The path to where the license file is found. The file name is the name of the license file.

### Default

`/usr/share/flexlm/licenses/license.dat`

### Notes

A FLEXlm variable read by the `lmgrd` daemon.

### Where defined

From the command line

### See also

`LSF_LICENSE_FILE` in `lsf.conf`

## LS\_EXEC\_T

### Syntax

**LS\_EXEC\_T=**START | END | CHPNT | JOB\_CONTROLS

### Description

Indicates execution type for a job. `LS_EXEC_T` is set to:

- START or END for a job when the job begins executing or when it completes execution

- CHKPNT when the job is checkpointed
- JOB\_CONTROLS when a control action is initiated

## Where defined

Set by sbatchd during job execution

## LS\_JOBPID

### Description

The process ID of the job.

## Where defined

During job execution, sbatchd sets LS\_JOBPID to be the same as the process ID assigned by the operating system.

## LS\_LICENSE\_SERVER\_*feature*

### Syntax

**LS\_LICENSE\_SERVER\_*feature***=*"domain.server.num\_available ..."*

*server* is of the format *port@host*

### Description

The license server information provided to the job. The purpose of this environment variable is to provide license server information to the job.

## Where defined

During the license job execution, sbatchd sets LS\_LICENSE\_SERVER\_*feature* to be the same as the license server information defined in the job's rusage string. This is only used by the job and logged in the mbatchd log file if DEBUG1 and LC\_LICSCHEM are defined in lsf.conf.

## LS\_SUBCWD

### Description

The current working directory (cwd) of the submission host where the remote task command was executed.

The current working directory can be up to 4094 characters long for UNIX and Linux or up to 255 characters for Windows.

## How set

1. LSF looks for the PWD environment variable. If it finds it, sets LS\_SUBCWD to PWD.
2. If the PWD environment variable does not exist, LSF looks for the CWD environment variable. If it finds CWD, sets LS\_SUBCWD to CWD.

3. If the CWD environment variable does not exist, LSF calls the `getwd()` system function to retrieve the current working directory path name. LSF sets `LS_SUBCWD` to the value that is returned.

## Where defined

Set by `sbatchd`

## LSB\_CHKPNT\_DIR

### Syntax

`LSB_CHKPNT_DIR=checkpoint_dir/job_ID`

### Description

The directory containing files related to the submitted checkpointable job.

### Valid values

The value of `checkpoint_dir` is the directory you specified through the `-k` option of `bsub` when submitting the checkpointable job.

The value of `job_ID` is the job ID of the checkpointable job.

## Where defined

Set by LSF, based on the directory you specified when submitting a checkpointable job with the `-k` option of `bsub`.

## LSB\_DEBUG

This parameter can be set from the command line or from `lsf.conf`. See `LSB_DEBUG` in `lsf.conf`.

## LSB\_DEBUG\_CMD

This parameter can be set from the command line or from `lsf.conf`. See `LSB_DEBUG_CMD` in `lsf.conf`.

## LSB\_DEBUG\_MBD

This parameter can be set from the command line with `badmin mbddebug` or from `lsf.conf`.

See `LSB_DEBUG_MBD` in `lsf.conf`.

## LSB\_DEBUG\_NQS

This parameter can be set from the command line or from `lsf.conf`. See `LSB_DEBUG_NQS` in `lsf.conf`.

## LSB\_DEBUG\_SBD

This parameter can be set from the command line with `badmin sbddebug` or from `lsf.conf`.

See `LSB_DEBUG_SBD` in `lsf.conf`.

## LSB\_DEBUG\_SCH

This parameter can be set from the command line or from `lsf.conf`. See `LSB_DEBUG_SCH` in `lsf.conf`.

## LSB\_DEFAULT\_JOBGROUP

### Syntax

`LSB_DEFAULT_JOBGROUP=job_group_name`

### Description

The name of the default job group.

When you submit a job to LSF without explicitly specifying a job group, LSF associates the job with the specified job group. `LSB_DEFAULT_JOBGROUP` overrides the setting of `DEFAULT_JOBGROUP` in `lsb.params`. The `bsub -g job_group_name` option overrides both `LSB_DEFAULT_JOBGROUP` and `DEFAULT_JOBGROUP`.

If you submit a job without the `-g` option of `bsub`, but you defined `LSB_DEFAULT_JOBGROUP`, then the job belongs to the job group specified in `LSB_DEFAULT_JOBGROUP`.

Job group names must follow this format:

- Job group names must start with a slash character (/). For example, `LSB_DEFAULT_JOBGROUP=/A/B/C` is correct, but `LSB_DEFAULT_JOBGROUP=A/B/C` is not correct.
- Job group names cannot end with a slash character (/). For example, `LSB_DEFAULT_JOBGROUP=/A/` is not correct.
- Job group names cannot contain more than one slash character (/) in a row. For example, job group names like `LSB_DEFAULT_JOBGROUP=/A//B` or `LSB_DEFAULT_JOBGROUP=A///B` are not correct.
- Job group names cannot contain spaces. For example, `LSB_DEFAULT_JOBGROUP=/A/B C/D` is not correct.
- Project names and user names used for macro substitution with `%p` and `%u` cannot start or end with slash character (/).
- Project names and user names used for macro substitution with `%p` and `%u` cannot contain spaces or more than one slash character (/) in a row.
- Project names or user names containing slash character (/) will create separate job groups. For example, if the project name is `canada/projects`, `LSB_DEFAULT_JOBGROUP=%p` results in a job group hierarchy `/canada/projects`.

### Where defined

From the command line

### Example

```
LSB_DEFAULT_JOBGROUP=/canada/projects
```

## Default

Not defined

## See also

DEFAULT\_JOBGROUP in `l sb. par ams`, the `-g` option of `bsub`

## LSB\_DEFAULTPROJECT

### Syntax

**LSB\_DEFAULTPROJECT**=*project\_name*

### Description

The name of the project to which resources consumed by a job will be charged.

### Default

Not defined

### Notes

If the LSF administrator defines a default project in the `l sb. par ams` configuration file, the system uses this as the default project. You can change the default project by setting `LSB_DEFAULTPROJECT` or by specifying a project name with the `-P` option of `bsub`.

If you submit a job without the `-P` option of `bsub`, but you defined `LSB_DEFAULTPROJECT`, then the job belongs to the project specified in `LSB_DEFAULTPROJECT`.

If you submit a job with the `-P` option of `bsub`, the job belongs to the project specified through the `-P` option.

### Where defined

From the command line, or through the `-P` option of `bsub`

### Example

```
LSB_DEFAULTPROJECT=engi neeri ng
```

### See also

DEFAULT\_PROJECT in `l sb. par ams`, the `-P` option of `bsub`

## LSB\_DEFAULTQUEUE

### Syntax

**LSB\_DEFAULTQUEUE**=*queue\_name*

### Description

Defines the default LSF queue.

## Default

`mbatchd` decides which is the default queue. You can override the default by defining `LSB_DEFAULTQUEUE`.

## Notes

If the LSF administrator defines a default queue in the `lsb.params` configuration file, then the system uses this as the default queue. Provided you have permission, you can change the default queue by setting `LSB_DEFAULTQUEUE` to a valid queue (see `bqueues` for a list of valid queues).

## Where defined

From the command line

## See also

`DEFAULT_QUEUE` in `lsb.params`

## LSB\_ECHKPNT\_METHOD

This parameter can be set as an environment variable and/or in `lsf.conf`. See `LSB_ECHKPNT_METHOD` in `lsf.conf`.

## LSB\_ECHKPNT\_METHOD\_DIR

This parameter can be set as an environment variable and/or in `lsf.conf`. See `LSB_ECHKPNT_METHOD_DIR` in `lsf.conf`.

## LSB\_ECHKPNT\_KEEP\_OUTPUT

This parameter can be set as an environment variable and/or in `lsf.conf`. See `LSB_ECHKPNT_KEEP_OUTPUT` in `lsf.conf`.

## LSB\_ERESTART\_USRCMD

### Syntax

`LSB_ERESTART_USRCMD=command`

### Description

Original command used to start the job.

This environment variable is set by `erestart` to pass the job's original start command to a custom `erestart` method `erestart.method_name`. The value of this variable is extracted from the job file of the checkpointed job.

If a job starter is defined for the queue to which the job was submitted, the job starter is also included in `LSB_ERESTART_USRCMD`. For example, if the job starter is `/bin/sh -c "%USRCMD"` in `lsb.queues`, and the job name is `myapp -d`, `LSB_ERESTART_USRCMD` will be set to:

```
/bin/sh -c "myapp -d"
```

## Where defined

Set by `erestart` as an environment variable before a job is restarted

## See also

`LSB_ECHKPNT_METHOD`, `erestart`, `echkpnt`

## LSB\_EXEC\_RUSAGE

### Syntax

```
LSB_EXEC_RUSAGE="resource_name1 resource_value1 resource_name2  
resource_value2..."
```

### Description

Indicates which `rusage` string is satisfied to permit the job to run. This environment variable is necessary because the OR (|) operator specifies alternative `rusage` strings for running jobs.

### Valid values

`resource_value1`, `resource_value2`,... refer to the resource values on `resource_name1`, `resource_name2`,... respectively.

### Default

Not defined

## Where defined

Set by LSF after reserving a resource for the job.

## LSB\_EXECHOSTS

### Description

A list of hosts on which a batch job will run.

### Where defined

Set by `sbatchd`

### Product

MultiCluster

## LSB\_EXIT\_IF\_CWD\_NOTEXIST

### Syntax

```
LSB_EXIT_IF_CWD_NOTEXIST=Y | y | N | n
```

## Description

Indicates that the job will exit if the current working directory specified by `bsub -cwd` or `bmod -cwd` is not accessible on the execution host.

## Default

Not defined

## Where defined

From the command line

## LSB\_EXIT\_PRE\_ABORT

### Description

The queue-level or job-level `pre_exec_command` can exit with this value if the job is to be aborted instead of being requeued or executed

### Where defined

Set by `sbatchd`

### See also

See `PRE_EXEC` in `l sb. queues`, or the `-E` option of `bsub`

## LSB\_EXIT\_REQUEUE

### Syntax

`LSB_EXIT_REQUEUE="exit_value1 exit_value2..."`

### Description

Contains a list of exit values found in the queue's `REQUEUE_EXIT_VALUES` parameter defined in `l sb. queues`.

### Valid values

Any positive integers

### Default

Not defined

### Notes

If `LSB_EXIT_REQUEUE` is defined, a job will be requeued if it exits with one of the specified values.

`LSB_EXIT_REQUEUE` is not defined if the parameter `REQUEUE_EXIT_VALUES` is not defined.

## Where defined

Set by the system based on the value of the parameter `REQUEUE_EXIT_VALUES` in `l sb. queues`

## Example

```
LSB_EXIT_REQUEUE="7 31"
```

## See also

`REQUEUE_EXIT_VALUES` in `l sb. queues`

## LSB\_FRAMES

### Syntax

**LSB\_FRAMES**=*start\_number,end\_number,step*

### Description

Determines the number of frames to be processed by a frame job.

### Valid values

The values of *start\_number*, *end\_number*, and *step* are positive integers. Use commas to separate the values.

### Default

Not defined

### Notes

When the job is running, `LSB_FRAMES` will be set to the relative frames with the format `LSB_FRAMES=start_number,end_number,step`.

From the *start\_number*, *end\_number*, and *step*, the frame job can know how many frames it will process.

## Where defined

Set by `sbatchd`

## Example

```
LSB_FRAMES=10, 20, 1
```

## LSB\_HOSTS

### Syntax

**LSB\_HOSTS**="*host\_name...*"

### Description

A list of hosts selected by LSF to run the job.

## Notes

If a job is run on a single processor, the system sets `LSB_HOSTS` to the name of the host used.  
For parallel jobs, the system sets `LSB_HOSTS` to the names of all the hosts used.

## Where defined

Set by `sbat chd` when the job is executed. `LSB_HOSTS` is set only when the list of host names is less than 4096 bytes.

## See also

`LSB_MCPU_HOSTS`

## LSB\_INTERACTIVE

### Syntax

**LSB\_INTERACTIVE=Y**

### Description

Indicates an interactive job. When you submit an interactive job using `bsub -I`, the system sets `LSB_INTERACTIVE` to `Y`.

### Valid values

`LSB_INTERACTIVE=Y` (if the job is interactive)

### Default

Not defined (if the job is not interactive)

## Where defined

Set by `sbatchd`

## LSB\_JOB\_INCLUDE\_POSTPROC

### Syntax

**LSB\_JOB\_INCLUDE\_POSTPROC=Y | y | N | n**

### Description

Enables the post-execution processing of the job to be included as part of the job.

`LSB_JOB_INCLUDE_POSTPROC` in the user environment overrides the value of `JOB_INCLUDE_POSTPROC` in `lsb.params` and `lsb.applications`.

### Default

Not defined

## Where defined

From the command line

## LSB\_JOBEXIT\_INFO

### Syntax

```
LSB_JOBEXIT_INFO="SIGNAL signal_value signal_name"
```

### Description

Contains information about signal that caused a job to exit.

Applies to post-execution commands. Post-execution commands are set with POST\_EXEC in lsb. queues.

When the post-execution command is run, the environment variable LSB\_JOBEXIT\_INFO is set if the job is signalled internally. If the job ends successfully, or the job is killed or signalled externally, LSB\_JOBEXIT\_INFO is not set.

### Examples

```
LSB_JOBEXIT_INFO="SIGNAL - 1 SIG_CHKPT" LSB_JOBEXIT_INFO="SIGNAL - 14  
SIG_TERM_USER" LSB_JOBEXIT_INFO="SIGNAL - 23 SIG_KILL_QUEUE"
```

### Default

Not defined

## Where defined

Set by sbatchd

## LSB\_JOBEXIT\_STAT

### Syntax

```
LSB_JOBEXIT_STAT=exit_status
```

### Description

Indicates a job's exit status.

Applies to post-execution commands. Post-execution commands are set with POST\_EXEC in lsb. queues.

When the post-execution command is run, the environment variable LSB\_JOBEXIT\_STAT is set to the exit status of the job. Refer to the man page for the wait(2) command for the format of this exit status.

The post-execution command is also run if a job is requeued because the job's execution environment fails to be set up, or if the job exits with one of the queue's QUEUE\_EXIT\_VALUES. The LSB\_JOBPEND environment variable is set if the job is requeued. If the job's execution environment could not be set up, LSB\_JOBEXIT\_STAT is set to 0.

## Valid values

Any positive integer

## Where defined

Set by sbatchd

## LSB\_JOBFILENAME

### Syntax

**LSB\_JOBFILENAME=***file\_name*

### Description

The path to the batch executable job file that invokes the batch job. The batch executable job file is a `/bin/sh` script on UNIX systems or a `.BAT` command script on Windows systems.

## LSB\_JOBGROUP

### Syntax

**LSB\_JOBGROUP=***job\_group\_name*

### Description

The name of the job group associated with the job. When a job is dispatched, if it belongs to a job group, the runtime variable `LSB_JOBGROUP` is defined as its group. For example, if a dispatched job belongs to job group `/X`, `LSB_JOBGROUP=/X`.

## Where defined

Set during job execution based on `bsub` options or the default job group defined in `DEFAULT_JOBGROUP` in `lsb.params` and the `LSB_DEFAULT_JOBGROUP` environment variable.

## Default

Not defined

## LSB\_JOBID

### Syntax

**LSB\_JOBID=***job\_ID*

### Description

The job ID assigned by `sbatchd`. This is the ID of the job assigned by LSF, as shown by `bjobs`.

## Valid values

Any positive integer

## Where defined

Set by sbatchd, defined by mbatchd

## See also

LSB\_REMOTEIID

## LSB\_JOBINDEX

### Syntax

**LSB\_JOBINDEX=***index*

### Description

Contains the job array index.

### Valid values

Any integer greater than zero but less than the maximum job array size.

### Notes

LSB\_JOBINDEX is set when each job array element is dispatched. Its value corresponds to the job array index. LSB\_JOBINDEX is set for all jobs. For non-array jobs, LSB\_JOBINDEX is set to zero (0).

## Where defined

Set during job execution based on bsub options.

## Example

You can use LSB\_JOBINDEX in a shell script to select the job command to be performed based on the job array index.

For example:

```
if [ $LSB_JOBINDEX -eq 1 ]; then cmd1 fi if [ $LSB_JOBINDEX -eq 2 ]; then cmd2 fi
```

## See also

LSB\_JOBINDEX\_STEP, LSB\_REMOTEINDEX

## LSB\_JOBINDEX\_STEP

### Syntax

**LSB\_JOBINDEX\_STEP=***step*

### Description

Step at which single elements of the job array are defined.

### Valid values

Any integer greater than zero but less than the maximum job array size

## Default

1

## Notes

LSB\_JOBINDEX\_STEP is set when a job array is dispatched. Its value corresponds to the step of the job array index. This variable is set only for job arrays.

## Where defined

Set during job execution based on bsub options.

## Example

The following is an example of an array where a step of 2 is used:

```
array[1-10:2] elements: 1 3 5 7 9
```

If this job array is dispatched, then LSB\_JOBINDEX\_STEP=2

## See also

LSB\_JOBINDEX

## LSB\_JOBNAME

### Syntax

**LSB\_JOBNAME**=*job\_name*

### Description

The name of the job defined by the user at submission time.

### Default

The job's command line

### Notes

The name of a job can be specified explicitly when you submit a job. The name does not have to be unique. If you do not specify a job name, the job name defaults to the actual batch command as specified on the bsub command line.

The job name can be up to 4094 characters long for UNIX and Linux or up to 255 characters for Windows.

### Where defined

Set by sbatchd

### Example

When you submit a job using the -J option of bsub, for example:

```
% bsub -J "my job" j ob
```

sbatchd sets LSB\_JOBNAME to the job name that you specified:

```
LSB_JOBNAME=myj ob
```

## LSB\_JOBPEND

### Description

Set if the job is requeued.

### Where defined

Set by sbatchd for POST\_EXEC only

### See also

LSB\_JOBEXIT\_STAT, REQUEUE\_EXIT\_VALUES, POST\_EXEC

## LSB\_JOBPGIDS

### Description

A list of the current process group IDs of the job.

### Where defined

The process group IDs are assigned by the operating system, and LSB\_JOBPGIDS is set by sbatchd.

### See also

LSB\_JOBPIIDS

## LSB\_JOBPIIDS

### Description

A list of the current process IDs of the job.

### Where defined

The process IDs are assigned by the operating system, and LSB\_JOBPIIDS is set by sbatchd.

### See also

LSB\_JOBPGIDS

## LSB\_MAILSIZE

### Syntax

```
LSB_MAILSIZE=value
```

### Description

Gives an estimate of the size of the batch job output when the output is sent by email. It is not necessary to configure LSB\_MAILSIZE\_LIMIT.

LSF sets `LSB_MAILSIZE` to the size in KB of the job output, allowing the custom mail program to intercept output that is larger than desired.

`LSB_MAILSIZE` is not recognized by the LSF default mail program. To prevent large job output files from interfering with your mail system, use `LSB_MAILSIZE_LIMIT` to explicitly set the maximum size in KB of the email containing the job information.

## Valid values

### A positive integer

If the output is being sent by email, `LSB_MAILSIZE` is set to the estimated mail size in kilobytes.

### -1

If the output fails or cannot be read, `LSB_MAILSIZE` is set to -1 and the output is sent by email using `LSB_MAILPROG` if specified in `lsf.conf`.

### Not defined

If you use the `-o` or `-e` options of `bsub`, the output is redirected to an output file. Because the output is not sent by email in this case, `LSB_MAILSIZE` is not used and `LSB_MAILPROG` is not called.

If the `-N` option is used with the `-o` option of `bsub`, `LSB_MAILSIZE` is not set.

## Where defined

Set by `sbatchd` when the custom mail program specified by `LSB_MAILPROG` in `lsf.conf` is called.

## LSB\_MCPU\_HOSTS

### Syntax

```
LSB_MCPU_HOSTS="host_nameA num_processors1 host_nameB num_processors2..."
```

### Description

Contains a list of the hosts and the number of CPUs used to run a job.

### Valid values

`num_processors1`, `num_processors2`,... refer to the number of CPUs used on `host_nameA`, `host_nameB`,..., respectively

### Default

Not defined

### Notes

The environment variables `LSB_HOSTS` and `LSB_MCPU_HOSTS` both contain the same information, but the information is presented in different formats. `LSB_MCPU_HOSTS` uses a shorter format than `LSB_HOSTS`. As a general rule, `sbatchd` sets both these variables. However, for some parallel jobs, `LSB_HOSTS` is not set.

For parallel jobs, several CPUs are used, and the length of `LSB_HOSTS` can become very long. `sbatchd` needs to spend a lot of time parsing the string. If the size of `LSB_HOSTS` exceeds 4096 bytes, `LSB_HOSTS` is ignored, and `sbatchd` sets only `LSB_MCPU_HOSTS`.

To verify the hosts and CPUs used for your dispatched job, check the value of `LSB_HOSTS` for single CPU jobs, and check the value of `LSB_MCPU_HOSTS` for parallel jobs.

## Where defined

Set by `sbatchd` before starting a job on the execution host

## Example

When the you submit a job with the `-m` and `-n` options of `bsub`, for example,

```
% bsub -m "hostA hostB" -n 6 job
```

`sbatchd` sets the environment variables `LSB_HOSTS` and `LSB_MCPU_HOSTS` as follows:

```
LSB_HOSTS= "hostA hostA hostA hostB hostB hostB"  
LSB_MCPU_HOSTS="hostA 3 hostB 3"
```

Both variables are set in order to maintain compatibility with earlier versions.

## See also

`LSB_HOSTS`

## LSB\_NQS\_PORT

This parameter can be defined in `lsf.conf` or in the services database such as `/etc/services`.

See `LSB_NUM_NIOS_CALLBACK_THREADS` in `lsf.conf` for more details.

## LSB\_NTRIES

### Syntax

**LSB\_NTRIES**=*integer*

### Description

The number of times that LSF libraries attempt to contact `mbatchd` or perform a concurrent jobs query.

For example, if this parameter is not defined, when you type `bj obs`, LSF keeps displaying "batch system not responding" if `mbatchd` cannot be contacted or if the number of pending jobs exceeds `MAX_PEND_JOBS` specified in `lsb.params` or `lsb.users`.

If this parameter is set to a value, LSF only attempts to contact `mbatchd` the defined number of times and then quits. LSF will wait for a period of time equal to `SUB_TRY_INTERVAL` specified in `lsb.params` before attempting to contact `mbatchd` again.

### Valid values

Any positive integer

## Default

INFINIT\_INT (The default is to continue the attempts to contact mbatchd)

## LSB\_OLD\_JOBID

### Syntax

**LSB\_OLD\_JOBID=***job\_ID*

### Description

The job ID of a job at the time it was checkpointed.

When a job is restarted, it is assigned a new job ID and LSB\_JOBID is replaced with the new job ID. LSB\_OLD\_JOBID identifies the original ID of a job before it is restarted.

### Valid values

Any positive integer

### Where defined

Set by sbatchd, defined by mbatchd

### See also

LSB\_JOBID

## LSB\_OUTPUT\_TARGETFAILED

### Syntax

**LSB\_OUTPUT\_TARGETFAILED=Y**

### Description

Indicates that LSF cannot access the output file specified for a job submitted the bsub -o option.

### Valid values

Set to Y if the output file cannot be accessed; otherwise, it is not defined.

### Where defined

Set by sbatchd during job execution

## LSB\_DJOB\_COMMFAIL\_ACTION

### Syntax

**LSB\_DJOB\_COMMFAIL\_ACTION="KILL\_TASKS"**

## Description

Defines the action LSF should take if it detects a communication failure with one or more remote parallel or distributed tasks. If defined, LSF will try to kill all the current tasks of a parallel or distributed job associated with the communication failure. If not defined, the job RES notifies the task RES to terminate all tasks, and shut down the entire job.

## Default

Terminate all tasks, and shut down the entire job

## Valid values

KILL\_TASKS

## Where defined

Set by the system based on the value of the parameter DJOB\_COMMFAIL\_ACTION in lsb. applications when running bsub - app for the specified application

## See also

DJOB\_COMMFAIL\_ACTION in lsb. applications

## LSB\_DJOB\_ENV\_SCRIPT

### Syntax

**LSB\_DJOB\_ENV\_SCRIPT**=*script\_name*

### Description

Defines the name of a user-defined script for setting and cleaning up the parallel or distributed job environment. This script will be executed by LSF with the argument setup before launching a parallel or distributed job, and with argument cleanup after the parallel job is finished.

The script will run as the user, and will be part of the job.

If a full path is specified, LSF will use the path name for the execution. Otherwise, LSF will look for the executable from \$LSF\_BINDIR.

### Where defined

Set by the system to the value of the parameter DJOB\_ENV\_SCRIPT in lsb. applications when running bsub - app for the specified application

### See also

DJOB\_ENV\_SCRIPT in lsb. applications

## LSB\_QUEUE

### Syntax

**LSB\_QUEUE**=*queue\_name*

## Description

The name of the queue from which the job is dispatched.

## Where defined

Set by `sbatchd`

## LSB\_REMOTEINDEX

### Syntax

**LSB\_REMOTEINDEX=*index***

## Description

The job array index of a remote MultiCluster job. LSB\_REMOTEINDEX is set only if the job is an element of a job array.

## Valid values

Any integer greater than zero, but less than the maximum job array size

## Where defined

Set by `sbatchd`

## See also

LSB\_JOBINDEX, MAX\_JOB\_ARRAY\_SIZE in `lsb.params`

## LSB\_REMOTEJID

### Syntax

**LSB\_REMOTEJID=*job\_ID***

## Description

The job ID of a remote MultiCluster job.

## Where defined

Set by `sbatchd`, defined by `mbatchd`

## See also

LSB\_JOBID

## LSB\_RESTART

### Syntax

**LSB\_RESTART=*Y***

## Description

Indicates that a job has been restarted or migrated.

## Valid values

Set to Y if the job has been restarted or migrated; otherwise, it is not defined.

## Notes

If a batch job is submitted with the `-r` option of `bsub`, and is restarted because of host failure, then `LSB_RESTART` is set to Y. If a checkpointable job is submitted with the `-k` option of `bsub`, then `LSB_RESTART` is set to Y when the job is restarted. If `bmi g` is used to migrate a job, then `LSB_RESTART` is set to Y when the migrated job is restarted.

If the job is not a restarted job, then `LSB_RESTART` is not set.

## Where defined

Set by `sbatchd` during job execution

## See also

`LSB_RESTART_PGID`, `LSB_RESTART_PID`

## LSB\_RESTART\_PGID

### Syntax

`LSB_RESTART_PGID=pgid`

### Description

The process group ID of the checkpointed job when the job is restarted.

### Notes

When a checkpointed job is restarted, the operating system assigns a new group process ID to the job. LSF sets `LSB_RESTART_PGID` to the new group process ID.

### Where defined

Set during restart of a checkpointed job.

### See also

`LSB_RESTART_PID`, `LSB_RESTART`

## LSB\_RESTART\_PID

### Syntax

`LSB_RESTART_PID=pid`

### Description

The process ID of the checkpointed job when the job is restarted.

## Notes

When a checkpointed job is restarted, the operating system assigns a new process ID to the job. LSF sets `LSB_RESTART_PID` to the new process ID.

## Where defined

Defined during restart of a checkpointed job

## See also

`LSB_RESTART_PGID`, `LSB_RESTART`

## LSB\_RTASK\_GONE\_ACTION

### Syntax

`LSB_RTASK_GONE_ACTION=task_action ...`

### Description

Defines the actions LSF should take if it detects that a remote task of a parallel job is gone. Where *task\_action* is:

#### **IGNORE\_TASKCRASH**

A remote task crashes. The job RES does nothing.

#### **KILLJOB\_TASKDONE**

A remote task exits with zero value. The job RES notifies the task RES to terminate all tasks in the job.

#### **KILLJOB\_TASKEXIT**

A remote task exits with non-zero value. The job RES notifies the task RES to terminate all tasks in the job.

## Where defined

Set by the system based on the value of the parameter `RTASK_GONE_ACTION` in `lsb.appl icat ions` when running `bsub - app` for the specified application

## See also

`RTASK_GONE_ACTION` in `lsb.appl icat ions`

## LSB\_SUB\_APP\_NAME

### Description

Application profile name specified by `bsub - app`.

## Where defined

Set by `esub` before a job is dispatched.

## LSB\_SUB\_CLUSTER

### Description

Name of submission cluster (MultiCluster only)

### Where defined

Set on the submission environment and passed to the execution cluster environment. The parameter will ONLY be valid in Multi Cluster environment. For jobs on a local cluster, the parameter is not set when using any daemon wrappers such as job starter, post-, pre- or eexec scripts.

## LSB\_SUB\_COMMAND\_LINE

### Description

The job command line.

The job command line can be up to 4094 characters long for UNIX and Linux or up to 255 characters for Windows.

### Where defined

Set by esub before a job is submitted.

## LSB\_SUB\_EXTSCHED\_PARAM

### Description

Value of external scheduling options specified by `bsub -extsched`, or queue-level `MANDATORY_EXTSCHED` or `DEFAULT_EXTSCHED`.

### Where defined

Set by esub before a job is submitted.

## LSB\_SUB\_JOB\_ACTION\_WARNING\_TIME

### Description

Value of job warning time period specified by `bsub -wt`.

### Where defined

Set by esub before a job is submitted.

## LSB\_SUB\_JOB\_WARNING\_ACTION

### Description

Value of job warning action specified by `bsub -wa`.

### Where defined

Set by esub before a job is submitted.

## LSB\_SUB\_PARM\_FILE

### Syntax

**LSB\_SUB\_PARM\_FILE**=*file\_name*

### Description

Points to a temporary file that LSF uses to store the bsub options entered in the command line. An esub reads this file at job submission and either accepts the values, changes the values, or rejects the job. Job submission options are stored as name-value pairs on separate lines in the format `option_name=value`. A typical use of this file is to control job submission options.

### Where defined

Set by LSF on the submission host before running esub. Not defined when `l srun` or `l sgrun` are used for interactive remote execution.

## LSB\_SUCCESS\_EXIT\_VALUES

### Syntax

**LSB\_SUCCESS\_EXIT\_VALUES**=[*exit\_code ...*]

### Description

Specifies the exit values that indicate successful execution for applications that successfully exit with non-zero values. Use spaces to separate multiple exit codes. `exit_code` should be the value between 0 and 255.

User-defined `LSB_SUCCESS_EXIT_VALUES` overrides application profile level specification of `SUCCESS_EXIT_VALUES` in `l sb. appl i cat i ons`.

## LSB\_SUSP\_REASONS

### Syntax

**LSB\_SUSP\_REASONS**=*integer*

### Description

An integer representing suspend reasons. Suspend reasons are defined in `l sbat ch. h`.

This parameter is set when a job goes to system-suspended (SSUSP) or user-suspended status (USUSP). It indicates the exact reason why the job was suspended.

To determine the exact reason, you can test the value of `LSB_SUSP_REASONS` against the symbols defined in `l sbat ch. h`.

### Where defined

Set during job execution

### See also

`LSB_SUSP_SUBREASONS`

# LSB\_SUSP\_SUBREASONS

## Syntax

**LSB\_SUSP\_SUBREASONS**=*integer*

## Description

An integer representing the load index that caused a job to be suspended.

When the suspending reason `SUSP_LOAD_REASON` (suspended by load) is set in `LSB_SUSP_REASONS`, `LSB_SUSP_SUBREASONS` set to one of the load index values defined in `lsf.h`.

Use `LSB_SUSP_REASONS` and `LSB_SUSP_SUBREASONS` together in your custom job control to determine the exact load threshold that caused a job to be suspended.

Load index values are defined in `lsf.h`.

| Load Index | Value |
|------------|-------|
| R15S       | 0     |
| R1M        | 1     |
| R15M       | 2     |
| UT         | 3     |
| PG         | 4     |
| IO         | 5     |
| LS         | 6     |
| IT         | 7     |
| TMP        | 8     |
| SWP        | 9     |
| MEM        | 10    |

## Default

Not defined

## Where defined

Set during job execution

## See also

`LSB_SUSP_REASONS`

## LSB\_UNIXGROUP

### Description

Specifies the UNIX user group of the submitting user.

### Notes

This variable is useful if you want pre- or post-execution processing to use the user group of the user who submitted the job, and not `sys(1)`.

### Where defined

Set during job execution

## LSB\_USER\_BIND\_CPU\_LIST

The binding requested at job submission takes effect when `LSF_BIND_JOB=USER_CPU_LIST` in `lsf.conf` or `BIND_JOB=USER_CPU_LIST` in an application profile in `lsb.appl` categories. LSF makes sure that the value is in the correct format, but does not check that the value is valid for the execution hosts.

The correct format is a list which may contain multiple items, separated by comma, and ranges. For example: 0,5,7,9-11.

## LSB\_USER\_BIND\_JOB

The binding requested at job submission takes effect when `LSF_BIND_JOB=USER` in `lsf.conf` or `BIND_JOB=USER` in an application profile in `lsb.appl` categories. This value must be one of Y, N, NONE, BALANCE, PACK, or ANY. Any other value is treated as ANY.

## LSF\_CMD\_LOGDIR

This parameter can be set from the command line or from `lsf.conf`.

See `LSF_CMD_LOGDIR` in `lsf.conf`.

## LSF\_DEBUG\_CMD

This parameter can be set from the command line or from `lsf.conf`.

See `LSB_DEBUG_MBD` in `lsf.conf`.

## LSF\_DEBUG\_LIM

This parameter can be set from the command line or from `lsf.conf`.

See `LSF_DEBUG_LIM` in `lsf.conf`.

## LSF\_DEBUG\_RES

This parameter can be set from the command line or from `lsf.conf`.

See `LSF_DEBUG_RES` in `lsf.conf`.

## LSF\_EAUTH\_AUX\_DATA

### Syntax

**LSF\_EAUTH\_AUX\_DATA**=*path/file\_name*

### Description

Used in conjunction with LSF daemon authentication, specifies the full path to the temporary file on the local file system that stores auxiliary authentication information (such as credentials required by a remote host for use during job execution). Provides a way for `eauth -c`, `mbatchd`, and `sbatchd` to communicate the location of auxiliary authentication data. Set internally by the LSF libraries in the context of `eauth`.

For Kerberos authentication, used for forwarding credentials to the execution host.

## LSF\_EAUTH\_AUX\_PASS

### Syntax

**LSF\_EAUTH\_AUX\_PASS**=yes

### Description

Enables forwarding of credentials from a submission host to an execution host when daemon authentication is enabled. `LSF_EAUTH_AUX_PASS=yes` indicates that a credential can be added to the execution context of a job. Set to yes by `bsub` during job submission or by `bmod` during job modification so that `eauth -c` can forward credentials.

## LSF\_EAUTH\_CLIENT

### Syntax

**LSF\_EAUTH\_CLIENT**=`mbatchd` | `sbatchd` | `pam` | `res` | `user`

### Description

Used with LSF daemon authentication, specifies the LSF daemon, command, or user that invokes `eauth -c`. Used when writing a customized `eauth` executable to set the context for the call to `eauth`. Set internally by the LSF libraries or by the LSF daemon, command, or user calling `eauth -c`.

## LSF\_EAUTH\_SERVER

### Syntax

**LSF\_EAUTH\_SERVER**=`mbatchd` | `sbatchd` | `pam` | `res`

### Description

Used with LSF daemon authentication, specifies the daemon that invokes `eauth -s`. Used when writing a customized `eauth` executable to set the context for the call to `eauth`. Set internally by the LSF libraries or by the LSF daemon calling `eauth -s`.

## LSF\_EAUTH\_UID

### Syntax

**LSF\_EAUTH\_UID**=*user\_ID*

### Description

Specifies the user account under which `eauth -s` runs. Set by the LSF daemon that executes `eauth`. Set by the LSF daemon that executes `eauth`.

## LSF\_EXECUTE\_DOMAIN

### Syntax

**LSF\_EXECUTE\_DOMAIN**=*domain\_name*`setenv LSF_EXECUTE_DOMAIN` *domain\_name*

### Description

If UNIX/Windows user account mapping is enabled, specifies the preferred Windows execution domain for a job submitted by a UNIX user. The execution domain must be one of the domains listed in `LSF_USER_DOMAIN`.

`LSF_EXECUTE_DOMAIN` is defined in the user environment (`.cshrc` or `.profile`) or from the command line. Specify only one domain.

Use this parameter in conjunction with the `bsub`, `l srun`, and `l sgrun` commands to bypass the order of the domains listed in `LSF_USER_DOMAIN` and run the job using the specified domain. If you do not have a Windows user account in the execution domain, LSF tries to run the job using one of the other domains defined by `LSF_USER_DOMAIN`. Once you submit a job with an execution domain defined, you cannot change the execution domain for that particular job.

## LSF\_INTERACTIVE\_STDERR

This parameter can be defined in `lsf.conf`.

See `LSF_INTERACTIVE_STDERR` in `lsf.conf` for more details.

## LSF\_INVOKE\_CMD

### Syntax

**LSF\_INVOKE\_CMD**=*invoking\_command\_name*

### Description

Indicates the name of the last LSF command that invoked an external executable (for example, `esub` or `eexec`).

External executables get called by different LSF commands, such as `bsub`, `bmod`, or `l srun`.

### Default

Not defined

## Where defined

Set internally within by LSF

## LSF\_JOB\_STARTER

### Syntax

**LSF\_JOB\_STARTER**=*binary*

### Description

Specifies an executable program that has the actual job as an argument.

### Default

Not defined

## Interactive Jobs

If you want to run an interactive job that requires some preliminary setup, LSF provides a job starter function at the command level. A command-level job starter allows you to specify an executable file that will run prior to the actual job, doing any necessary setup and running the job when the setup is complete.

If LSF\_JOB\_STARTER is properly defined, RES will invoke the job starter (rather than the job itself), supplying your commands as arguments.

## Batch Jobs

A job starter can also be defined at the queue level using the JOB\_STARTER parameter, although this can only be done by the LSF administrator.

## Where defined

From the command line

## Example: UNIX

The job starter is invoked from within a Bourne shell, making the command-line equivalent:

```
/bin/sh -c "$LSF_JOB_STARTER command [argument...]"
```

where *command* [*argument...*] are the command line arguments you specified in `l srun`, `l sgrun`, or `ch`.

If you define LSF\_JOB\_STARTER as follows:

```
setenv LSF_JOB_STARTER "/bin/csh -c"
```

and run a simple C-shell job:

```
l srun "' a.out; echo hi '"
```

The following will be invoked to correctly start the job:

```
/bin/sh -c "/bin/csh -c ' a.out; echo hi '"
```

## Example: Windows

RES runs the job starter, passing it your commands as arguments:

```
LSF_JOB_STARTER command [argument...]
```

If you define LSF\_JOB\_STARTER as follows:

```
set LSF_JOB_STARTER=C:\cmd.exe /C
```

and run a simple DOS shell job:

```
C:\> lsrunc dir /p
```

then the following will be invoked to correctly start the job:

```
C:\cmd.exe /C dir /p
```

## See also

JOB\_STARTER in `lsb.queues`

## LSF\_LD\_LIBRARY\_PATH

### Description

When `LSF_LD_SECURITY=Y` in `lsf.conf`, contains the value of the `LD_LIBRARY_PATH` environment variable, which is removed from the job environment during job initialization to ensure enhanced security against users obtaining root privileges.

`LSF_LD_LIBRARY_PATH` allows the `LD_LIBRARY_PATH` environment variable to be put back before the job runs.

### Where defined

For jobs submitted using `bsub -Is` or `bsub -Ip` only.

## See also

`LSF_LD_PRELOAD`, `LSF_LD_SECURITY` in `lsf.conf`

## LSF\_LD\_PRELOAD

### Description

When `LSF_LD_SECURITY=Y` in `lsf.conf`, contains the value of the `LD_PRELOAD` environment variable, which is removed from the job environment during job initialization to ensure enhanced security against users obtaining root privileges. `LSF_LD_PRELOAD` allows the `LD_PRELOAD` environment variable to be put back before the job runs.

### Where defined

For jobs submitted using `bsub -Is` or `bsub -Ip` only.

## See also

`LSF_LD_LIBRARY_PATH`, `LSF_LD_SECURITY` in `lsf.conf`

## LSF\_LIM\_API\_NTRIES

### Syntax

**LSF\_LIM\_API\_NTRIES**=*integer*

### Description

Defines the number of times LSF commands will retry to communicate with the LIM API when LIM is not available. LSF\_LIM\_API\_NTRIES is ignored by LSF and EGO daemons and EGO commands. The LSF\_LIM\_API\_NTRIES environment variable, overrides the value of LSF\_LIM\_API\_NTRIES in `lsf.conf`.

### Valid values

1 to 65535

### Where defined

From the command line or from `lsf.conf`

### Default

Not defined. If not defined in `lsf.conf`, LIM API exits without retrying.

## LSF\_LIM\_DEBUG

This parameter can be set from the command line or from `lsf.conf`.

See LSF\_LIM\_DEBUG in `lsf.conf`.

## LSF\_LOGDIR

This parameter can be set from the command line or from `lsf.conf`.

See LSF\_LOGDIR in `lsf.conf`.

## LSF\_MASTER

### Description

Set by the LIM to identify the master host. The value is Y on the master host and N on all other hosts. An `elim` executable can use this parameter to check the host on which the `elim` is currently running.

Used when the external load indices feature is enabled.

### When defined

Set by the LIM when it starts the master external load information manager (MELIM).

### See also

LSF\_RESOURCES

## LSF\_NIOS\_DEBUG

This parameter can be set from the command line or from `lsf.conf`.

See `LSF_NIOS_DEBUG` in `lsf.conf`.

## LSF\_NIOS\_DIE\_CMD

### Syntax

`LSF_NIOS_DIE_CMD=command`

### Description

If set, the command defined by `LSF_NIOS_DIE_CMD` is executed before NIOS exits.

### Default

Not defined

### Where defined

From the command line

## LSF\_NIOS\_IGNORE\_SIGWINDOW

### Syntax

`LSF_NIOS_IGNORE_SIGWINDOW=any_value`

### Description

If defined, the NIOS will ignore the SIGWINDOW signal.

### Default

Not defined

### Notes

When the signal SIGWINDOW is defined, some tasks appear to die when they receive the SIGWINDOW while doing I/O. By defining `LSF_NIOS_IGNORE_SIGWINDOW`, these tasks are given the chance to ignore the signal.

### Where defined

From the command line

## LSF\_NIOS\_PEND\_TIMEOUT

### Syntax

`LSF_NIOS_PEND_TIMEOUT=minutes`

## Description

Applies only to interactive batch jobs.

Maximum amount of time that an interactive batch job can remain pending.

If this parameter is defined, and an interactive batch job is pending for longer than the specified time, the interactive batch job is terminated.

## Valid values

Any integer greater than zero

## Default

Not defined

## LSF\_NIOS\_PORT\_RANGE

### Syntax

```
LSF_NIOS_PORT_RANGE=min_port_number-max_port_number
```

### Description

Defines a range of listening ports for NIOS to use.

### Example

```
LSF_NIOS_PORT_RANGE=5000-6000
```

### Default

Not defined. LSF randomly assigns a NIOS port number.

## LSF\_RESOURCES

### Syntax

```
LSF_RESOURCES=dynamic_external_resource_name...
```

### Description

Space-separated list of dynamic external resources. When the LIM starts a master external load information manager (MELIM) on a host, the LIM checks the resource mapping defined in the ResourceMap section of `lsf.cluster.cluster_name`. Based on the mapping (default, all, or a host list), the LIM sets LSF\_RESOURCES to the list of resources expected on the host and passes the information to the MELIM.

Used when the external load indices feature is enabled.

### When defined

Set by the MELIM on the host when the MELIM invokes the `el im` executable.

## See also

LSF\_MASTER

## LSF\_TS\_LOGON\_TIME

### Syntax

**LSF\_TS\_LOGON\_TIME**=*milliseconds*

### Description

Specifies the time to create a Windows Terminal Service session. Configure LSF\_TS\_LOGON\_TIME according to the load on your network environment.

The default, 30000 milliseconds, is suitable for most environments. If you set LSF\_TS\_LOGON\_TIME too small, the LSF tries multiple times before it succeeds in making a TS session with the TS server, which can cause the job wait a long time before it runs. For a congested network. set LSF\_TS\_LOGON\_TIME=1000000.

### Where defined

From the command line

### Default

30000 milliseconds

## LSF\_USE\_HOSTEQUIV

### Syntax

**LSF\_USE\_HOSTEQUIV**=y | Y

### Description

Used for authentication purposes. If LSF\_USE\_HOSTEQUIV is defined, RES and mbatchd call the ruserok(3) function to decide if a user is allowed to run remote jobs. LSF trusts all hosts configured in the LSF cluster that are defined in hosts.equiv, or in .rhosts in the user's home directory.

The ruserok(3) function checks in the /etc/hosts.equiv file and the user's \$HOME/.rhosts file to decide if the user has permission to execute remote jobs.

If LSF\_USE\_HOSTEQUIV is not defined, all normal users in the cluster can execute remote jobs on any host.

If LSF\_ROOT\_REX is set, root can also execute remote jobs with the same permission test as for normal users.

### Default

Not defined

## See also

LSF\_ROOT\_REX and LSF\_AUTH in lsf.conf

## LSF\_USER\_DOMAIN

### Syntax

**LSF\_USER\_DOMAIN**=*domain\_name* / .

### Description

Set during LSF installation or setup. If you modify this parameter in an existing cluster, you probably have to modify passwords and configuration files also.

Windows or mixed UNIX-Windows clusters only.

Enables default user mapping, and specifies the LSF user domain. The period (.) specifies local accounts, not domain accounts.

- A user name specified without a domain is interpreted (on a Windows host) as belonging to the LSF user domain
- A user name specified with the domain name of the LSF user domain is not valid
- In a mixed cluster, this parameter defines a 2-way, 1:1 user map between UNIX user accounts and Windows user accounts belonging to the specified domain, as long as the accounts have the same user name. This means jobs submitted by the Windows user account can run on a UNIX host, and jobs submitted by the UNIX account can run on any Windows host that is available to the Windows user account.

If this parameter is not defined, the default user mapping is not enabled. You can still configure user mapping at the user or system level. User account mapping is required to run cross-platform jobs in a UNIX-Windows mixed cluster.

### Where defined

lsf.conf

### Default

- If you upgrade from LSF 4.0.1 or earlier, the default is the existing LSF user domain.
- For a new, Windows-only cluster, this parameter is not defined (no LSF user domain, no default user mapping).
- For a new, mixed UNIX-Windows cluster, the default is the domain that the Windows installation account belongs to. This can be modified during LSF installation.

P A R T

---

# IV

## Troubleshooting



# Troubleshooting and error messages

## Shared file access

A frequent problem is non-accessible files due to a non-uniform file space. If a task is run on a remote host where a file it requires cannot be accessed using the same name, an error results. Almost all interactive LSF commands fail if the user's current working directory cannot be found on the remote host.

## Shared files on UNIX

If you are running NFS, rearranging the NFS mount table may solve the problem. If your system is running the `automount` server, LSF tries to map the filenames, and in most cases it succeeds. If shared mounts are used, the mapping may break for those files. In such cases, specific measures need to be taken to get around it.

The automount maps must be managed through NIS. When LSF tries to map filenames, it assumes that automounted file systems are mounted under the `/tmp_mnt` directory.

## Shared files on Microsoft Windows

To share files among Windows machines, set up a share on the server and access it from the client. You can access files on the share either by specifying a UNC path (`\\server\share\path`) or connecting the share to a local drive name and using a `drive:\path` syntax. Using UNC is recommended because drive mappings may be different across machines, while UNC allows you to unambiguously refer to a file on the network.

## Shared files across UNIX and Windows

For file sharing across UNIX and Windows, you require a third party NFS product on Windows to export directories from Windows to UNIX.

## Common LSF problems

This section lists some common problems with LSF jobs. Most problems are due to incorrect installation or configuration. Check the `mbatchd` and `sbatchd` error log files; often the log message points directly to the problem.

The section also includes some common problems with the LIM, the RES and interactive applications.

## LIM dies quietly

Run the following command to check for errors in the LIM configuration files.

```
lsadmin ckconfig -v
```

This displays most configuration errors. If this does not report any errors, check in the LIM error log.

## LIM unavailable

Sometimes the LIM is up, but executing the `lsload` command prints the following error message:

```
Communication time out.
```

If the LIM has just been started, this is normal, because the LIM needs time to get initialized by reading configuration files and contacting other LIMs. If the LIM does not become available within one or two minutes, check the LIM error log for the host you are working on.

To prevent communication timeouts when starting or restarting the local LIM, define the parameter `LSF_SERVER_HOSTS` in the `lsf.conf` file. The client will contact the LIM on one of the `LSF_SERVER_HOSTS` and execute the command, provided that at least one of the hosts defined in the list has a LIM that is up and running.

When the local LIM is running but there is no master LIM in the cluster, LSF applications display the following message:

```
Cannot locate master LIM now, try later.
```

Check the LIM error logs on the first few hosts listed in the `Host` section of the `lsf.cluster.cluster_name` file. If `LSF_MASTER_LIST` is defined in `lsf.conf`, check the LIM error logs on the hosts listed in this parameter instead.

## Master LIM is down

Sometimes the master LIM is up, but executing the `lsl load` or `lshosts` command prints the following error message:

```
Master LIM is down; try later
```

If the `/etc/hosts` file on the host where the master LIM is running is configured with the host name assigned to the loopback IP address (127.0.0.1), LSF client LIMs cannot contact the master LIM. When the master LIM starts up, it sets its official host name and IP address to the loopback address. Any client requests will get the master LIM address as 127.0.0.1, and try to connect to it, and in fact will try to access itself.

Check the IP configuration of your master LIM in `/etc/hosts`. The following IPv4 example incorrectly sets the master LIM IP address to the loopback address:

```
127.0.0.1      local host      myhostname
```

The following example correctly sets the master LIM IP address:

```
127.0.0.1      local host
192.168.123.123 myhostname
```

For a master LIM running on a host that uses an IPv6 address, the loopback address is

```
::1
```

An IPv6-enabled host should have the following entries in its `/etc/hosts` file:

```
::1          local host ipv6-local host ipv6-loopback
fe00::0      ipv6-local net
ff00::0      ipv6-mcast prefix
ff02::1      ipv6-all nodes
ff02::2      ipv6-all routers
ff02::3      ipv6-all hosts
```

## RES does not start

Check the RES error log.

On UNIX, if the RES is unable to read the `lsf.conf` file and does not know where to write error messages, it logs errors into `syslog`.

On Windows, if the RES is unable to read the `lsf.conf` file and does not know where to write error messages, it logs errors into `C:\temp`.

## User permission denied

If remote execution fails with the following error message, the remote host could not securely determine the user ID of the user requesting remote execution.

```
User permission denied.
```

Check the RES error log on the remote host; this usually contains a more detailed error message.

If you are not using an identification daemon (LSF\_AUTH is not defined in the `lsf.conf` file), then all applications that do remote executions must be owned by root with the `setuid` bit set. This can be done as follows.

**chmod 4755 filename**

If the binaries are on an NFS-mounted file system, make sure that the file system is not mounted with the `nosuid` flag.

If you are using an identification daemon (defined in the `lsf.conf` file by LSF\_AUTH), `inetd` must be configured to run the daemon. The identification daemon must not be run directly.

If LSF\_USE\_HOSTEQUIV=Y is defined in the `lsf.conf` file, check if `/etc/hosts.equiv` or `HOME/.rhosts` on the destination host has the client host name in it. Inconsistent host names in a name server with `/etc/hosts` and `/etc/hosts.equiv` can also cause this problem.

On SGI hosts running a name server, you can try the following command to tell the host name lookup code to search the `/etc/hosts` file before calling the name server.

**setenv HOSTRESORDER "local,nis,bind"**

For Windows hosts, users must register and update their Windows passwords using the `lspasswd` command. Passwords must be 3 characters or longer and 31 characters or less.

For Windows password authentication in a non-shared file system environment, you must define the parameter LSF\_MASTER\_LIST in `lsf.conf` so that jobs will run with correct permissions. If you do not define this parameter, LSF assumes that the cluster uses a shared file system environment.

## Non-uniform file name space

A command may fail with the following error message due to a non-uniform file name space.

```
chdir(...) failed: no such file or directory
```

You are trying to execute a command remotely, where either your current working directory does not exist on the remote host, or your current working directory is mapped to a different name on the remote host.

If your current working directory does not exist on a remote host, you should not execute commands remotely on that host.

On UNIX, if the directory exists, but is mapped to a different name on the remote host, you have to create symbolic links to make them consistent.

LSF can resolve most, but not all, problems using `automount`. The automount maps must be managed through NIS. Follow the instructions in your Release Notes for obtaining technical

support if you are running automount and LSF is not able to locate directories on remote hosts.

## Batch daemons die quietly

First, check the sbatchd and mbatchd error logs. Try running the following command to check the configuration.

### **badadmin ckconfig**

This reports most errors. You should also check if there is any email from LSF in the LSF administrator's mailbox. If the mbatchd is running but the sbatchd dies on some hosts, it may be because mbatchd has not been configured to use those hosts.

## sbatchd starts but mbatchd does not

Check whether LIM is running. You can test this by running the `l s i d` command. If LIM is not running properly, follow the suggestions in this chapter to fix the LIM first. You should make sure that all hosts use the same `l s f . c o n f` file. Note that it is possible that mbatchd is temporarily unavailable because the master LIM is temporarily unknown, causing the following error message.

```
sbatchd: unknown service
```

Check whether services are registered properly. See *Administering Platform LSF* for information about registering LSF services.

## Host not used by LSF

If you configure a list of server hosts in the Host section of the `l s b . h o s t s` file, mbatchd allows sbatchd to run only on the hosts listed. If you try to configure an unknown host as a HOSTS definition for a queue in the `l s b . q u e u e s` file, mbatchd logs the following message.

```
mbatchd on host: LSB_CONFDIR/cluster/configdir/file(line #): Host  
hostname is not used by lsbatch; ignored
```

If you try to configure an unknown host in the HostGroup or HostPartition sections of the `l s b . h o s t s` file, you also see the message.

If you start sbatchd on a host that is not known by mbatchd, mbatchd rejects the sbatchd. The sbatchd logs the following message and exits.

```
This host is not used by lsbatch system.
```

Both of these errors are most often caused by not running the following commands, in order, after adding a host to the configuration.

```
l s a d m i n r e c o n f i g b a d m i n r e c o n f i g
```

You must run both of these before starting the daemons on the new host.

## Data limit error on AIX

On AIX, if the `XPG_SUS_ENV=ON` environment variable is set in the user's environment before the process is executed and a process attempts to set the limit lower than current usage, the operation fails with `errno` set to `EINVAL`. If the `XPG_SUS_ENV` environment variable is not set, the operation fails with `errno` set to `EFAULT`.

## Error messages

The following error messages are logged by the LSF daemons, or displayed by the following commands.

```
lsadmin ckconfig badmin ckconfig
```

## General errors

The messages listed in this section may be generated by any LSF daemon.

```
can't open file: error
```

The daemon could not open the named file for the reason given by *error*. This error is usually caused by incorrect file permissions or missing files. All directories in the path to the configuration files must have execute (x) permission for the LSF administrator, and the actual files must have read (r) permission. Missing files could be caused by incorrect path names in the `lsf.conf` file, running LSF daemons on a host where the configuration files have not been installed, or having a symbolic link pointing to a nonexistent file or directory.

```
file(line): malloc failed
```

Memory allocation failed. Either the host does not have enough available memory or swap space, or there is an internal error in the daemon. Check the program load and available swap space on the host; if the swap space is full, you must add more swap space or run fewer (or smaller) programs on that host.

```
auth_user: getservbyname(ident/tcp) failed: error; ident must be registered in services
```

LSF\_AUTH=ident is defined in the `lsf.conf` file, but the `ident/tcp` service is not defined in the services database. Add `ident/tcp` to the services database, or remove LSF\_AUTH from the `lsf.conf` file and `setuid root` those LSF binaries that require authentication.

```
auth_user: operation(<host>/<port>) failed: error
```

LSF\_AUTH=ident is defined in the `lsf.conf` file, but the LSF daemon failed to contact the `identd` daemon on host. Check that `identd` is defined in `inetd.conf` and the `identd` daemon is running on host.

```
auth_user: Authentication data format error (rbuf=<data>) from <host>/<port>
```

```
auth_user: Authentication port mismatch (...) from <host>/<port>
```

LSF\_AUTH=ident is defined in the `lsf.conf` file, but there is a protocol error between LSF and the `ident` daemon on *host*. Make sure the `ident` daemon on the host is configured correctly.

```
userok: Request from bad port (<port_number>), denied
```

LSF\_AUTH is not defined, and the LSF daemon received a request that originates from a non-privileged port. The request is not serviced.

Set the LSF binaries (for example, `lsrun`) to be owned by root with the `setuid` bit set, or define LSF\_AUTH=ident and set up an `ident` server on all hosts in the cluster. If the binaries are on an NFS-mounted file system, make sure that the file system is not mounted with the `nosuid` flag.

```
userok: Forged username suspected from <host>/<port>: <claimed_user>/<actual_user>
```

The service request claimed to come from user *claimed\_user* but ident authentication returned that the user was actually *actual\_user*. The request was not serviced.

```
userok: ruserok(<host>, <uid>) failed
```

LSF\_USE\_HOSTEQUIV=Y is defined in the `lsf.conf` file, but *host* has not been set up as an equivalent host (see `/etc/host.equiv`), and user *uid* has not set up a `.rhosts` file.

```
init_AcceptSock: RES service(res) not registered, exiting
```

```
init_AcceptSock: res/tcp: unknown service, exiting  
initSock: LIM service not registered.
```

```
initSock: Service lim/udp is unknown. Read LSF Guide for help  
get_ports: <serv> service not registered
```

The LSF services are not registered. See *Administering Platform LSF* for information about configuring LSF services.

```
init_AcceptSock: Can't bind daemon socket to port <port>: error,  
exiting
```

```
init_ServSock: Could not bind socket to port <port>: error
```

These error messages can occur if you try to start a second LSF daemon (for example, RES is already running, and you execute RES again). If this is the case, and you want to start the new daemon, kill the running daemon or use the `lsadmi n` or `badmi n` commands to shut down or restart the daemon.

## Configuration errors

The messages listed in this section are caused by problems in the LSF configuration files. General errors are listed first, and then errors from specific files.

```
file(line): Section name expected after Begin; ignoring section  
(line): Invalid section name name; ignoring section
```

The keyword `begin` at the specified line is not followed by a section name, or is followed by an unrecognized section name.

```
file(line): section section: Premature EOF
```

The end of file was reached before reading the end section line for the named section.

```
file(line): keyword line format error for section section; Ignore  
this section
```

The first line of the section should contain a list of keywords. This error is printed when the keyword line is incorrect or contains an unrecognized keyword.

```
file(line): values do not match keys for section section; Ignoring  
line
```

The number of fields on a line in a configuration section does not match the number of keywords. This may be caused by not putting `()` in a column to represent the default value.

```
file: HostModel section missing or invalid
```

```
file: Resource section missing or invalid
```

```
file: HostType section missing or invalid
```

The HostModel, Resource, or HostType section in the lsf.shared file is either missing or contains an unrecoverable error.

file(line): Name name reserved or previously defined. Ignoring index

The name assigned to an external load index must not be the same as any built-in or previously defined resource or load index.

file(line): Duplicate clustername name in section cluster. Ignoring current line

A cluster name is defined twice in the same lsf.shared file. The second definition is ignored.

file(line): Bad cpuFactor for host model model. Ignoring line

The CPU factor declared for the named host model in the lsf.shared file is not a valid number.

file(line): Too many host models, ignoring model name

You can declare a maximum of 127 host models in the lsf.shared file.

file(line): Resource name name too long in section resource. Should be less than 40 characters. Ignoring line

The maximum length of a resource name is 39 characters. Choose a shorter name for the resource.

file(line): Resource name name reserved or previously defined. Ignoring line.

You have attempted to define a resource name that is reserved by LSF or already defined in the lsf.shared file. Choose another name for the resource.

file(line): illegal character in resource name: name, section resource. Line ignored.

Resource names must begin with a letter in the set [a-zA-Z], followed by letters, digits or underscores [a-zA-Z0-9\_].

## LIM messages

The following messages are logged by the LIM:

main: LIM cannot run without licenses, exiting

The LSF software license key is not found or has expired. Check that FLEXlm is set up correctly, or contact Platform support at support@platform.com.

main: Received request from unlicensed host <host>/<port>

LIM refuses to service requests from hosts that do not have licenses. Either your LSF license has expired, or you have configured LSF on more hosts than your license key allows.

initLicense: Trying to get license for LIM from source <LSF\_CONFDIR/license.dat>

getLicense: Can't get software license for LIM from license file <LSF\_CONFDIR/license.dat>: feature not yet available.

Your LSF license is not yet valid. Check whether the system clock is correct.

findHostbyAddr/<proc>: Host <host>/<port> is unknown by <myhostname>

```
function: Gethostbyaddr_(<host>/<port>) failed: error  
main: Request from unknown host <host>/<port>: error  
function: Received request from non-LSF host <host>/<port>
```

The daemon does not recognize *host* as a Platform LSF host. The request is not serviced. These messages can occur if *host* was added to the configuration files, but not all the daemons have been reconfigured to read the new information. If the problem still occurs after reconfiguring all the daemons, check whether the host is a multi-addressed host. See *Administering Platform LSF* for information about working with multi-addressed hosts.

```
rcvLoadVector: Sender (<host>/<port>) may have different config?  
MasterRegister: Sender (host) may have different config?
```

LIM detected inconsistent configuration information with the sending LIM. Run the following command so that all the LIMs have the same configuration information.

#### **Isadmin reconfig**

Note any hosts that failed to be contacted.

```
rcvLoadVector: Got load from client-only host <host>/<port>. Kill LIM  
on <host>/<port>
```

A LIM is running on a Platform LSF client host. Run the following command, or go to the client host and kill the LIM daemon.

#### **Isadmin limshutdown host**

```
saveIdx: Unknown index name <name> from ELIM
```

LIM received an external load index name that is not defined in the `lsf.shared` file. If `name` is defined in `lsf.shared`, reconfigure the LIM. Otherwise, add `name` to the `lsf.shared` file and reconfigure all the LIMs.

```
saveIdx: ELIM over-riding value of index <name>
```

This is a warning message. The ELIM sent a value for one of the built-in index names. LIM uses the value from ELIM in place of the value obtained from the kernel.

```
getusr: Protocol error numIdx not read (cc=num): error  
getusr: Protocol error on index number (cc=num): error
```

Protocol error between ELIM and LIM. See *Administering Platform LSF* for a description of the ELIM and LIM protocols.

## RES messages

These messages are logged by the RES.

```
doacceptconn: getpwnam(<username>@<host>/<port>) failed: error  
doacceptconn: User <username> has uid <uid1> on client host <host>/  
<port>, uid <uid2> on RES host; assume bad user authRequest: username/  
uid <userName>/<uid>@<host>/<port> does not exist  
authRequest: Submitter's name <clname>@<clhost> is different from  
name <lname> on this host
```

RES assumes that a user has the same userID and username on all the LSF hosts. These messages occur if this assumption is violated. If the user is allowed to use LSF for interactive remote execution, make sure the user's account has the same user ID and user name on all LSF hosts.

```
doacceptconn: root remote execution permission denied authRequest:
root job submission rejected
```

Root tried to execute or submit a job but LSF\_ROOT\_REX is not defined in the `lsf.conf` file.

```
resControl: operation permission denied, uid = <uid>
```

The user with user ID *uid* is not allowed to make RES control requests. Only the LSF administrator, or root if LSF\_ROOT\_REX is defined in `lsf.conf`, can make RES control requests.

```
resControl: access(respath, X_OK): error
```

The RES received a reboot request, but failed to find the file `respath` to re-execute itself. Make sure `respath` contains the RES binary, and it has execution permission.

## LSF messages

The following messages are logged by the `mbatchd` and `sbatchd` daemons:

```
renewJob: Job <jobId>: rename(<from>, <to>) failed: error
```

`mbatchd` failed in trying to re-submit a rerunnable job. Check that the file *from* exists and that the LSF administrator can rename the file. If *from* is in an AFS directory, check that the LSF administrator's token processing is properly setup

See *Administering Platform LSF* for information about installing on AFS.

```
logJobInfo_: fopen(<logdir/info/jobfile>) failed: error
```

```
logJobInfo_: write <logdir/info/jobfile> <data> failed: error
```

```
logJobInfo_: seek <logdir/info/jobfile> failed: error
```

```
logJobInfo_: write <logdir/info/jobfile> xdrpos <pos> failed: error
```

```
logJobInfo_: write <logdir/info/jobfile> xdr buf len <len> failed:
error
```

```
logJobInfo_: close(<logdir/info/jobfile>) failed: error
```

```
rmLogJobInfo: Job <jobId>: can't unlink(<logdir/info/jobfile>): error
```

```
rmLogJobInfo_: Job <jobId>: can't stat(<logdir/info/jobfile>): error
```

```
readLogJobInfo: Job <jobId> can't open(<logdir/info/jobfile>): error
```

```
start_job: Job <jobId>: readLogJobInfo failed: error
```

```
readLogJobInfo: Job <jobId>: can't read(<logdir/info/jobfile>) size
size: error
```

```
initLog: mkdir(<logdir/info>) failed: error
```

```
<fname>: fopen(<logdir/file>) failed: error
```

```
getElogLock: Can't open existing lock file <logdir/file>: error
```

```
getElogLock: Error in opening lock file <logdir/file>: error
```

```
releaseLogLock: unlink(<logdir/lockfile>) failed: error  
touchLogLock: Failed to open lock file <logdir/file>: error  
touchLogLock: close <logdir/file> failed: error
```

mbatchd failed to create, remove, read, or write the log directory or a file in the log directory, for the reason given in *error*. Check that LSF administrator has read, write, and execute permissions on the `logdir` directory.

If `logdir` is on AFS, check that the instructions in *Administering Platform LSF* have been followed. Use the `fs ls` command to verify that the LSF administrator owns `logdir` and that the directory has the correct ACL.

```
replay_newjob: File <logfile> at line <line>: Queue <queue> not  
found, saving to queue <lost_and_found>replay_switchjob: File  
<logfile> at line <line>: Destination queue <queue> not found,  
switching to queue <lost_and_found>
```

When `mbatchd` was reconfigured, jobs were found in *queue* but that queue is no longer in the configuration.

```
replay_startjob: JobId <jobId>: exec host <host> not found, saving to  
host <lost_and_found>
```

When `mbatchd` was reconfigured, the event log contained jobs dispatched to host, but that host is no longer configured to be used by LSF.

```
do_restartReq: Failed to get hData of host <host_name>/<host_addr>
```

`mbatchd` received a request from `sbatchd` on host *host\_name*, but that host is not known to `mbatchd`. Either the configuration file has been changed but `mbatchd` has not been reconfigured to pick up the new configuration, or *host\_name* is a client host but the `sbatchd` daemon is running on that host. Run the following command to reconfigure the `mbatchd` or kill the `sbatchd` daemon on *host\_name*.

**badadmin reconfig**

## LSF command messages

```
LSF daemon (LIM) not responding ... still trying
```

During LIM restart, LSF commands will fail and display this error message. User programs linked to the LIM API will also fail for the same reason. This message is displayed when LIM running on the master host list or server host list is restarted after configuration changes, such as adding new resources, binary upgrade, and so on.

Use `LSF_LIM_API_NTRIES` in `lsf.conf` or as an environment variable to define how many times LSF commands will retry to communicate with the LIM API while LIM is not available. `LSF_LIM_API_NTRIES` is ignored by LSF and EGO daemons and all EGO commands.

When `LSB_API_VERBOSE=Y` in `lsf.conf`, LSF batch commands will display the not responding retry error message to `stderr` when LIM is not available.

When `LSB_API_VERBOSE=N` in `lsf.conf`, LSF batch commands will not display the retry error message when LIM is not available.

## Batch command client messages

LSF displays error messages when a batch command cannot communicate with mbatchd. The following table provides a list of possible error reasons and the associated error message output.

| Point of failure                               | Possible reason                                                                                   | Error message output                                                                                       |
|------------------------------------------------|---------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------|
| Establishing a connection with mbatchd         | mbatchd is too busy to accept new connections. The connect() system call times out.               | LSF is processing your request. Please wait...                                                             |
|                                                | mbatchd is down or there is no process listening at either the LSB_MBD_PORT or the LSB_QUERY_PORT | LSF is down. Please wait...                                                                                |
|                                                | mbatchd is down and the LSB_QUERY_PORT is busy                                                    | bhosts displays "LSF is down. Please wait. . ."<br>bj obs displays "Cannot connect to LSF. Please wait..." |
|                                                | Socket error on the client side                                                                   | Cannot connect to LSF. Please wait...                                                                      |
|                                                | connect() system call fails                                                                       | Cannot connect to LSF. Please wait...                                                                      |
|                                                | Internal library error                                                                            | Cannot connect to LSF. Please wait...                                                                      |
| Send/receive handshake message to/from mbatchd | mbatchd is busy. Client times out when waiting to receive a message from mbatchd.                 | LSF is processing your request. Please wait...                                                             |
|                                                | Socket read()/write() fails                                                                       | Cannot connect to LSF. Please wait...                                                                      |
|                                                | Internal library error                                                                            | Cannot connect to LSF. Please wait...                                                                      |

## Batch event format errors

When mbatchd and batch commands fail reading lsb\_event files, LSF logs and displays details about which event field was reached when parsing of the event file failed.

*event time\_stamp offset[byte:field]: field\_name [field\_name ...]*

where:

**event**

The name of the event being parsed.

**time\_stamp**

The timestamp of the event. Use this field to search for the problem record from history event files.

**offset[byte:field]**

Byte offset is the approximate position in the line (number of characters from beginning of the line) where parsing the fields failed.

Field offset is the number of field where parsing failed.

**field\_name**

the name of the fields being read when parsing failed.

## Examples

Errors like the following are logged to the `mbat chd log` file when `mbat chd` fails to read `lsb.events`:

```
Dec 28 14:25:30 2008 9861 3 7.02 init_log: Reading event file </home/user1/LSF7/work/LSF7/logdir/lsb.events>: Bad event format at line 15: JOB_NEW 1198869866 offset[28:3]: First 10 fields: jobId userId options numProcessors subTime beginTime termTime sigValue chkpntPeriod restartPid
Dec 28 14:25:30 2008 9861 3 7.02 init_log: Reading event file </home/user1/LSF7/work/LSF7/logdir/lsb.events>: Bad event format at line 16: bad eventVersion
Dec 28 14:25:30 2008 9861 3 7.02 switch_log(): reading event file </home/user1/LSF7/work/LSF7/logdir/lsb.events>: Bad event format at line 15: JOB_NEW 1198869866 offset[28:2]: First 10 fields: jobId userId options numProcessors subTime beginTime termTime sigValue chkpntPeriod restartPid
Dec 28 14:25:30 2008 9861 3 7.02 switch_log(): reading event file </home/user1/LSF7/work/LSF7/logdir/lsb.events>: Bad event format at line 16: bad eventVersion
```

Batch event format errors like the following are displayed by LSF batch commands:

### **bhist -l 309**

```
Dec 28 16:04:53 2008 8146 3 7.02 File /home/user1/LSF7/work/LSF7/logdir/lsb.events: Bad event format at line 20: JOB_EXECUTE 1198888660 offset[48:1]: execCwd
```

### **badadmin mbdhist**

```
File /home/user1/LSF7/work/LSF7/logdir/lsb.events: Bad event format at line 19: JOB_EXECUTE 1198888660 offset[48:1]: execCwd
File /home/user1/LSF7/work/LSF7/logdir/lsb.events: Bad event format at line 20: bad eventVersion
```

## EGO command messages

You cannot run the `egosh` command because the administrator has chosen not to enable EGO in `lsf.conf`: `LSF_ENABLE_EGO=N`.

If EGO is disabled, the `egosh` command cannot find `ego.conf` or cannot contact `vemkd` (not started).

# Understanding Platform LSF job exit information

## Contents

- Why did my job exit?
- How LSF translates events into exit codes
- Application and system exit values
- LSF job termination reason logging
- Job termination by LSF exit information
- LSF RMS integration exit values

## Why did my job exit?

LSF collects job information and reports the final status of a job. Traditionally jobs finishing normally report a status of 0, which usually means the job has finished normally. Any non-zero status means that the job has exited abnormally.

Most of the time, the abnormal job exit is related either to the job itself or to the system it ran on and not because of an LSF error. This document explains some of the information LSF provides about the abnormal job termination.

## How LSF translates events into exit codes

The following table summarizes LSF exit behavior for some common error conditions.

| Error condition                    | LSF exit code | Operating system | System exit code equivalent | Meaning                                                                                                                     |
|------------------------------------|---------------|------------------|-----------------------------|-----------------------------------------------------------------------------------------------------------------------------|
| Command not found                  | 127           | all              | 1 or 127                    | Command shell returns 1 if command not found. If the command cannot be found inside a job script, LSF return exit code 127. |
| Directory not available for output | 0             | all              | 1                           | LSF sends the output back to user through email if directory not available for output (bsub -o).                            |
| LSF internal error                 | -127, 127     | all              | N/A                         | RES returns -127 or 127 for all internal problems.                                                                          |
| Out of memory                      | N/A           | all              | N/A                         | Exit code depends on the error handling of the application itself.                                                          |
| LSF job states                     | 0             | all              | N/A                         | Exit code 0 is returned for all job states                                                                                  |

## Host failure

If an LSF server host fails, jobs running on that host are lost. No other jobs are affected. At initial job submission, you must submit a job with specific options for them to be automatically rerun from the beginning or restarted from a checkpoint on another host if they are lost because of a host failure.

- If a job is submitted with `bsub -r` or to a queue with `RERUNNABLE` set, it reruns automatically on host failure.
- If a job is submitted with `bsub -k` or to a checkpointable queue or application profile, it can be restarted if the host fails and the checkpoint succeeds.

If all of the hosts in a cluster go down, all running jobs are lost. When a host comes back up and takes over as master, it reads the `lsb.events` file to get the state of all batch jobs. Jobs that were running when the systems went down are assumed to have exited, and email is sent to the submitting user. Pending jobs remain in their queues, and are scheduled as hosts become available.

## Exited jobs

A job might terminate abnormally for various reasons. Job termination can happen from any state. An abnormally terminated job goes into `EXIT` state. The situations where a job terminates abnormally include:

- The job is cancelled by its owner or the LSF administrator while pending, or after being dispatched to a host.
- The job is not able to be dispatched before it reaches its termination deadline, and thus is aborted by LSF.
- The job fails to start successfully. For example, the wrong executable is specified by the user when the job is submitted.

The job exits with a non-zero exit status.

You can configure hosts so that LSF detects an abnormally high rate of job exit from a host. See *Administering Platform LSF* for more information.

## Application and system exit values

LSF monitors a job while running and returns the exit code returned from the job itself. LSF collects this exit code via `wait3()` system call on UNIX platforms. The exit code is a result of the system exit values. Use `bhist` or `bjobs` to see the exit code for your job.

## Application exit values

The most common cause of abnormal LSF job termination is due to application system exit values. If your application had an explicit exit value less than 128, `bjobs` and `bhist` display the actual exit code of the application; for example,

```
Exited with exit code 3
```

. You would have to refer to the application code for the meaning of exit code 3.

It is possible for a job to explicitly exit with an exit code greater than 128, which can be confused with the corresponding UNIX signal. Make sure that applications you write do not use exit codes greater than 128.

## System signal exit values

When you send a signal that terminates the job, LSF reports either the signal or the *signal\_value* +128. If the return status is greater than 128, and the job was terminated with a signal, then *return\_status*-128=signal. For example, return status 133 means that the job was terminated with signal 5 (SIGTRAP on most systems, 133-128=5). A job with exit status 130 was terminated with signal 2 (SIGINT on most systems, 130-128 = 2).

Some operating systems define exit codes as 0-255. As a result, negative exit values or values > 255 may have a wrap-around effect on that range. The most common example of this is a program that exits -1 will be seen with "exit code 255" in LSF.

How or why the job may have been signaled, or exited with a certain exit code, can be application and/or system specific. The application or system logs might be able to give a better description of the problem.

---

#### Note:

Termination signals are operating system dependent, so signal 5 may not be SIGTRAP and 11 may not be SIGSEGV on all UNIX and Linux systems. You need to pay attention to the execution host type in order to correct translate the exit value if the job has been signaled.

---

## bhist and bjobs output

In most cases, `bj obs` and `bhi st` show the application exit value ( $128 + \text{signal}$ ). In some cases, `bj obs` and `bhi st` show the actual signal value.

If LSF sends catchable signals to the job, it displays the exit value. For example, if you run `bki 11 jobID` to kill the job, LSF passes SIGINT, which causes the job to exit with exit code 130 (SIGINT is 2 on most systems,  $128+2 = 130$ ).

If LSF sends uncatchable signals to the job, then the entire process group for the job exits with the corresponding signal. For example, if you run `bki 11 -s SEGV jobID` to kill the job, `bj obs` and `bhi st` show

```
Exi ted by si gnal 7
```

## Example

The following example shows a job that exited with exit code 139, which means that the job was terminated with signal 11 (SIGSEGV on most systems,  $139-128=11$ ). This means that the application had a core dump.

#### **bjobs -l 2012**

```
Job <2012>, User , Project , Status , Queue , Command
Fri Dec 27 22:47:28: Submitted from host , CWD <SHOME>;
Fri Dec 27 22:47:37: Started on , Execution Home , Execution CWD ; Fri Dec 27
22:48:02: Exited with exit code 139. The CPU time used is 0.2 seconds.
SCHEDULING PARAMETERS:
          r15s  r1m  r15m  ut      pg    io   ls    it    tmp  swp
mem
loadSched -    -    -    -    -    -    -    -    -    -
loadStop  -    -    -    -    -    -    -    -    -    -
          cpuspeed  bandwi dth
loadSched -    -    -
loadStop  -    -    -
```

## LSF job termination reason logging

When LSF takes action on a job, it may send multiple signals. In the case of job termination, LSF will send, SIGINT, SIGTERM and SIGKILL in succession until the job has terminated. As a result, the job may exit with any of those corresponding exit values at the system level. Other actions may send "warning" signals to applications (SIGUSR2) etc. For specific signal sequences, refer to the LSF documentation for that feature.

Run `bhi st` to see the actions that LSF takes on a job:

```
bhist -l 1798
```

```

Job <1798>, User <user1>, Command <sleep 10000>
Tue Feb 25 16:35:31: Submitted from host <hostA>, to Queue <normal>, CWD <SHOME/lsf_7.0/conf/lsbatch/lsf_7.0/configdir>;
Tue Feb 25 16:35:51: Dispatched to <hostA>;
Tue Feb 25 16:35:51: Starting (Pid 12955);
Tue Feb 25 16:35:53: Running with execution home </home/user1>, Execution CWD </home/user1/Testing/lsf_7.0/conf/lsbatch/lsf_7.0/configdir>, Execution Pid <12955>;
Tue Feb 25 16:38:20: Signal <KILL> requested by user or administrator <user1>;
Tue Feb 25 16:38:22: Exited with exit code 130. The CPU time used is 0.1 seconds;
Summary of time in seconds spent in various states by Tue Feb 25 16:38:22
PEND    PSUSP    RUN      USUSP    SSUSP    UNKWN    TOTAL
  20      0        151      0         0         0        171
    
```

Here we see that LSF itself sent the signal to terminate the job, and the job exits 130 (130-128 = 2 = SIGINT).

When a job finishes, LSF reports the last job termination action it took against the job and logs it into lsb.acct.

If a running job exits because of node failure, LSF sets the correct exit information in lsb.acct, lsb.events, and the job output file.

## View logged job exit information (bacct -l)

1. Use bacct -l to view job exit information logged to lsb.acct:

```

bacct -l 7265
Accounting information about jobs that are:
- submitted by all users.
- accounted on all projects.
- completed normally or exited
- executed on all hosts.
- submitted to all queues.
- accounted on all service classes.
-----
Job <7265>, User <lsfadmin>, Project <default>, Status <EXIT>, Queue <normal>,
Command <srun sleep 100000>
Thu Sep 16 15:22:09: Submitted from host <hostA>, CWD <SHOME>;
Thu Sep 16 15:22:20: Dispatched to 4 Hosts/Processors <4*hostA>;
Thu Sep 16 15:23:21: Completed <exit>; TERM_RUNLIMIT: job killed after reaching LSF run time limit.
Accounting information about this job:
Share group charged </lsfadmin>
CPU_T    WAIT    TURNAROUND    STATUS    HOG_FACTOR    MEM    SWAP
  0.04     11         72      exit      0.0006       OK     OK
-----
SUMMARY:      ( time unit: second )
Total number of done jobs:      0      Total number of exited jobs:      1
Total CPU time consumed:      0.0      Average CPU time consumed:      0.0
Maximum CPU time of a job:      0.0      Minimum CPU time of a job:      0.0
Total wait time in queues:      11.0
Average wait time in queue:      11.0
Maximum wait time in queue:      11.0      Minimum wait time in queue:      11.0
Average turnaround time:      72 (seconds/job)
Maximum turnaround time:      72      Minimum turnaround time:      72
Average hog factor of a job:      0.00 ( cpu time / turnaround time )
Maximum hog factor of a job:      0.00      Minimum hog factor of a job:      0.00
    
```

## Termination reasons displayed by bacct

When LSF detects that a job is terminated, bacct -l displays one of the following termination reasons:

| Keyword displayed by bacct | Termination reason                                                                             | Integer value logged to JOB_FINISH in lsb.acct |
|----------------------------|------------------------------------------------------------------------------------------------|------------------------------------------------|
| TERM_ADMIN                 | Job killed by root or LSF administrator                                                        | 15                                             |
| TERM_BUCKET_KILL           | Job killed with bkill -b                                                                       | 23                                             |
| TERM_CHKPNT                | Job killed after checkpointing                                                                 | 13                                             |
| TERM_CPULIMIT              | Job killed after reaching LSF CPU usage limit                                                  | 12                                             |
| TERM_CWD_NOTEXIST          | Current working directory is not accessible or does not exist on the execution host            | 25                                             |
| TERM_DEADLINE              | Job killed after deadline expires                                                              | 6                                              |
| TERM_EXTERNAL_SIGNAL       | Job killed by a signal external to LSF                                                         | 17                                             |
| TERM_FORCE_ADMIN           | Job killed by root or LSF administrator without time for cleanup                               | 9                                              |
| TERM_FORCE_OWNER           | Job killed by owner without time for cleanup                                                   | 8                                              |
| TERM_LOAD                  | Job killed after load exceeds threshold                                                        | 3                                              |
| TERM_MEMLIMIT              | Job killed after reaching LSF memory usage limit                                               | 16                                             |
| TERM_OTHER                 | Member of a chunk job in WAIT state killed and requeued after being switched to another queue. | 4                                              |
| TERM_OWNER                 | Job killed by owner                                                                            | 14                                             |
| TERM_PREEMPT               | Job killed after preemption                                                                    | 1                                              |
| TERM_PROCESSLIMIT          | Job killed after reaching LSF process limit                                                    | 7                                              |
| TERM_REQUEUE_ADMIN         | Job killed and requeued by root or LSF administrator                                           | 11                                             |
| TERM_REQUEUE_OWNER         | Job killed and requeued by owner                                                               | 10                                             |
| TERM_RMS                   | Job exited from an RMS system error                                                            | 18                                             |
| TERM_RUNLIMIT              | Job killed after reaching LSF run time limit                                                   | 5                                              |
| TERM_SLURM                 | Job terminated abnormally in SLURM (node failure)                                              | 22                                             |
| TERM_SWAP                  | Job killed after reaching LSF swap usage limit                                                 | 20                                             |
| TERM_THREADLIMIT           | Job killed after reaching LSF thread limit                                                     | 21                                             |
| TERM_UNKNOWN               | LSF cannot determine a termination reason—0 is logged but TERM_UNKNOWN is not displayed        | 0                                              |
| TERM_WINDOW                | Job killed after queue run window closed                                                       | 2                                              |
| TERM_ZOMBIE                | Job exited while LSF is not available                                                          | 19                                             |

**Tip:**

The integer values logged to the JOB\_FINISH event in `lsb. acct` and termination reason keywords are mapped in `lsbat ch. h`.

## Restrictions

- If a queue-level `JOB_CONTROL` is configured, LSF cannot determine the result of the action. The termination reason only reflects what the termination reason could be in LSF.
- LSF cannot be guaranteed to catch any external signals sent directly to the job.
- In `MultiCluster`, a `brequeue` request sent from the submission cluster is translated to `TERM_OWNER` or `TERM_ADMIN` in the remote execution cluster. The termination reason in the email notification sent from the execution cluster as well as that in the `lsb. acct` is set to `TERM_OWNER` or `TERM_ADMIN`.

## Example output of `bacct` and `bhist`

| Example termination cause                               | Termination reason in <code>bacct -l</code>                                                                                                                                                  | Example <code>bhist</code> output                                                                                                                            |
|---------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>bkill -s KILL</code><br><code>bkill job_ID</code> | Completed <exit>; <code>TERM_OWNER</code> or <code>TERM_ADMIN</code>                                                                                                                         | Thu Mar 13 17:32:05: Signal <KILL> requested by user or administrator <user2>;<br>Thu Mar 13 17:32:06: Exited by signal 2. The CPU time used is 0.1 seconds; |
| <code>bkill -r</code>                                   | Completed <exit>; <code>TERM_FORCE_ADMIN</code> or <code>TERM_FORCE_OWNER</code> when <code>sbatchd</code> is not reachable.<br>Otherwise, <code>TERM_USER</code> or <code>TERM_ADMIN</code> | Thu Mar 13 17:32:05: Signal <KILL> requested by user or administrator <user2>;<br>Thu Mar 13 17:32:06: Exited by signal 2. The CPU time used is 0.1 seconds; |
| <code>TERMINATE_WHEN</code>                             | Completed <exit>; <code>TERM_LOAD/</code><br><code>TERM_WINDOWS/</code><br><code>TERM_PREEMPT</code>                                                                                         | Thu Mar 13 17:33:16: Signal <KILL> requested by user or administrator <user2>;<br>Thu Mar 13 17:33:18: Exited by signal 2. The CPU time used is 0.1 seconds; |
| Memory limit reached                                    | Completed <exit>; <code>TERM_MEMLIMIT</code>                                                                                                                                                 | Thu Mar 13 19:31:13: Exited by signal 2. The CPU time used is 0.1 seconds;                                                                                   |
| Run limit reached                                       | Completed <exit>; <code>TERM_RUNLIMIT</code>                                                                                                                                                 | Thu Mar 13 20:18:32: Exited by signal 2. The CPU time used is 0.1 seconds.                                                                                   |
| CPU limit                                               | Completed <exit>; <code>TERM_CPULIMIT</code>                                                                                                                                                 | Thu Mar 13 18:47:13: Exited by signal 24. The CPU time used is 62.0 seconds;                                                                                 |
| Swap limit                                              | Completed <exit>; <code>TERM_SWAPLIMIT</code>                                                                                                                                                | Thu Mar 13 18:47:13: Exited by signal 24. The CPU time used is 62.0 seconds;                                                                                 |

| Example termination cause           | Termination reason in bacct -l                                                        | Example bhist output                                                                                                                                                                    |
|-------------------------------------|---------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Regular job exits when host crashes | Rusage 0,<br>Completed <exit>;<br>TERM_ZOMBIE                                         | Thu Jun 12 15:49:02: Unknown; unable to reach the execution host;<br>Thu Jun 12 16:10:32: Running;<br>Thu Jun 12 16:10:38: Exited with exit code 143. The CPU time used is 0.0 seconds; |
| bqueue -r                           | For each requeue,<br>Completed <exit>;<br>TERM_REQUEUE_ADMIN or<br>TERM_REQUEUE_OWNER | Thu Mar 13 17:46:39: Signal <REQUEUE_PEND> requested by user or administrator <user2>;<br>Thu Mar 13 17:46:56: Exited by signal 2. The CPU time used is 0.1 seconds;                    |
| bchkpnt -k                          | On the first run:<br>Completed <exit>;<br>TERM_CHKPNT                                 | Wed Apr 16 16:00:48: Checkpoint succeeded (actpid 931249);<br>Wed Apr 16 16:01:03: Exited with exit code 137. The CPU time used is 0.0 seconds;                                         |
| Kill -9 <RES> and job               | Completed <exit>;<br>TERM_EXTERNAL_SIGNAL                                             | Thu Mar 13 17:30:43: Exited by signal 15. The CPU time used is 0.1 seconds;                                                                                                             |
| Others                              | Completed <exit>;                                                                     | Thu Mar 13 17:30:43: Exited with 3; The CPU time used is 0.1 seconds;                                                                                                                   |

## Job termination by LSF exit information

LSF also provides additional information in the POST\_EXEC of the job. Use this information to detect conditions where LSF has terminated the job and take the appropriate action.

The job exit information in the POST\_EXEC is defined in 2 parts:

- `LSB_JOBEXIT_STAT`—the raw `wai t 3()` output (converted using the wait macros `/usr/include/sys/wait.h`)
- `LSB_JOBEXIT_INFO`—defined only if the job exit was due to a defined LSF reason.

Queue-level POST\_EXEC commands should be written by the cluster administrator to perform whatever task is necessary for specific exit situations.

### Note:

System level enforced limits like CPU and Memory (listed above), cannot be shown in the `LSB_JOBEXIT_INFO` since it is the operating system performing the action and not LSF. Set appropriate parameters in the queue or at job submission to allow LSF to enforce the limits, which makes this information available to LSF.

## Common `LSB_JOBEXIT_STAT` and `LSB_JOBEXIT_INFO` values

The following is a table of common scenarios covered and not covered by the `LSB_JOBEXIT_INFO`

## Understanding Platform LSF job exit information

| Example termination cause                                    | LSB_JOBEXIT_STAT | LSB_JOBEXIT_INFO             | Example bhist output                                                                                                                                                                                                                                                  |
|--------------------------------------------------------------|------------------|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Job killed with the SIGINT bkill -s INT 520                  | 33280            | SIGNAL 2 INT                 | Fri Feb 14 16:48:00: Exited with exit code 130. The CPU time used is 0.2 seconds;                                                                                                                                                                                     |
| Job killed with SIGTERM bkill -s TERM 521                    | 36608            | SIGNAL 15 TERM               | Fri Feb 14 16:49:50: Exited with exit code 143. The CPU time used is 0.2 seconds;                                                                                                                                                                                     |
| Job killed with SIGKILL bkill -s KILL 522                    | 33280            | SIGNAL -14 SIG_TERM_USER     | Fri Feb 14 16:51:03: Exited with exit code 130. The CPU time used is 0.2 seconds;                                                                                                                                                                                     |
| Automatic migration when MIG is defined at queue level       | 33280            | SIGNAL -1 SIG_CHKPNT         | Fri Feb 14 17:32:17: Job has been requeued; Fri Feb 14 17:32:17: Pending: Migrating job is waiting for rescheduling;                                                                                                                                                  |
| bsub -l "hostname;exit 130"                                  | 33280            | Undefined                    | Fri Feb 14 14:41:51: Exited with exit code 130. The CPU time used is 0.2 seconds;                                                                                                                                                                                     |
| Killing the job with bkill command bkill 210                 | 33280            | SIGNAL -14 SIG_TERM_USER     | Fri Feb 14 14:45:51: Exited with exit code 130. The CPU time used is 0.2 seconds;                                                                                                                                                                                     |
| Job being brequeued. brequeue -r Job <211> is being requeued | 33280            | SIGNAL -23 SIG_KILL_REQUEUE  | Fri Feb 14 14:48:15: Signal <REQUEUE_PEND> requested by user or administrator <iayaz>; Fri Feb 14 14:48:18: Exited with exit code 130. The CPU time used is 0.2 second                                                                                                |
| Job being migrated bmig -m togni Job <213> is being migrated | 33280            | SIGNAL -1 SIG_CHKPNT         | Fri Feb 14 15:04:42: Migration requested by user or administrator <iayaz>; Specified Hosts <toigni>; Fri Feb 14 15:04:44: Job is being requeued; Fri Feb 14 15:05:01: Job has been requeued; Fri Feb 14 15:05:01: Pending: Migrating job is waiting for rescheduling; |
| Job killed due REQUEUE_EXIT_VALUE bsub "sleep 100;exit 34"   | 8704             | Undefined                    | Fri Feb 14 15:10:21: Pending: Requeued job is waiting for rescheduling;(exit code 34);                                                                                                                                                                                |
| Job killed by LSF when CPULIMIT enforced by LSF              | 158              | SIGNAL -24 SIG_TERM_CPULIMIT | Wed Feb 19 14:18:13: Exited by signal 30. The CPU time used is 89.4 seconds.                                                                                                                                                                                          |
| Job killed because queue level CPULIMIT is reached.          | 40448            | Undefined                    | Fri Feb 14 15:30:01: Exited with exit code 158. The CPU time used is 61.2 seconds;                                                                                                                                                                                    |

| Example termination cause                                                               | LSB_JOBEXIT_STAT | LSB_JOBEXIT_INFO             | Example bhist output                                                                                                                 |
|-----------------------------------------------------------------------------------------|------------------|------------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Job killed because queue level RUNLIMIT is reached.                                     | 37120            | Undefined                    | Fri Feb 14 15:37:44: Exited with exit code 145. The CPU time used is 0.2 seconds;                                                    |
| Job killed due to the check pointing. bchkpnt - k 838 Job <838> is being checkpointed   | 9                | SIGNAL -1 SIG_CHKPNT         | Fri Feb 14 17:59:12: Checkpoint succeeded (actpid 25298); Fri Feb 14 17:59:12: Exited by signal 9. The CPU time used is 0.1 seconds; |
| Job killed when reaches the MEMLIMIT bsub -M 5 "/home/iayaz/script/memwrite -m 10 -r 2" | 2                | SIGNAL -25 SIG_TERM_MEMLIMIT | Fri Feb 21 10:50:50: Exited by signal 2. The CPU time used is 0.1 seconds;                                                           |
| Job killed when termination time approaches bsub -t 21:11:10 sleep 500;date             | 37120            | Undefined                    | Exited with exit code 145. The CPU time used is 0.2 seconds;                                                                         |
| Job killed when TERMINATE_WHEN = LOAD                                                   | 33280            | SIGNAL -15 SIG_TERM_LOAD     | Exited with exit code 130. The CPU time used is 7.2 seconds.                                                                         |
| Job killed when TERMINATE_WHEN = PREEMPT                                                | 33280            | SIGNAL -16 SIG_TERM_PREEMPT  | Exited with exit code 130. The CPU time used is 0.3 seconds;                                                                         |

## LSF RMS integration exit values

For the RMS integrations with LSF (HP AlphaServer SC and Linux QsNet), LSF jobs running through RMS will return `rms_run()` return code as the job exit code. RMS documents certain exit codes and corresponding job exit reasons.

See the `rms_run()` man page for more information.

Upon successful completion, `rms_run()` returns the global OR of the exit status values of the processes in the parallel program. If one of the processes is killed, `rms_run()` returns a status value of 128 plus the signal number. It can also return the following codes:

| Return Code | RMS Meaning                                                                                                      |
|-------------|------------------------------------------------------------------------------------------------------------------|
| 0           | A process exited with the code 127 (GLOBAL EXIT), which indicates success, causing all of the processes to exit. |
| 123         | A process exited with the code 123 (GLOBAL ERROR) causing all of the processes to exit.                          |
| 124         | The node the job executing on has been removed from the system.                                                  |
| 125         | One or more processes were still running when the exit timeout expired.                                          |
| 126         | The resource is inadequate for the request.                                                                      |



---

# Index

.lsftask file 584  
.rhosts file 645  
/etc/hosts file 645  
/etc/hosts.equiv file 645  
/tmp\_mnt directory 643

## A

abnormal job termination 656  
ABS\_RUNLIMIT  
    lsb.params file 172, 262  
ACCT\_ARCHIVE\_AGE  
    lsb.params file 263  
ACCT\_ARCHIVE\_SIZE  
    lsb.params file 263  
ACCT\_ARCHIVE\_TIME  
    lsb.params file 264  
ADJUST\_DURATION  
    lsf.cluster file 406  
ADMIN  
    lsb.hosts file 254  
    lsf.licensescheduler file Parameters section 545  
administrator  
    user group 396  
ADMINISTRATORS  
    lsb.queues file 313  
    lsf.cluster file 416  
ALLOCATION  
    lsf.licensescheduler file Feature section 556  
application-level job checkpoint and restart  
    description 100  
application-specific job checkpoint and restart  
    configuring 106  
    enabling 106  
APS\_PRIORITY  
    lsb.queues file 313  
ARCHITECTURE  
    lsf.shared file 574  
AUTH  
    lsf.licensescheduler file Parameters section 545

automatic time-based configuration  
    lsb.hosts 256  
    lsb.params 309  
    lsb.queues 357  
    lsb.resources 385  
    lsb.users 401  
    lsf.licensescheduler 570  
automount, NFS (Network File System) 643

## B

BACKFILL  
    lsb.queues file 314  
between-host user account mapping  
    description 7  
        local user account mapping  
            configuring 9  
            example 10  
    scope 8  
        Windows workgroup  
            configuring 9  
        Windows workgroup account mapping  
            example 10  
BIND\_JOB 173  
BLC\_HEARTBEAT\_FACTOR  
    lsf.licensescheduler file Parameters section 551  
bld  
    License Scheduler daemon 553  
bld.license.acct file 135  
BSUB\_BLOCK variable 601  
BSUB\_QUIET variable 602  
BSUB\_QUIET2 variable 603  
BSUB\_STDERR variable 603

## C

CACHE\_INTERVAL  
    lsf.cluster file 424  
checkpoint and restart

- description 98
- CHKPNT
  - lsb.hosts file 242
  - lsb.queues file 314
- CHKPNT\_DIR
  - lsb.applications file 173
- CHKPNT\_INITPERIOD
  - lsb.applications file 174
- CHKPNT\_METHOD
  - lsb.applications file 175
- CHKPNT\_PERIOD
  - lsb.applications file 175
- chunk jobs
  - CHKPNT parameter in lsb.queues 314
  - MIG parameter in lsb.queues 186, 336
  - rerunnable 192, 346
- CHUNK\_JOB\_DURATION
  - lsb.params file 264
- CHUNK\_JOB\_SIZE
  - lsb.applications file 175
  - lsb.queues file 315
- CLEAN\_PERIOD
  - lsb.params file 265
- CLEARCASE\_DRIVE variable 604
- CLEARCASE\_MOUNTDIR variable 604
- CLEARCASE\_ROOT variable 605
- ClusterName
  - lsf.shared file 572
- CLUSTERNAME
  - lsf.cluster file 424
- CLUSTERS
  - lsf.licensescheduler file Clusters section 551
- Clusters section
  - lsf.licensescheduler file
    - description 551
- COMMITTED\_RUN\_TIME\_FACTOR
  - lsb.params file 265
- COMPUTE\_UNIT\_TYPES
  - lsb.params file 266
- CONDENSE
  - lsb.hosts file 246, 252
- CONDENSE\_PENDING\_REASONS
  - lsb.params file 266
- configurable job ID limit 290
- CONSUMABLE
  - lsf.shared file 576
- CONSUMER
  - bsla 388
  - lsb.serviceclasses file 388
- CONTROL\_ACTION
  - lsb.serviceclasses file 388
- CORELIMIT
  - lsb.applications file 176
  - lsb.queues file 316
- cores
  - setting cluster to 429
- CPU\_TIME\_FACTOR
  - lsb.params file 267
- CPUFACTOR
  - lsf.shared file 574
- CPULIMIT
  - lsb.applications file 177
  - lsb.queues file 316
- Cray checkpointing 242
- cross-cluster account mapping 400
- cross-cluster account mapping in MultiCluster 400
- cross-cluster user account mapping
  - configuring 13
  - description 12
  - enabling 13
  - scope 8, 13
    - system level
      - configuring 13
      - example 14
    - user level
      - configuring 13
      - examples 15
- cross-cluster user account mapping in MultiCluster 400
- CSA (IRIX Comprehensive System Accounting)
  - configuring and using 491
- cshrc.lsf file
  - description 137
  - setting the LSF environment 138
- CUMULATIVE\_RUSAGE
  - LSF HPC extensions parameter 496
- custom resources
  - reserving 384

## D

- daemons
  - automatic shut down 430
  - security 534
- DATALIMIT
  - lsb.applications file 177
  - lsb.queues file 317

DB\_HOST  
     install.config file 150  
 dedicated resource. *See* exclusive resource 419  
 DEFAULT\_APPLICATION  
     lsb.params file 267  
 DEFAULT\_EXTSCHED  
     lsb.queues file 317  
 DEFAULT\_HOST\_SPEC  
     lsb.params file 267  
     lsb.queues file 318  
 DEFAULT\_JOBGROUP  
     lsb.params file 268  
 DEFAULT\_PROJECT  
     lsb.params file 269  
 DEFAULT\_QUEUE  
     lsb.params file 269  
 DEFAULT\_SLA\_VELOCITY  
     lsb.params file 269  
 DESCRIPTION  
     lsb.applications file 178  
     lsb.queues file 318  
     lsb.serviceclasses file 389  
     lsf.licensescheduler file Project section 570  
     lsf.licensescheduler file ProjectGroup section 569  
     lsf.shared file 577  
 DETECT\_IDLE\_JOB\_AFTER  
     lsb.params file 270  
 DIRECTION  
     lsb.users file 400  
 DISABLE\_UACCT\_MAP  
     lsb.params file 270  
 DISP\_RES\_USAGE\_LIMITS  
     LSF HPC extensions parameter 496  
 DISPATCH\_ORDER  
     lsb.queues file 318  
 DISPATCH\_WINDOW  
     lsb.hosts file 242  
     lsb.queues file 319  
 DISTRIBUTION  
     lsb.resources file HostExport section 377  
     lsb.resources file SharedResourceExport section 379  
     lsf.licensescheduler file Feature section 554  
 DISTRIBUTION\_POLICY\_VIOLATION\_ACTION  
     lsf.licensescheduler file Parameters section 545  
 DJOB\_COMMFAIL\_ACTION  
     lsb.applications file 178  
 DJOB\_DISABLED  
     lsb.applications file 178  
 DJOB\_ENV\_SCRIPT  
     lsb.applications file 179  
 DJOB\_HB\_INTERVAL  
     lsb.applications file 179  
 DJOB\_RU\_INTERVAL  
     lsb.applications file 180  
 dual-core CPUs  
     enabling detection 492  
 dual-stack hosts  
     setting to IPv6 only 487  
 DYNAMIC  
     lsf.licensescheduler file Feature section 565

## E

EADMIN\_TRIGGER\_DURATION  
     lsb.params file 270  
 echkpnt  
     configuring 106  
     enabling 106  
     naming convention 103  
     syntax 104  
 eexec  
     configuring 75, 88  
     definition 73  
     enabling 75, 88  
     example of monitoring execution environment 87  
     specifying a user account 88  
     typical uses 74  
 EGO administrator login bypass  
     enabling 34, 35  
 EGO\_BINDIR  
     cshrc.lsf and profile.lsf files 142  
 EGO\_CONF\_RETRY\_INT parameter in ego.conf 479  
 EGO\_CONF\_RETRY\_MAX parameter in ego.conf 479  
 EGO\_CONFDIR  
     cshrc.lsf and profile.lsf files 142  
 EGO\_DAEMON\_CONTROL  
     install.config file 150, 590  
 EGO\_DEBUG\_LIM parameter in ego.conf 484  
 EGO\_DHCP\_ENV parameter in ego.conf 486  
 EGO\_DYNAMIC\_HOST\_TIMEOUT parameter in ego.conf 488  
 EGO\_DYNAMIC\_HOST\_WAIT\_TIME parameter in ego.conf 489  
 EGO\_ENABLE\_AUTO\_DAEMON\_SHUTDOWN 430  
 EGO\_ENABLE\_DUALCORE parameter in ego.conf 492  
 EGO\_ESLIM\_TIMEOUT 430

EGO\_ESRVDIR  
     cshrc.lsf and profile.lsf files 143  
 EGO\_LIBDIR  
     cshrc.lsf and profile.lsf files 143  
 EGO\_LIM\_CONNTIMEOUT parameter in ego.conf 474  
 EGO\_LIM\_DEBUG parameter in ego.conf 509  
 EGO\_LIM\_PORT parameter in ego.conf 510  
 EGO\_LIM\_RECVTIMEOUT parameter in ego.conf 475  
 EGO\_LOCAL\_CONFDIR  
     cshrc.lsf and profile.lsf files 144  
 EGO\_LOCAL\_RESOURCES parameter in ego.conf 512  
 EGO\_LOG\_MASK parameter in ego.conf 484, 513  
 EGO\_MASTER\_LIST parameter in ego.conf 519  
 EGO\_PERF\_CONTROL  
     install.config file 151  
 EGO\_PIM\_INFODIR parameter in ego.conf 525  
 EGO\_PIM\_SLEEPTIME parameter in ego.conf 525  
 EGO\_PIM\_SLEEPTIME\_UPDATE parameter in ego.conf 526  
 EGO\_PMC\_CONTROL  
     install.config file 151  
 EGO\_RES\_REQ  
     bsla 389  
     lsb.serviceclasses file 389  
 EGO\_RSH parameter in ego.conf 531  
 EGO\_SERVERDIR  
     cshrc.lsf and profile.lsf files 144  
 EGO\_STATIC\_LIM\_TIMEOUT 430  
 EGO\_STRIP\_DOMAIN parameter in ego.conf 535  
 EGO\_TIME\_LIM parameter in ego.conf 536  
 EGO\_TOP  
     cshrc.lsf and profile.lsf files 145  
 ego.conf file  
     corresponding lsf.conf parameters 428  
     LSF parameter migration for upgrade 428  
     managing error logs 484  
 egroup  
     configuring 130  
     creating 130  
     description 128  
     enabling 130  
     scope 129  
 elim  
     configuring 118  
     creating 120  
     description 116  
     enabling 118  
     example 122  
     overriding a built-in load index 122  
     scope 118  
 ELIM\_ABORT\_VALUE variable 606  
 ELIM\_POLL\_INTERVAL  
     lsf.cluster file 406  
 ELIMARGS  
     lsf.cluster file 406  
 email  
     configuring on UNIX 452  
 ENABLE\_DEFAULT\_EGO\_SLA  
     lsb.params file 271  
 ENABLE\_DYNAMIC\_HOSTS  
     install.config file 152  
 ENABLE\_DYNAMIC\_RUSAGE  
     lsf.licensescheduler file Feature section 565  
 ENABLE\_EGO  
     install.config file 152, 591  
 ENABLE\_EVENT\_STREAM  
     lsb.params file 271  
 ENABLE\_HIST\_RUN\_TIME  
     lsb.params file 272  
 ENABLE\_HOST\_INTERSECTION  
     lsb.params¶ 272  
 ENABLE\_HPC\_INST  
     install.config file 152  
 ENABLE\_INTERACTIVE  
     lsf.licensescheduler file Parameters section 546  
 ENABLE\_MINJOB\_PREEMPTION  
     lsf.licensescheduler file Feature section 565  
 ENABLE\_USER\_RESUME  
     lsb.params file 273  
 encryption  
     esub 83  
     X-Window 85  
 ENFORCE\_ONE\_UG\_LIMITS  
     lsb.params file 273  
 environment variables  
     BSUB\_BLOCK 601  
     BSUB\_QUIET 602  
     BSUB\_QUIET2 603  
     BSUB\_STDERR 603  
     CLEARCASE\_DRIVE 604  
     CLEARCASE\_MOUNTDIR 604  
     CLEARCASE\_ROOT 605  
     ELIM\_ABORT\_VALUE 606  
     LM\_LICENSE\_FILE 606  
     LS\_EXEC\_T 606  
     LS\_JOBPID 607  
     LS\_LICENSE\_SERVER\_feature 607

LS\_SUBCWD 607  
 LSB\_CHKPNT\_DIR 608  
 LSB\_DEBUG 608  
 LSB\_DEBUG\_CMD 608  
 LSB\_DEBUG\_MBD 608  
 LSB\_DEBUG\_NQS 608  
 LSB\_DEBUG\_SBD 608  
 LSB\_DEBUG\_SCH 609  
 LSB\_DEFAULT\_JOBGROUP 609  
 LSB\_DEFAULTPROJECT 610  
 LSB\_DEFAULTQUEUE 610  
 LSB\_DJOB\_COMMMFAIL\_ACTION 623  
 LSB\_DJOB\_ENV\_SCRIPT 624  
 LSB\_ECHKPNT\_KEEP\_OUTPUT 611  
 LSB\_ECHKPNT\_METHOD 611  
 LSB\_ECHKPNT\_METHOD\_DIR 611  
 LSB\_ERESTART\_USRCMD 611  
 LSB\_EXEC\_RUSAGE 612  
 LSB\_EXECHOSTS 612  
 LSB\_EXIT\_IF\_CWD\_NOTEXIST 613  
 LSB\_EXIT\_PRE\_ABORT 613  
 LSB\_EXIT\_REQUEUE 613  
 LSB\_FRAMES 614  
 LSB\_HOSTS 614  
 LSB\_INTERACTIVE 615  
 LSB\_JOB\_INCLUDE\_POSTPROC 615  
 LSB\_JOBEXIT\_INFO 616  
 LSB\_JOBEXIT\_STAT 616  
 LSB\_JOBFILENAME 617  
 LSB\_JOBGROUP 617  
 LSB\_JOBID 617  
 LSB\_JOBINDEX 618  
 LSB\_JOBINDEX\_STEP 618  
 LSB\_JOBNAME 619  
 LSB\_JOBPEND 620  
 LSB\_JOBPGIDS 620  
 LSB\_JOBPIIDS 620  
 LSB\_MAILSIZE 620  
 LSB\_MCPU\_HOSTS 621  
 LSB\_NQS\_PORT 622  
 LSB\_NTRIES 622  
 LSB\_OLD\_JOBID 623  
 LSB\_OUTPUT\_TARGETFAILED 623  
 LSB\_QUEUE 625  
 LSB\_REMOTEINDEX 625  
 LSB\_REMOTEJID 625  
 LSB\_RESTART 625  
 LSB\_RESTART\_PGID 626  
 LSB\_RESTART\_PID 626  
 LSB\_RTASK\_GONE\_ACTION 627  
 LSB\_SUB\_APP\_NAME 627  
 LSB\_SUB\_CLUSTER 628  
 LSB\_SUB\_COMMAND\_LINE 628  
 LSB\_SUB\_EXTSCHED\_PARAM 628  
 LSB\_SUB\_JOB\_ACTION\_WARNING\_TIME 628  
 LSB\_SUB\_JOB\_WARNING\_ACTION 628  
 LSB\_SUB\_PARM\_FILE 629  
 LSB\_SUCCESS\_EXIT\_VALUES 629  
 LSB\_SUSP\_REASONS 629  
 LSB\_SUSP\_SUBREASONS 630  
 LSB\_UNIXGROUP 631  
 LSB\_USER\_BIND\_CPU\_LIST 631  
 LSB\_USER\_BIND\_JOB 631  
 LSF\_CMD\_LOGDIR 631  
 LSF\_DEBUG\_CMD 631  
 LSF\_DEBUG\_LIM 631  
 LSF\_DEBUG\_RES 631  
 LSF\_EAUTH\_AUX\_DATA 632  
 LSF\_EAUTH\_AUX\_PASS 632  
 LSF\_EAUTH\_CLIENT 632  
 LSF\_EAUTH\_SERVER 632  
 LSF\_EAUTH\_UID 633  
 LSF\_EXECUTE\_DOMAIN 633  
 LSF\_INTERACTIVE\_STDERR 633  
 LSF\_INVOKE\_CMD 633  
 LSF\_JOB\_STARTER 634  
 LSF\_LD\_LIBRARY\_PATH 635  
 LSF\_LIM\_API\_NTRIES 636  
 LSF\_LIM\_DEBUG 636  
 LSF\_LOGDIR 636  
 LSF\_MASTER 636  
 LSF\_NIOS\_DEBUG 637  
 LSF\_NIOS\_DIE\_CMD 637  
 LSF\_NIOS\_IGNORE\_SIGWINDOW 637  
 LSF\_NIOS\_PEND\_TIMEOUT 637  
 LSF\_NIOS\_PORT\_RANGE 638  
 LSF\_RESOURCES 638  
 LSF\_TS\_LOGON\_TIME 639  
 LSF\_USE\_HOSTEQUIV 639  
 LSF\_USER\_DOMAIN 640  
 EP\_BACKUP  
     install.config file 153  
     slave.config file 591  
 EQUIV  
     lsf.cluster file 424  
 erestart

- configuring 106
  - enabling 106
  - naming convention 103
  - syntax 104
- error logs
  - EGO\_LOG\_MASK parameter 484
- errors
  - lsb.events record format 653
- esub
  - configuring 75, 88
  - configuring a mandatory esub 88
  - definition 70
  - enabling 75, 88
  - example of changing job parameters 87
  - example of validating job parameters 86
  - naming convention 76
  - order in which multiple esubs run 72
  - typical uses 71
- event record format errors 653
- EVENT\_ADRSV\_FINISH record
  - lsb.acct 168
- EVENT\_STREAM\_FILE
  - lsb.params file 274
- EVENT\_UPDATE\_INTERVAL
  - lsb.params file 274
- EXCLUSIVE
  - lsb.queues file 319
- exclusive resource 419
- EXINTERVAL
  - lsf.cluster file 407
- EXIT job state
  - abnormal job termination 656
- EXIT\_RATE
  - lsb.hosts file 242
- EXIT\_RATE\_TYPE
  - lsb.params file 275
- external authentication
  - configuration of 24
  - configuring 23
    - daemon authentication
      - enabling 24
    - daemon credentials
      - description 22
  - description 22
    - eauth user name
      - configuration of 26
  - enabling 23, 24
  - encryption key
    - configuration of 26
    - host credentials
      - description 22
    - Kerberos
      - configuration of 27
        - eauth user name
          - configuration of 27
        - enabling 27
      - Kerberos authentication
        - configuration 26
        - description 22
      - Kerberos daemon authentication
        - enabling 27
        - non-Solaris 27
        - Solaris 27
      - LSF\_AUTH parameter 475
      - scope 23
        - user credentials
          - description 22
  - external encryption key
    - configuring 26
  - external host and user groups
    - configuring 130
    - defining 130
    - description 128
      - egroup
        - creating 130
      - enabling 130
      - importing 132
      - retrieving 132
      - scope 129
  - external host groups
    - egroup
      - creating 130
  - external load indices
    - behavior 123
    - benefits 116
    - commands 126
    - configuration to modify 126
    - configuring 118
    - description 116
      - elim
        - creating 120
        - example 122
          - host locations
            - environment variables 124
            - resource mapping 124
          - multiple executables 123

- overriding a built-in load index 122
- enabling 118
- resource mapping 120
- scope 118
- external resource
  - defining 118
  - defining a dynamic resource 118
- external user groups
  - egroup
    - creating 130

## F

- FAIRSHARE
  - Isb.queues file 320
- FAIRSHARE\_ADJUSTMENT\_FACTOR
  - Isb.params file 275
- FAIRSHARE\_QUEUES
  - Isb.queues file 320
- Feature section
  - Isf.licensescheduler file
    - description 553
- FeatureGroup
  - Isf.licensescheduler 566
- FILELIMIT
  - Isb.applications file 181
  - Isb.queues file 321
- files
  - adding default system lists 585
  - removing default system lists 585
  - viewing task lists 585
- FLEX\_NAME
  - Isf.licensescheduler file Feature section 554
- FLOAT\_CLIENTS
  - Isf.cluster file 407
- FLOAT\_CLIENTS\_ADDR\_RANGE
  - Isf.cluster file 408

## G

- GLOBAL\_EXIT\_RATE
  - Isb.params file 272, 276
- GOALS
  - Isb.serviceclasses file 389
- GROUP
  - Isf.licensescheduler file Feature section 558
  - Isf.licensescheduler file ProjectGroup section 567
- GROUP\_ADMIN

- Isb.hosts file 247
- GROUP\_DISTRIBUTION
  - Isf.licensescheduler file Feature section 558
- GROUP\_MEMBER
  - Isb.hosts file 246
  - Isb.users file 396
- GROUP\_NAME
  - Isb.hosts file 245
  - Isb.users file 396
- GRP\_ADD record
  - Isb.events 235
- GRP\_MOD record
  - Isb.events 236

## H

- hierarchical fairshare user groups 397
- HIST\_HOURS
  - Isb.params file 276
- HJOB\_LIMIT
  - Isb.queues file 322
- host failure 655
- host groups
  - EGO enabled 324
  - external
    - configuring 130
    - defining 130
    - description 128
    - retrieving 132
- host management
  - daemon clean up 430
- host models
  - automatic detection 574
- host types
  - automatic detection 574
- HOST\_CTRL record
  - Isb.events 216
- HOST\_INACTIVITY\_LIMIT
  - Isf.cluster file 410
- HOST\_NAME
  - Isb.hosts file 241
- HostExport section
  - Isb.resources 375
- HOSTNAME
  - Isf.cluster file 418
- HOSTRESORDER variable 645
- hosts
  - exclusive resource 419

HOSTS

- lsb.hosts file 250
- lsb.queues file 322
- lsb.resources file Limit section 362
- lsb.resources file ResourceReservation section 380
- lsf.licensescheduler file Parameters section 546

hosts file 146

HPART\_NAME

- lsb.hosts file 250

I

identd 475

identification daemon authentication

- LSF\_AUTH parameter 475

identification daemons 475

IGNORE\_DEADLINE

- lsb.queues file 325

IMPT\_JOBBKLG

- lsb.queues file 325

INCREASING

- lsf.shared file 576

install.config file

- description 149

INTERACTIVE

- lsb.queues file 326

INTERRUPTIBLE\_BACKFILL

- lsb.queues file 326

INTERVAL

- lsf.shared file 576

io

- lsb.hosts file 244
- lsb.queues file 332

IPv6

- dual-stack hosts 487
- enable 493
- example 146, 148
- in FLOAT\_CLIENTS\_ADDR\_RANGE 409
- in LSF\_HOST\_ADDR\_RANGE 413
- loopback address 644

IRIX ULDB (User Limits Database)

- description 538
- jlimit.in file 538

it

- lsb.hosts file 244
- lsb.queues file 332

J

JL/P

- lsb.users file 399

JL/U

- lsb.hosts file 243

jlimit.in file

- IRIX ULDB 538

job checkpoint and restart

- application level
  - configuring 103
  - description 100
  - enabling 103
- application-level
  - chkpnt requirements 103
  - restart requirements 103
- checkpoint directory 105
- checkpoint files 105
- commands 108
- configuration to checkpoint jobs before suspension or termination 108
- configuration to copy open job files to the checkpoint directory 108
- configuration to save stderr and stdout 107
- configuration to specify directory for application-level executables 107
- configuration to specify mandatory application-level executables 106
- configuring 101
- description 98
- chkpnt 98
- enabling 101
- restart 98
  - kernel level
    - configuring 102
    - description 99
    - enabling 102
  - queue level
    - configuring 102
- scope 100
  - user level
    - configuring 102
    - description 100
    - enabling 102

job ID

- limit 290
- rollover 290
- sequencing 290

job migration

- absolute job priority scheduling 97, 313
  - automatic
    - configure at host level 95

- configure at queue level 95
    - configuring 95
    - enabling 95
  - configuration to modify 96
  - configuring 93
  - description 91
  - enabling 93
  - scope 92
- job preemption
  - description 50
  - job slot limits 55
- job slot limits
  - calculation of usage for preemption 54
- job states
  - EXIT
    - abnormal job termination 656
- job submission and execution controls
  - configuring 75, 88
  - description 70
  - enabling 75, 88
  - scope 75
- JOB\_ACCEPT record
  - Isb.events 211
- JOB\_ACCEPT\_INTERVAL
  - Isb.params file 276
  - Isb.queues file 327
- JOB\_ACTION\_WARNING\_TIME
  - Isb.queues file 328
- JOB\_ATTA\_DATA record
  - Isb.events 228
- JOB\_ATTA\_DIR
  - Isb.params file 277
- JOB\_CHUNK record
  - Isb.events 229
- JOB\_CLEAN record
  - Isb.events 226
- JOB\_CONTROLS
  - Isb.queues file 328
- JOB\_DEP\_LAST\_SUB
  - Isb.params file 278
- JOB\_EXECUTE record
  - Isb.events 225
- JOB\_EXIT\_RATE\_DURATION
  - Isb.params file 278
- JOB\_EXT\_MSG record
  - Isb.events 228
- JOB\_FINISH record
  - Isb.acct 163
- JOB\_FORCE record
  - Isb.events 234
- JOB\_FORWARD record
  - Isb.events 211
- JOB\_GROUP\_CLEAN
  - Isb.params file 278
- JOB\_IDLE
  - Isb.queues file 329
- JOB\_INCLUDE\_POSTPROC parameter
  - Isb.applications 181
  - Isb.params 279
- JOB\_MODIFY2 record
  - Isb.events 220
- JOB\_MOVE record
  - Isb.events 215
- JOB\_NEW record
  - Isb.events 206
- JOB\_OVERRUN
  - Isb.queues file 330
- JOB\_POSITION\_CONTROL\_BY\_ADMIN
  - Isb.params file 279
- JOB\_POSTPROC\_TIMEOUT parameter
  - Isb.applications 181
  - Isb.params 280
- JOB\_PRIORITY\_OVER\_TIME
  - Isb.params file 280
- JOB\_REQUEUE record
  - Isb.events 226
- JOB\_RUNLIMIT\_RATIO
  - Isb.params file 281
- JOB\_SCHEDULING\_INTERVAL
  - Isb.params file 282
- JOB\_SIGACT record
  - Isb.events 218
- JOB\_SIGNAL record
  - Isb.events 224
- JOB\_SPOOL\_DIR
  - Isb.params file
    - description 283
- JOB\_START record
  - Isb.events 212
- JOB\_START\_ACCEPT record
  - Isb.events 213
- JOB\_STARTER
  - Isb.applications file 182
  - Isb.queues file 330
- JOB\_STATUS record
  - Isb.events 213

- JOB\_SWITCH record
  - Isb.events 214
- JOB\_TERMINATE\_INTERVAL
  - Isb.params file 284
- JOB\_UNDERRUN
  - Isb.queues file 331
- JOB\_WARNING\_ACTION
  - Isb.queues file 331
- jobs
  - allowing preemption of 341
  - preempting by run time 303
- JOBSS
  - Isb.resources file Limit section 363
- JSDL
  - elim for 122
  - load indices 122
- K**
- Kerberos authentication
  - configuration 26
  - configuration of 27
  - description 22
    - eauth user name
      - configuration of 27
  - enabling 27
- Kerberos daemon authentication
  - enabling 27
  - non-Solaris 27
  - Solaris 27
- kernel-level job checkpoint and restart
  - description 99
- L**
- LIB\_RECVTIMEOUT
  - Isf.licensescheduler file Parameters section 547
- LIC\_COLLECTOR
  - Isf.licensescheduler file ServiceDomain section 552
- LIC\_SERVERS
  - Isf.licensescheduler file ServiceDomain section 552
- LICENSE
  - Isb.resources file Limit section 364
- lim.acct file 161
- LIMIT
  - Isf.licensescheduler file ProjectGroup section 568
- limit number of hosts 454
- Limit section
  - Isb.resources 359
- limits
  - enforced with overlapping members 273
  - job ID 290
- LM\_LICENSE\_FILE variable 606
- LM\_REMOVE\_INTERVAL
  - Isf.licensescheduler file Features section 565
  - Isf.licensescheduler file Parameters section 547
- LM\_STAT\_INTERVAL
  - Isf.licensescheduler file Parameters section 547
  - Isf.licensescheduler file ServiceDomain section 553
- LMSTAT\_PATH
  - Isf.licensescheduler file Parameters section 547
- load\_index
  - Isb.hosts file 244
  - Isb.queues file 332
- LOAD\_INDEX record
  - Isb.events 218
- LOCAL
  - Isb.users file 400
- local tasks in task files 586
- local user account mapping 7
- LOCAL\_MAX\_PREEXEC\_RETRY
  - Isb.applications file 182
  - Isb.params file 284
  - Isb.queues file 333
- LOCAL\_TO
  - Isf.licensescheduler file Features section 559
- LOCATION
  - Isf.cluster file 422
- log files
  - nios.log.host\_name 521
- ls
  - Isb.hosts file 244
  - Isb.queues file 332
- LS\_ADMIN
  - setup.config file 587
- LS\_DEBUG\_BLD
  - Isf.licensescheduler file Parameters section 548
- LS\_ENABLE\_MAX\_PREEMPT
  - Isf.licensescheduler file Parameters section 548
- LS\_EXEC\_T variable 606
- LS\_FEATURE\_PERCENTAGE
  - Isf.licensescheduler file Features section 561
- LS\_HOSTS
  - setup.config file 588
- LS\_JOBPID variable 607
- LS\_LICENSE\_FILE

setup.config file 588  
 LS\_LICENSE\_SERVER\_feature variable 607  
 LS\_LMSTAT\_PATH  
     setup.config file 589  
 LS\_LOG\_MASK  
     Isf.licensescheduler file Parameters section 549  
 LS\_MAX\_TASKMAN\_PREEMPTS  
     Isf.licensescheduler file Parameters section 550  
 LS\_MAX\_TASKMAN\_SESSIONS  
     Isf.licensescheduler file Parameters section 550  
 LS\_PREEMPT\_PEER  
     Isf.licensescheduler file Parameters section 550  
 LS\_SUBCWD variable 607  
 LS\_TOP  
     setup.config file 589  
 LSB\_API\_CONNTIMEOUT  
     Isf.conf file 431  
 LSB\_API\_RECVTIMEOUT  
     Isf.conf file 431  
 LSB\_API\_VERBOSE  
     Isf.conf file 431  
 LSB\_BJOBS\_CONSISTENT\_EXIT\_CODE  
     Isf.conf file 432  
 LSB\_BLOCK\_JOBINFO\_TIMEOUT  
     Isf.conf file 433  
 LSB\_BPEEK\_METHOD  
     Isf.conf file 434  
 LSB\_CHKPNT\_DIR variable 608  
 LSB\_CHUNK\_RUSAGE  
     Isf.conf file 434  
 LSB\_CMD\_LOG\_MASK  
     Isf.conf file 435  
 LSB\_CMD\_LOGDIR  
     Isf.conf file 436  
 LSB\_CONFDIR  
     Isf.conf file 436  
 LSB\_CPUSET\_BESTCPUS  
     Isf.conf file 436  
 LSB\_CRDIR  
     Isf.conf file 437  
 LSB\_DEBUG  
     Isf.conf file 437  
     variable 608  
 LSB\_DEBUG\_CMD  
     Isf.conf file 438  
     variable 608  
 LSB\_DEBUG\_MBD  
     Isf.conf file 439  
     variable 608  
 LSB\_DEBUG\_NQS  
     Isf.conf file 440  
     variable 608  
 LSB\_DEBUG\_SBD  
     Isf.conf file 441  
     variable 608  
 LSB\_DEBUG\_SCH  
     Isf.conf file 441  
     variable 609  
 LSB\_DEFAULT\_JOBGROUP variable 609  
 LSB\_DEFAULTPROJECT variable 610  
 LSB\_DEFAULTQUEUE variable 610  
 LSB\_DISABLE\_LIMLOCK\_EXCL  
     Isf.conf file 304, 442  
 LSB\_DISABLE\_RERUN\_POST\_EXEC  
     Isf.conf file 443  
 LSB\_DJOB\_COMMFAIL\_ACTION variable 623  
 LSB\_DJOB\_ENV\_SCRIPT variable 624  
 LSB\_ECHKPNT\_KEEP\_OUTPUT  
     Isf.conf file 443  
 LSB\_ECHKPNT\_KEEP\_OUTPUT variable 611  
 LSB\_ECHKPNT\_METHOD  
     Isf.conf file 443  
 LSB\_ECHKPNT\_METHOD variable 611  
 LSB\_ECHKPNT\_METHOD\_DIR  
     Isf.conf file 444  
 LSB\_ECHKPNT\_METHOD\_DIR variable 611  
 LSB\_ERESTART\_USRCMD variable 611  
 LSB\_ESUB\_METHOD  
     Isf.conf file 443, 445  
 LSB\_EXEC\_RUSAGE variable 612  
 LSB\_EXECHOSTS variable 612  
 LSB\_EXIT\_IF\_CWD\_NOTEXIST variable 613  
 LSB\_EXIT\_PRE\_ABORT variable 613  
 LSB\_EXIT\_REQUEUE variable 613  
 LSB\_FRAMES variable 614  
 LSB\_HCLOSE\_BY\_RES  
     LSF HPC extensions parameter 496  
 LSB\_HOSTS variable 614  
 LSB\_INTERACT\_MSG\_ENH  
     Isf.conf file 445  
 LSB\_INTERACT\_MSG\_INTVAL  
     Isf.conf file 446  
 LSB\_INTERACTIVE variable 615  
 LSB\_JOB\_CPULIMIT  
     Isf.conf file 447  
 LSB\_JOB\_INCLUDE\_POSTPROC variable 615

LSB\_JOB\_MEMLIMIT  
     Isf.conf file 448  
 LSB\_JOBEXIT\_INFO variable 616  
 LSB\_JOBEXIT\_STAT variable 616  
 LSB\_JOBFILENAME variable 617  
 LSB\_JOBGROUP variable 617  
 LSB\_JOBID variable 617  
 LSB\_JOBID\_DISP\_LENGTH  
     Isf.conf file 446  
 LSB\_JOBINDEX variable 618  
 LSB\_JOBINDEX\_STEP variable 618  
 LSB\_JOBNAME variable 619  
 LSB\_JOBPEND variable 620  
 LSB\_JOBPGIDS variable 620  
 LSB\_JOBPIIDS variable 620  
 LSB\_KEEP\_SYSDEF\_RLIMIT  
     Isf.conf file 450  
 LSB\_LIMLOCK\_EXCLUSIVE parameter 442  
 LSB\_LOAD\_TO\_SERVER\_HOSTS  
     Isf.conf file 450  
 LSB\_LOCALDIR  
     Isf.conf file 451  
 LSB\_MAILPROG  
     Isf.conf file 451  
 LSB\_MAILSERVER  
     Isf.conf file 452  
 LSB\_MAILSIZE variable 620  
 LSB\_MAILSIZE\_LIMIT  
     Isf.conf file 453  
 LSB\_MAILTO  
     Isf.conf file 453  
 LSB\_MAX\_ASKED\_HOSTS\_NUMBER  
     lsb.params 454  
 LSB\_MAX\_JOB\_DISPATCH\_PER\_SESSION  
     Isf.conf file 455  
 LSB\_MAX\_NQS\_QUEUES  
     Isf.conf file 456  
 LSB\_MAX\_PROBE\_SBD  
     Isf.conf file 455  
 LSB\_MBD\_BUSY\_MSG  
     Isf.conf file 457  
 LSB\_MBD\_CONNECT\_FAIL\_MSG  
     Isf.conf file 457  
 LSB\_MBD\_DOWN\_MSG  
     Isf.conf file 457  
 LSB\_MBD\_MAX\_SIG\_COUNT 458  
 LSB\_MBD\_PORT  
     Isf.conf file 458, 510  
 LSB\_MC\_CHKPNT\_RERUN  
     Isf.conf file 458  
 LSB\_MC\_INITFAIL\_MAIL  
     Isf.conf file 459  
 LSB\_MC\_INITFAIL\_RETRY  
     Isf.conf file 459  
 LSB\_MCPU\_HOSTS variable 621  
 LSB\_MEMLIMIT\_ENFORCE  
     Isf.conf file 459  
 LSB\_MIG2PEND  
     Isf.conf file 460  
 LSB\_MIXED\_PATH\_DELIMITER  
     Isf.conf 460  
 LSB\_MOD\_ALL\_JOBS  
     Isf.conf file 461  
 LSB\_NCPU\_ENFORCE  
     Isf.conf file 462  
 LSB\_NQS\_PORT  
     Isf.conf file 462  
 LSB\_NQS\_PORT variable 622  
 LSB\_NTRIES environment variable 291  
 LSB\_NTRIES variable 622  
 LSB\_NUM\_NIOS\_CALLBACK\_THREADS  
     Isf.conf file 463  
 LSB\_OLD\_JOBID variable 623  
 LSB\_OUTPUT\_TARGETFAILED variable 623  
 LSB\_PRE\_POST\_EXEC\_USER  
     Isf.sudoers file 580  
 LSB\_PSET\_BIND\_DEFAULT  
     Isf.conf file 463  
 LSB\_QUERY\_PORT  
     Isf.conf file 463  
 LSB\_QUEUE variable 625  
 LSB\_REMOTEINDEX variable 625  
 LSB\_REMOTEJID variable 625  
 LSB\_REQUEUE\_TO\_BOTTOM  
     Isf.conf file 465  
 LSB\_RESTART variable 625  
 LSB\_RESTART\_PGID variable 626  
 LSB\_RESTART\_PID variable 626  
 LSB\_RLA\_HOST\_LIST  
     Isf.conf file 465  
 LSB\_RLA\_PORT  
     Isf.conf file 465  
 LSB\_RLA\_UPDATE  
     Isf.conf file 466  
 LSB\_RLA\_WORKDIR  
     Isf.conf file 466

LSB\_RMS\_MAXNUMNODES 466  
 LSB\_RMS\_MAXNUMRAILS  
     Isf.conf file 467  
 LSB\_RMS\_MAXPTILE  
     Isf.conf file 467  
 LSB\_RMSACCT\_DELAY  
     Isf.conf file 466  
 LSB\_RTASK\_GONE\_ACTION variable 627  
 LSB\_SBD\_PORT  
     Isf.conf file 468, 510  
 LSB\_SET\_TMPDIR  
     Isf.conf file 468  
 LSB\_SHAREDIR  
     Isf.conf file 468  
 LSB\_SHORT\_HOSTLIST  
     Isf.conf file 469  
 LSB\_SIGSTOP  
     Isf.conf file 469  
 LSB\_SLURM\_BESTFIT  
     Isf.conf file 467  
 LSB\_STDOUT\_DIRECT  
     Isf.conf file 470  
 LSB\_STOP\_ASKING\_LICENSES\_TO\_LS  
     Isb.params 285  
 LSB\_STOP\_IGNORE\_IT  
     Isf.conf file 470  
 LSB\_SUB\_APP\_NAME variable 627  
 LSB\_SUB\_CLUSTER variable 628  
 LSB\_SUB\_COMMAND\_LINE variable 628  
 LSB\_SUB\_COMMANDNAME  
     Isf.conf file 470  
 LSB\_SUB\_EXTSCHED\_PARAM variable 628  
 LSB\_SUB\_JOB\_ACTION\_WARNING\_TIME variable 628  
 LSB\_SUB\_JOB\_WARNING\_ACTION variable 628  
 LSB\_SUB\_PARM\_FILE variable 629  
 LSB\_SUCCESS\_EXIT\_VALUES variable 629  
 LSB\_SUSP\_REASONS variable 629  
 LSB\_SUSP\_SUBREASONS variable 630  
 LSB\_SYNC\_HOST\_STAT\_LIM  
     Isb.params 285  
 LSB\_TIME\_CMD  
     Isf.conf file 471  
 LSB\_TIME\_MBD  
     Isf.conf file 471  
 LSB\_TIME\_RESERVE\_NUMJOBS  
     Isf.conf file 472  
 LSB\_TIME\_SBD  
     Isf.conf file 472  
 LSB\_TIME\_SCH  
     Isf.conf file 472  
 LSB\_UNIXGROUP  
     variable 631  
 LSB\_USER\_BIND\_CPU\_LIST  
     variable 631  
 LSB\_USER\_BIND\_JOB  
     variable 631  
 LSB\_UTMP  
     Isf.conf file 473  
 Isb.acct file 162  
 Isb.applications  
     JOB\_INCLUDE\_POSTPROC parameter 181  
     JOB\_POSTPROC\_TIMEOUT parameter 181  
     POST\_EXEC parameter 188  
     PRE\_EXEC parameter 189  
 Isb.applications file 173  
     description 171  
 Isb.events  
     event format errors 653  
 Isb.events file 205  
 Isb.hosts file  
     description 241  
     time-based configuration 256  
     user group administrator 396  
 Isb.modules file 257  
 Isb.params  
     JOB\_INCLUDE\_POSTPROC parameter 279  
     JOB\_POSTPROC\_TIMEOUT parameter 280  
     PREEMPT\_FOR parameter 303  
     PREEMPT\_JOBTYPE parameter 304  
 Isb.params file  
     description 262  
     SUB\_TRY\_INTERVAL parameter 291  
     time-based configuration 309  
 Isb.queues  
     POST\_EXEC parameter 338  
     PRE\_EXEC parameter 339  
 Isb.queues file  
     description 311  
     time-based configuration 357  
 Isb.resources file  
     description 359  
     time-based configuration 385  
 Isb.serviceclasses file 387  
 Isb.users file  
     description 395  
     time-based configuration 401

- LSF daemon startup control
  - configuring 33
  - description 29
    - EGO administrator login bypass
      - configuring 34
      - description 30
  - enabling 33
  - scope 32
    - startup by users other than root
      - configuration of 33
      - configuring 33
      - description 29
      - enabling 33
- LSF\_ADD\_CLIENTS
  - install.config file 154
- LSF\_ADD\_SERVERS
  - install.config file 153
- LSF\_ADMINS
  - install.config file 154
  - slave.config file 592
- LSF\_AFS\_CELLNAME
  - lsf.conf file 473
- LSF\_AM\_OPTIONS
  - lsf.conf file 474
- LSF\_API\_CONNTIMEOUT
  - lsf.conf file 474
- LSF\_API\_RECVTIMEOUT
  - lsf.conf file 475
- LSF\_ASPLUGIN
  - lsf.conf file 476
- LSF\_AUTH
  - lsf.conf file 475
- LSF\_AUTH parameter 475
- LSF\_AUTH\_DAEMONS
  - lsf.conf file 476
- LSF\_BIND\_JOB
  - lsf.conf file 173, 476
- LSF\_BINDIR
  - cshrc.lsf and profile.lsf files 139
  - lsf.conf file 476
- LSF\_BMPLUGIN
  - lsf.conf file 477
- LSF\_CLUSTER\_NAME
  - install.config file 155
- LSF\_CMD\_LOG\_MASK
  - lsf.conf file 478
- LSF\_CMD\_LOGDIR
  - lsf.conf file 477
- variable 631
- LSF\_CONF\_RETRY\_INT
  - lsf.conf file 479
- LSF\_CONF\_RETRY\_MAX
  - lsf.conf file 479
- LSF\_CONFDIR
  - lsf.conf file 480
- LSF\_CPUSETLIB
  - lsf.conf file 480
- LSF\_CRASH\_LOG
  - lsf.conf file 480
- LSF\_DAEMON\_WRAP
  - lsf.conf file 482
- LSF\_DAEMONS\_CPUS
  - lsb.params file 481
- LSF\_DAEMONS\_CPUS parameter in ego.conf 482
- LSF\_DEBUG\_CMD
  - lsf.conf file 482
- LSF\_DEBUG\_CMD variable 631
- LSF\_DEBUG\_LIM
  - lsf.conf file 483
- variable 631
- LSF\_DEBUG\_RES
  - lsf.conf file 485
- variable 631
- LSF\_DHCP\_ENV
  - lsf.conf file 485
- LSF\_DISABLE\_LSRUN
  - lsf.conf file 486
- LSF\_DISPATCHER\_LOGDIR
  - lsf.conf file 486
- LSF\_DUALSTACK\_PREFER\_IPV6
  - lsf.conf file 487
- LSF\_DYNAMIC\_HOST\_TIMEOUT
  - lsf.conf file 488
- LSF\_DYNAMIC\_HOST\_WAIT\_TIME
  - install.config file 156
  - lsf.conf file 488
- LSF\_EAUTH\_AUX\_DATA variable 632
- LSF\_EAUTH\_AUX\_PASS variable 632
- LSF\_EAUTH\_CLIENT variable 632
- LSF\_EAUTH\_KEY
  - lsf.sudoers file 580
- LSF\_EAUTH\_SERVER variable 632
- LSF\_EAUTH\_UID variable 633
- LSF\_EAUTH\_USER
  - lsf.sudoers file 581
- LSF\_EEXEC\_USER

|                                     |                                     |
|-------------------------------------|-------------------------------------|
| Isf.sudoers file 581                | Isf.conf file 500                   |
| LSF_EGO_ADMIN_PASSWD                | LSF_HPC_PJL_LOADENV_TIMEOUT         |
| Isf.sudoers file 581                | Isf.conf file 500                   |
| LSF_EGO_ADMIN_USER                  | LSF_ID_PORT                         |
| Isf.sudoers file 581                | Isf.conf file 501                   |
| LSF_EGO_DAEMON_CONTROL              | LSF_INCLUDEDIR                      |
| Isf.conf file 489                   | Isf.conf file 501                   |
| LSF_EGO_ENVDIR                      | LSF_INDEP                           |
| Isf.conf file 490                   | Isf.conf file 501                   |
| LSF_ELIM_BLOCKTIME                  | LSF_INTERACTIVE_STDERR              |
| Isf.cluster file 411                | Isf.conf file 502                   |
| LSF_ELIM_DEBUG                      | variable 633                        |
| Isf.cluster file 411                | LSF_INVOKE_CMD variable 633         |
| LSF_ELIM_RESTARTS                   | LSF_JOB_STARTER variable 634        |
| Isf.cluster file 412                | LSF_LD_LIBRARY_PATH variable 635    |
| LSF_ENABLE_CSA                      | LSF_LD_SECURITY                     |
| Isf.conf file 490                   | Isf.conf 503                        |
| LSF_ENABLE_DUALCORE                 | LSF_LIBDIR                          |
| Isf.conf file 492                   | cshrc.Isf and profile.Isf files 140 |
| LSF_ENABLE_EGO                      | Isf.conf file 504                   |
| Isf.conf file 492                   | LSF_LIC_SCHED_HOSTS                 |
| LSF_ENABLE_EXTSCHEDULER             | Isf.conf file 504                   |
| Isf.conf file 493                   | LSF_LIC_SCHED_PREEMPT_REQUEUE       |
| LSF_ENABLE_SUPPORT_IPV6             | Isf.conf file 504                   |
| Isf.conf 493                        | LSF_LIC_SCHED_PREEMPT_SLOT_RELEASE  |
| LSF_ENVDIR                          | Isf.conf file 505                   |
| cshrc.Isf and profile.Isf files 140 | LSF_LIC_SCHED_PREEMPT_STOP          |
| Isf.conf file 493                   | Isf.conf file 505                   |
| LSF_EVENT_PROGRAM                   | LSF_LIC_SCHED_STRICT_PROJECT_NAME   |
| Isf.conf file 494                   | Isf.conf file 506                   |
| LSF_EVENT_RECEIVER                  | LSF_LICENSE                         |
| Isf.conf file 494                   | install.config file 156             |
| LSF_EXECUTE_DOMAIN variable 633     | LSF_LICENSE_ACCT_PATH               |
| LSF_HOST_ADDR_RANGE                 | Isf.conf file 506                   |
| Isf.cluster file 412                | LSF_LICENSE_FILE                    |
| LSF_HOST_CACHE_NTTL                 | Isf.conf file 506                   |
| Isf.conf file 495                   | LSF_LICENSE_MAINTENANCE_INTERVAL    |
| LSF_HOST_CACHE_PTTL                 | Isf.conf file 507                   |
| Isf.conf file 495                   | LSF_LICENSE_NOTIFICATION_INTERVAL   |
| LSF_HPC_EXTENSIONS                  | Isf.conf file 508                   |
| Isf.conf file 496                   | LSF_LIM_API_NTRIES                  |
| LSF_HPC_NCPU_COND                   | Isf.conf file 509                   |
| Isf.conf file 499                   | variable 636                        |
| LSF_HPC_NCPU_INCR_CYCLES            | LSF_LIM_DEBUG                       |
| Isf.conf file 500                   | Isf.conf file 509                   |
| LSF_HPC_NCPU_INCREMENT              | variable 636                        |
| Isf.conf file 499                   | LSF_LIM_IGNORE_CHECKSUM             |
| LSF_HPC_NCPU_THRESHOLD              | Isf.conf file 510                   |

|                                        |                                              |                                               |
|----------------------------------------|----------------------------------------------|-----------------------------------------------|
| LSF_LIM_PORT                           | Isf.conf file 510<br>slave.config file 592   | Isf.conf file 522                             |
| LSF_LOAD_PLUGINS                       | Isf.sudoers file 582                         | LSF_NON_PRIVILEGED_PORTS<br>Isf.conf file 522 |
| LSF_LOAD_USER_PROFILE                  | Isf.conf 511                                 | LSF_PAM_APPL_CHKPNPNT 523<br>Isf.conf 523     |
| LSF_LOG_MASK                           | Isf.conf file 512, 513                       | LSF_PAM_CLEAN_JOB_DELAY<br>Isf.conf file 523  |
| LSF_LOGDIR                             | Isf.conf file 514, 515<br>variable 636       | LSF_PAM_HOSTLIST_USE<br>Isf.conf file 523     |
| LSF_LSLOGIN_SSH                        | Isf.conf file 516                            | LSF_PAM_PLUGINDIR<br>Isf.conf file 524        |
| LSF_MACHDEP                            | Isf.conf file 517                            | LSF_PAM_USE_ASH<br>Isf.conf file 524          |
| LSF_MANAGER product name               | Isf.cluster_name.license.acct file 426       | LSF_PIM_INFODIR<br>Isf.conf file 524          |
| LSF_MANDIR                             | Isf.conf file 517                            | LSF_PIM_SLEEPTIME<br>Isf.conf file 525        |
| LSF_MASTER variable 636                |                                              | LSF_PIM_SLEEPTIME_UPDATE<br>Isf.conf file 525 |
| LSF_MASTER_LIST                        | install.config file 157<br>Isf.conf file 518 | LSF_POE_TIMEOUT_BIND<br>Isf.conf file 526     |
| LSF_MASTER_NSLOOKUP_TIMEOUT            | Isf.conf file 519                            | LSF_POE_TIMEOUT_SELECT<br>Isf.conf file 526   |
| LSF_MAX_TRY_ADD_HOST                   | Isf.conf file 519                            | LSF_QUIET_INST<br>install.config file 157     |
| LSF_MC_NON_PRIVILEGED_PORTS            | Isf.conf file 519                            | LSF_RES_ACCT<br>Isf.conf file 526             |
| LSF_MISC                               | Isf.conf file 520                            | LSF_RES_ACCTDIR<br>Isf.conf file 527          |
| LSF_MONITOR_LICENSE_TOOL               | Isf.conf file 520                            | LSF_RES_ACTIVE_TIME<br>Isf.conf file 527      |
| LSF_MULTICLUSTER product name          | Isf.cluster_name.license.acct file 427       | LSF_RES_CLIENT_TIMEOUT<br>Isf.conf 528        |
| LSF_NIOS_DEBUG                         | Isf.conf file 520<br>variable 637            | LSF_RES_CONNECT_RETRY<br>Isf.conf file 528    |
| LSF_NIOS_DIE_CMD variable 637          |                                              | LSF_RES_DEBUG<br>Isf.conf file 528            |
| LSF_NIOS_IGNORE_SIGWINDOW variable 637 |                                              | LSF_RES_PORT<br>Isf.conf file 510             |
| LSF_NIOS_JOBSTATUS_INTERVAL            | Isf.conf file 521                            | LSF_RES_RLIMIT_UNLIM<br>Isf.conf file 529     |
| LSF_NIOS_MAX_TASKS                     | Isf.conf file 522                            | LSF_RES_TIMEOUT<br>Isf.conf file 530          |
| LSF_NIOS_PEND_TIMEOUT variable 637     |                                              | LSF_RESOURCES variable 638                    |
| LSF_NIOS_PORT_RANGE variable 638       |                                              | LSF_ROOT_REX<br>Isf.conf file 530             |
| LSF_NIOS_RES_HEARTBEAT                 |                                              | LSF_RSH<br>Isf.conf file 530                  |

LSF\_SECUREDIR  
     lsf.conf file 531  
 LSF\_SERVER\_HOSTS  
     lsf.conf file 531  
     slave.config file 593  
 LSF\_SERVERDIR  
     cshrc.lsf and profile.lsf files 141  
     lsf.conf file 532  
 LSF\_SHELL\_AT\_USERS  
     lsf.conf file 533  
 LSF\_SHIFT\_JIS\_INPUT  
     lsf.conf file 533  
 LSF\_SLURM\_DISABLE\_CLEANUP  
     lsf.conf file 533  
 LSF\_SLURM\_TMPDIR  
     lsf.conf file 534  
 LSF\_STARTUP\_PATH  
     lsf.sudoers file 582  
 LSF\_STARTUP\_USERS  
     lsf.sudoers file 582  
 LSF\_STRICT\_CHECKING  
     lsf.conf file 534  
 LSF\_STRICT\_RESREQ  
     lsf.conf file 535  
 LSF\_STRIP\_DOMAIN  
     lsf.conf file 535  
 LSF\_TARDIR  
     install.config file 158  
     slave.config file 593  
 LSF\_TIME\_CMD  
     lsf.conf file 536  
 LSF\_TIME\_LIM  
     lsf.conf file 536  
 LSF\_TIME\_RES  
     lsf.conf file 536  
 LSF\_TMPDIR  
     lsf.conf file 537  
 LSF\_TOP  
     install.config file 158  
     slave.config file 595  
 LSF\_TS\_LOGON\_TIME  
     variable 639  
 LSF\_ULDB\_DOMAIN  
     lsf.conf file 538  
 LSF\_UNIT\_FOR\_LIMITS  
     lsf.conf file 539  
 LSF\_USE\_HOSTEQUIV  
     lsf.conf file 540  
     variable 639  
 LSF\_USER\_DOMAIN  
     lsf.conf file 541  
     variable 640  
 LSF\_USER\_DOMAIN parameter 541  
 LSF\_VPLUGIN  
     lsf.conf file 541  
 lsf.cluster file 405  
 lsf.cluster\_name.license.acct file 426  
 lsf.conf  
     EGO\_DEFINE\_NCPUS 429  
     LSB\_LIMLOCK\_EXCLUSIVE parameter 442  
     LSB\_MBD\_MAX\_SIG\_COUNT 458  
     LSF\_AUTH parameter 475  
     LSF\_USER\_DOMAIN parameter 541  
 lsf.conf file 428  
     corresponding ego.conf parameters 428  
 lsf.licensescheduler file  
     time-based configuration 570  
 lsf.shared file 572  
 lsf.sudoers file 578  
 lsf.task file 584  
 lsf.task.cluster file 584

## M

mail  
     configuring on UNIX 452  
 MANDATORY\_EXTSCHED  
     lsb.queues file 333  
 MASTER\_INACTIVITY\_LIMIT  
     lsf.cluster file 415  
 MAX\_ACCT\_ARCHIVE\_FILE  
     lsb.params file 285  
 MAX\_CONCURRENT\_JOB\_QUERY  
     lsb.params file 286  
 MAX\_EVENT\_STREAM\_FILE\_NUMBER  
     lsb.params file 286  
 MAX\_EVENT\_STREAM\_SIZE  
     lsb.params file 287  
 MAX\_HOST\_IDLE\_TIME  
     bsla 391  
     lsb.serviceclasses file 391  
 MAX\_INFO\_DIRS  
     lsb.params file 287  
 MAX\_JOB\_ARRAY\_SIZE  
     lsb.params file 288  
 MAX\_JOB\_ATTACHEMENT\_SIZE

- lsb.params file 288
- MAX\_JOB\_MSG\_NUM
  - lsb.params file 289
- MAX\_JOB\_NUM
  - lsb.params file 289
- MAX\_JOB\_PREEMPT
  - lsb.applications file 183
  - lsb.params file 289
  - lsb.queues file 333
- MAX\_JOB\_REQUEUE
  - lsb.applications file 183
  - lsb.params file 290
  - lsb.queues file 334
- MAX\_JOBID
  - lsb.params file 290
- MAX\_JOBINFO\_QUERY\_PERIOD
  - lsb.params file 291
- MAX\_JOBS
  - lsb.users file 399
- MAX\_PEND\_JOBS
  - lsb.params file 291
  - lsb.users file 400
- MAX\_PREEXEC\_RETRY
  - lsb.applications file 183
  - lsb.params file 292
  - lsb.queues file 334
- MAX\_RSCHED\_TIME
  - lsb.queues file 334
- MAX\_SBD\_FAIL
  - lsb.params file 292
- MAX\_USER\_PRIORITY
  - lsb.params file 293
- maximum
  - job ID 290
- mbatchd
  - how to fix when busy 458
- MBD\_DIE record
  - lsb.events 217
- MBD\_EGO\_CONNECT\_TIMEOUT
  - lsb.params file 293
- MBD\_EGO\_READ\_TIMEOUT
  - lsb.params file 293
- MBD\_EGO\_TIME2LIVE
  - lsb.params file 294
- MBD\_QUERY\_CPUS
  - lsb.params file 294
- MBD\_REFRESH\_TIME
  - lsb.params file 295
- MBD\_SLEEP\_TIME
  - lsb.params file 296
- MBD\_START record
  - lsb.events 216
- MBD\_USE\_EGO\_MXJ
  - lsb.params file 296
- MC\_PENDING\_REASON\_PKG\_SIZE
  - lsb.params file 297
- MC\_PENDING\_REASON\_UPDATE\_INTERVAL
  - lsb.params file 297
- MC\_PLUGIN\_REMOTE\_RESOURCE
  - lsf.conf file 542
- MC\_RECLAIM\_DELAY
  - lsb.params file 297
- MC\_RUSAGE\_UPDATE\_INTERVAL
  - lsb.params file 298
- mem
  - lsb.hosts file 244
  - lsb.queues file 332
- MEM
  - lsb.resources file HostExport section 377
  - lsb.resources file Limit section 364
- MEMBER
  - lsb.hosts file 253
- MEMLIMIT
  - lsb.applications file 184, 185
  - lsb.queues file 335
  - per parallel task 497
  - per-job limit 448
- mesub
  - definition 72
- METHOD
  - lsb.resources file ReservationUsage section 384
- MIG
  - lsb.hosts file 243
  - lsb.queues file 186, 336
- MIG record
  - lsb.events 219
- migrated jobs
  - absolute job priority scheduling 97, 313
- MIN\_SWITCH\_PERIOD
  - lsb.params file 298
- mixed cluster
  - specifying paths 461
- model
  - lsf.cluster file 418
- MODELNAME
  - lsf.shared file 574

MXJ  
 Isb.hosts file 244

**N**

NAME  
 Isb.hosts file 252  
 Isb.resources file Limit section 365  
 Isb.resources file ResourceReservation section 381  
 Isb.resources file SharedResourceExport section 379  
 Isb.serviceclasses file 391  
 Isf.licensescheduler file Feature section 554  
 Isf.licensescheduler file ServiceDomain section 552

nd  
 Isf.cluster file 419

NEW\_JOB\_SCHED\_DELAY  
 Isb.queues file 337

NFS (Network File System) automount 643

NHOSTS  
 Isb.resources file HostExport section 377

NICE  
 Isb.queues file 337

NINSTANCES  
 Isb.resources file SharedResourceExport section 379

NIOS  
 standard message format 503

nios.log.host\_name 521

NO\_PREEMPT\_RUN\_TIME  
 Isb.applications file 187  
 Isb.params file 300

NON\_SHARED  
 Isf.licensescheduler file ProjectGroup section 568

NON\_SHARED\_DISTRIBUTION  
 Isf.licensescheduler file Feature section 562

non-uniform user name space  
 between-host user account mapping  
 description 7  
 cross-cluster user account mapping  
 description 12

NQS\_QUEUES  
 Isb.queues file 337

NQS\_QUEUES\_FLAGS  
 Isb.params file 300

NQS\_REQUESTS\_FLAGS  
 Isb.params file 301

**O**

OK license usage status  
 bld.license.acct file 135  
 Isf.cluster\_name.license.acct file 427

OS types  
 automatic detection 430

OVERUSE license usage status  
 bld.license.acct file 135  
 Isf.cluster\_name.license.acct file 427

OWNERSHIP  
 Isf.licensescheduler file ProjectGroup section 567

**P**

parallel jobs  
 optimizing preemption of 303  
 preemption of 59

PARALLEL\_SCHED\_BY\_SLOT 301

Parameters section  
 Isf.licensescheduler file  
 description 544

PATCH\_BACKUP\_DIR  
 install.config file 158

PATCH\_HISTORY\_DIR  
 install.config file 159

PEND\_REASON\_MAX\_JOBS 302

PEND\_REASON\_UPDATE\_INTERVAL 302

PER\_HOST  
 Isb.resources file HostExport section 376  
 Isb.resources file Limit section 366

PER\_PROJECT  
 Isb.resources file Limit section 367

PER\_QUEUE  
 Isb.resources file Limit section 367

PER\_USER  
 Isb.resources file Limit section 368

PERF\_HOST  
 install.config file 159

PERSISTENT\_HOST\_ORDER  
 Isb.applications 187

pg  
 Isb.hosts file 244  
 Isb.queues file 332

PG\_SUSP\_IT  
 Isb.params file 302

PJOB\_LIMIT  
 Isb.queues file 338

PMC\_HOST  
 install.config file 160

PORT  
 Isf.licensescheduler file Parameters section 550

POST\_EXEC

- lsb.applications file
  - bsub -Ep 188
- lsb.queues file
  - bsub -Ep 188
- POST\_EXEC parameter
  - lsb.applications 188
  - lsb.queues 338
- PRE\_EXEC
  - lsb.applications file 189
  - lsb.queues file 339
- PRE\_EXEC parameter
  - lsb.applications 189
  - lsb.queues 339
- PRE\_EXEC\_START record
  - lsb.events 233
- pre- and post-execution processing
  - application level
    - configuration of 41
    - enabling 41
    - POST\_EXEC parameter 188
    - PRE\_EXEC parameter 189
  - configuring 40
  - description 38
  - enabling 40
    - include post-processing in job finish status
      - configuration of 44
  - JOB\_INCLUDE\_POSTPROC parameter 181, 279
  - JOB\_POSTPROC\_TIMEOUT parameter 181, 280
  - post-processing timeout
    - configuration of 45
  - queue level
    - configuration of 40
    - enabling 40
    - POST\_EXEC parameter 338
    - PRE\_EXEC parameter 339
  - user account
    - configuration of 45
- pre-and post execution processing
  - scope 39
- pre-execution retry limit
  - application level
    - configuration of 46
    - enabling 46
  - cluster-wide
    - configuration of 46
    - enabling 46
  - queue level
    - configuration of 46
- enabling 46
- PREEMPT\_FINISH\_TIME
  - lsb.applications file 187
  - lsb.params file 300
- PREEMPT\_FOR
  - lsb.params file 303
- PREEMPT\_FOR parameter 303
- PREEMPT\_JOBTYPE
  - lsb.params file 304
- PREEMPT\_JOBTYPE parameter 304
- PREEMPT\_LSF
  - lsf.licensescheduler file Feature section 563
- PREEMPT\_RESERVE
  - lsf.licensescheduler file Feature section 563
- preemptable queue
  - defining 340
- preemptable queues
  - definition 50
- PREEMPTABLE\_RESOURCES
  - lsb.params file 304
- preempted jobs
  - control action 60
  - limit preemption retry 60
- preemption
  - jobs by run time 303
  - of parallel jobs 303
- PREEMPTION
  - lsb.queues file 340
- PREEMPTION\_WAIT\_TIME
  - lsb.params file 305
- preemption. *See* preemptive scheduling
- preemptive
  - scheduling
    - description 50
- preemptive queue
  - defining 340
- preemptive queues
  - definition 50
- preemptive scheduling
  - backfill jobs 304
  - configuration of 56
  - control action for preempted jobs 60
  - description 50
  - enabling 53, 340, 341
  - exclusive jobs 304
  - job slot limits 55
  - job slot usage 54
  - jobs by run time 303

- limit preemption retry 60
- limitations 51
- LSB\_LIMLOCK\_EXCLUSIVE parameter 442
- order of preemption 53
- parallel jobs 59
- per-host job slot limit for users and user groups 59, 303
- per-processor job slot limit for a user 59, 304
- per-processor job slot limit for user groups 59, 303
- PREEMPT\_FOR parameter 303
- PREEMPT\_JOBTYPE parameter 304
- total job slot limit for user groups 59, 303
- priority
  - queues 342
- PRIORITY
  - Isb.queues file 342
  - Isb.serviceclasses file 392
  - Isf.licensescheduler file ProjectGroup section 568
  - Isf.licensescheduler file Projects section 570
- privileged ports authentication
  - LSF\_AUTH parameter 475
- PROBE\_TIMEOUT
  - Isf.cluster file 415
- PROCESSLIMIT
  - Isb.applications file 190
  - Isb.queues file 343
- processors
  - setting cluster to 429
- PROCLIMIT
  - Isb.applications file 190
  - Isb.queues file 343
- PRODUCTS
  - Isf.cluster file 415
- profile.Isf file
  - description 137
  - setting the LSF environment 138
- ProjectGroup section
  - Isf.licensescheduler file
    - description 566
- PROJECTS
  - Isb.resources file Limit section 369
  - Isf.licensescheduler file Projects section 570
- Projects section
  - Isf.licensescheduler file
    - description 569

**Q**

- QJOB\_LIMIT
  - Isb.queues file 344
- QUEUE\_CTRL record
  - Isb.events 215
- QUEUE\_GROUP
  - Isb.queues file 344
- QUEUE\_NAME
  - Isb.applications file 186
  - Isb.queues file 344
- queues
  - making preemptable 341
  - making preemptive 341
  - preemptive and preemptable 50
  - setting priority of 342
- QUEUES
  - Isb.resources file Limit section 369

**R**

- r15m
  - Isb.hosts file 244
  - Isb.queues file 332
- r15s
  - Isb.hosts file 244
  - Isb.queues file 332
- r1m
  - Isb.hosts file 244
  - Isb.queues file 332
- RB\_PLUGIN
  - Isb.modules file 260
- RCVJOBS\_FROM
  - Isb.queues file 345
- RECV\_FROM
  - Isf.cluster file 424
- RELEASE
  - Isf.shared file 577
- REMOTE
  - Isb.users file 400
- remote task list 584
- remote tasks in task files 586
- REMOTE\_MAX\_PREEEXEC\_RETRY
  - Isb.applications file 191
  - Isb.params file 305
  - Isb.queues file 345
- REQUEUE\_EXIT\_VALUES
  - Isb.applications file 191
  - Isb.queues file 345
- RERUNNABLE
  - Isb.applications file 192
  - Isb.queues file 346

- RES\_REQ
  - Isb.applications file 193
  - Isb.queues file 347
- RES\_SELECT
  - Isb.resources file HostExport section 376
- ReservationUsage section
  - Isb.resources 383
- reserve
  - custom resources 384
- reserve resources 384
- RESERVE\_BY\_STARTTIME
  - LSF HPC extensions parameter 496
- RESOURCE
  - Isb.resources file Limit section 370
  - Isb.resources file ReservationUsage section 384
- RESOURCE\_RESERVE
  - Isb.queues file 347
- RESOURCE\_RESERVE\_PER\_SLOT
  - Isb.params file 306
- RESOURCE\_NAME
  - Isf.cluster file 423
  - Isf.shared file 575
- ResourceReservation section
  - Isb.resources 380
- RESOURCES
  - Isf.cluster file 419
- RESUME\_COND
  - Isb.queues file 349
- RETRY\_LIMIT
  - Isf.cluster file 416
- REXPRI
  - Isf.cluster file 420
- rollover
  - job IDs 290
- RTASK\_GONE\_ACTION
  - Isb.applications file 197
- RUN\_JOB\_FACTOR
  - Isb.params file 306
- RUN\_TIME\_FACTOR
  - Isb.params file 307
- RUN\_WINDOW
  - Isb.queues file 349
- RUNLIMIT
  - Isb.applications file 198
  - Isb.queues file 350
- RUNTIME
  - Isb.applications file 199
- RUNWINDOW

- Isf.cluster file 420

## S

- SBD\_SLEEP\_TIME
  - Isb.params file 307, 308
- SBD\_UNREPORTED\_STATUS record
  - Isb.events 229
- SCH\_DISABLE\_PHASES
  - Isb.modules file 260
- SCH\_PLUGIN
  - Isb.modules file 258
- scheduling
  - preemptive
    - description 50
  - schmod\_advrsv scheduler plugin 259
  - schmod\_aps scheduler plugin 259
  - schmod\_cpuset scheduler plugin 259
  - schmod\_default scheduler plugin 258
  - schmod\_fairshare scheduler plugin 258
  - schmod\_fcfs scheduler plugin 258
  - schmod\_jobweight scheduler plugin 259
  - schmod\_limit scheduler plugin 258
  - schmod\_mc scheduler plugin 259
  - schmod\_parallel scheduler plugin 258
  - schmod\_preemption scheduler plugin 259
  - schmod\_ps scheduler plugin 259
  - schmod\_pset scheduler plugin 259
  - schmod\_reserve scheduler plugin 259
- security
  - daemons
    - increasing 534
- sendmail program 452
- server
  - Isf.cluster file 421
- Servers
  - Isf.shared file 572
- service class
  - examples 393
- SERVICE\_DOMAINS
  - Isf.licensescheduler file Feature section 563
- ServiceDomain section
  - Isf.licensescheduler file
    - description 551
- setuid permissions 645
- setup.config file 587
- seven-digit job ID 290
- shared files 643

- SharedResourceExport section
  - Isb.resources 378
- SHARES
  - Isf.licensescheduler file ProjectGroup section 567
- SHORT\_EVENTFILE
  - LSF HPC extensions parameter 496
- SLA scheduling
  - service classes
    - examples 393
- SLA\_TIMER
  - Isb.params file 308
- slave.config file 590
- SLOT\_POOL
  - Isb.queues file 351
- SLOT\_RESERVE
  - Isb.queues file 351
- SLOT\_SHARE
  - Isb.queues file 352
- SLOTS
  - Isb.resources file HostExport section 378
  - Isb.resources file Limit section 371
- SLOTS\_PER\_PROCESSOR
  - Isb.resources file Limit section 372
- SNDJOBS\_TO
  - Isb.queues file 353
- SSH 83, 85
- STACKLIMIT
  - Isb.applications file 199
  - Isb.queues file 353
- STOP\_COND
  - Isb.queues file 353
- SUB\_TRY\_INTERVAL
  - Isb.params file 308
- SUB\_TRY\_INTERVAL parameter in Isb.params 291
- SUCCESS\_EXIT\_VALUES
  - Isb.applications file 200
- SUSPEND\_CONTROL
  - Isb.applications file 196, 200, 202
- SWAP
  - Isb.resources file HostExport section 378
- SWAPLIMIT
  - Isb.applications file 201
  - Isb.queues file 354
  - per parallel task 497
- swp
  - Isb.hosts file 244
  - Isb.queues file 332
- SWP
  - Isb.resources file Limit section 373
- SYSTEM\_MAPPING\_ACCOUNT
  - Isb.params file 309

## T

- task files
  - description 584
  - format 586
  - permissions 585
  - sections 586
- task lists
  - files 584
  - remote 584
  - viewing 585
- TASK\_MEMLIMIT
  - LSF HPC extensions parameter 497
- TASK\_SWAPLIMIT
  - LSF HPC extensions parameter 497
- TERMINATE\_WHEN
  - Isb.queues file 354
- THREADLIMIT
  - Isb.applications file 203
  - Isb.queues file 355
- threads
  - setting cluster to 429
- time windows
  - syntax 382
- TIME\_WINDOW
  - Isb.resources file ResourceReservation section 382
- time-based configuration
  - Isb.hosts 256
  - Isb.params 309
  - Isb.queues 357
  - Isb.resources 385
  - Isb.users 401
  - Isf.licensescheduler 570
- tmp
  - Isb.hosts file 244
  - Isb.queues file 332
- TMP
  - Isb.resources file Limit section 374
- troubleshoot
  - host groups 324
- troubleshooting
  - cluster performance 458
- type
  - Isf.cluster file 421

- TYPE
  - lsb.hosts file 254
  - lsb.resources file HostExport section 378
  - lsf.shared file 576
- TYPENAME
  - lsf.shared file 573
- U
  - UJOB\_LIMIT
    - lsb.queues file 355
  - ULDB (IRIX User Limits Database)
    - description 538
    - jlimit.in file 538
  - UNFULFILL record
    - lsb.events 217
  - UNIX/Windows user account mapping
    - configuring 65
    - description 62
    - enabling 65, 67
    - example 66
      - local machine name
        - enabling 66
    - LSF\_EXECUTE\_DOMAIN parameter 633
    - LSF\_USER\_DOMAIN parameter 541
      - multi-domain
        - enabling 66
    - scope 64
      - single domain
        - enabling 66
  - untrusted environments 534
  - USE\_SUSP\_SLOTS
    - lsb.params file 309
  - user account mapping
    - between-host
      - description 7
      - local user account mapping 9, 10
      - Windows workgroup 9
      - Windows workgroup account mapping 10
    - cross-cluster
      - configuring 13
      - description 12
      - enabling 13
      - system level 13, 14
      - user level 13, 15
    - local user account mapping 7
      - UNIX/Windows
        - configuring 65
  - description 62
  - enabling 65
  - example 66
  - Windows workgroups 7
  - user group administrator 396
  - user groups
    - external
      - configuring 130
      - defining 130
      - description 128
      - retrieving 132
    - hierarchical fairshare 397
  - user profiles
    - loading for a job 511
  - User section
    - lsb.users file 398
  - USER\_NAME
    - lsb.users file 399
  - USER\_SHARES
    - lsb.hosts file 251
    - lsb.users file 397
  - user-level job checkpoint and restart
    - description 100
  - UserGroup section
    - lsb.users file 395
  - UserMap section
    - lsb.users file 400
  - users
    - overlapping members 273
  - USERS
    - lsb.queues file 356
    - lsb.resources file Limit section 375
    - lsb.resources file ResourceReservation section 383
    - lsb.serviceclasses file 392
  - ut
    - lsb.hosts file 244
    - lsb.queues file 332
- V
  - variables. *See* environment variables
- W
  - windows
    - time 382
  - Windows
    - workgroup account mapping 7

Windows and UNIX

enable mixed paths 461

WORKLOAD\_DISTRIBUTION

Isf.licensescheduler file Feature section 563

X

XLSF\_APPDIR

Isf.conf file 542

XLSF\_UIDDIR

cshrc.Isf and profile.Isf files 141

Isf.conf file 543