

Rational. Rhapsody

IBM

IBM® Rational® Rhapsody® TestConductor Add On



User Guide

Rhapsody[®]

**IBM[®] Rational[®] Rhapsody[®]
TestConductor Add On**

User Guide

Release 2.4.5



License Agreement

No part of this publication may be reproduced, transmitted, stored in a retrieval system, nor translated into any human or computer language, in any form or by any means, electronic, mechanical, magnetic, optical, chemical, manual or otherwise, without the prior written permission of the copyright owner, BTC Embedded Systems AG.

The information in this publication is subject to change without notice, and BTC Embedded Systems AG assumes no responsibility for any errors which may appear herein. No warranties, either expressed or implied, are made regarding Rhapsody software and its fitness for any particular purpose.

Trademarks

IBM[®] Rational[®] Rhapsody[®], IBM[®] Rational[®] Rhapsody[®] Automatic Test Generation Add On, and IBM[®] Rational[®] Rhapsody[®] TestConductor Add On are registered trademarks of IBM Corporation.

All other product or company names mentioned herein may be trademarks or registered trademarks of their respective owners.

© Copyright 2000-2011 BTC Embedded Systems AG. All rights reserved.

Contents

Contents	6
Document Structure	8
Contacting IBM® Rational® Software Support	9
Conventions	10
Introduction	11
Rhapsody	
UML Testing Profile	15
Structure Overview	15
Functional Specification	19
Using the Testing Profile	30
Model-based	
Unit Test Definition	31
Automatic Test Architecture Generation	32
Test Case Definition	44
Test Execution	68
Overview	68
Test Configuration	68
Test Case Execution	74
Test Context Execution	86
Test Package Execution	89
Assertion based testing mode	92
Computing Model Coverage during Test Execution	104
Computing Code Coverage (only assertion based testing mode)	109
Computing Code Coverage, Memory Profiling, and Performance Profiling with Rational TestRealTime during Test Execution	111
Integration with CUnit/CppUnit Framework	118
Command Line Execution	124
Test Case Execution on Targets	126
Driving Operations Calls	127
Test Management	129
Managing Test Data	129
TestConductor Dialog	131

TestConductor Settings	132
Generating Test Reports with Rhapsody ReporterPLUS	143
Using the TestConductor API	150
Advanced Test Definition	154
Specifying Requirements with Sequence Diagrams	154
Advanced Sequence Diagram Test Definition	181
Black-Box Testing of External Files and Libraries	215
Using Serialize/Unserialize Functions for User Defined Types	220
Failure Analysis	223
Failure Reporting	224
Using TestConductor from Eclipse	241
Using TestConductor from Rational Quality Manager	243
Automatic Test Case Generation	244
Appendix	246
TestConductor Assert Macros (C/C++), TestConductor assert methods (Java), TestConductor assert functions (Ada).....	246
Syntax for Activation Conditions / Condition Marks	251
TestConductor Messages	253
Restrictions	255

Document Structure

This user guide is organized as follows:

- ◆ **Chapter 1, Introduction**, provides an introduction to IBM® Rational® Rhapsody® TestConductor Add On through a high-level overview of the main features.
- ◆ **Chapter 2, Rhapsody UML Testing Profile**, describes the defined stereotypes and new terms which can be used for the definition and management of tests.
- ◆ **Chapter 3, Model-based Unit Test Definition**, explains how to create Test Architectures and how to define test cases with sequence diagrams, statecharts, flow charts, or pure code.
- ◆ **Chapter 4, Test Execution**, explains how to build and execute a test configuration.
- ◆ **Chapter 5, Test Management**, guides you through the process of creating and editing the entire test suite.
- ◆ **Chapter 6, Upgrading old TestConductor Test Cases**, describes the process of upgrading of existing test definitions from older TestConductor versions.
- ◆ **Chapter 7, Advanced Test Definition**, describes the powerful features of sequence diagram test case definition like ordering, parameter mapping, activation conditions, etc.
- ◆ **Chapter 8, Failure Analysis**, explains how to analyze the source of a possible failure (after you have made design extensions and modifications).
- ◆ **Chapter 9, Automatic Test Generation**, explains the new features of Rhapsody Automatic Test Generation (ATG) and the integration of test cases into the model.

Contacting IBM® Rational® Software Support

IBM Rational Software Support provides you with technical assistance. The IBM Rational Software Support Home page for Rational products can be found at <http://www.ibm.com/software/rational/support/>.

For contact information and guidelines or reference materials that you need for support, read the [IBM Software Support Handbook](#).

For Rational software product news, events, and other information, visit the [IBM Rational Software Web site](#).

Voice support is available to all current contract holders by dialing a telephone number in your country (where available). For specific country phone numbers, go to <http://www.ibm.com/planetwide>.

Before you contact IBM Rational Software Support, gather the background information that you will need to describe your problem. When describing a problem to an IBM software support specialist, be as specific as possible and include all relevant background information so that the specialist can help you solve the problem efficiently. To save time, know the answers to these questions:

What software versions were you running when the problem occurred?

Do you have logs, traces, or messages that are related to the problem?

Can you reproduce the problem? If so, what steps do you take to reproduce it?

Is there a workaround for the problem? If so, be prepared to describe the workaround.


Conventions

The following table lists the conventions used in the Rhapsody documentation.

Style	Description
command1 > command2	The greater-than (>) symbol leads you through the steps in a menu or key sequence. For example, Add New > Package means that you should first select Add New , then select Package from the Add New submenu.
Bold type	Bold type indicates items that you should select, such as buttons or checkboxes in dialog boxes. For example: Click Apply
<i>Italic type</i>	<i>Italic type</i> is used for emphasis, titles of referenced documents and new terms.
Courier type	Courier type is used for file names and directory paths, user input, and code-related items such as instance names and properties.
<filename>	Angle brackets surround variable names that you should replace with actual names. For example, you should replace <filename> with the actual name of a file.

Introduction

Welcome to the User Guide for IBM® Rational® Rhapsody® TestConductor Add On. TestConductor is part of the Rhapsody Testing Environment which is based on three main components: “Automatic Test Architecture Generation”, “Automatic Test Case Execution” and “Automatic Test Case Generation”. These three components are developed along the UML Testing Profile as implemented in Rhapsody.



TestConductor supports the two main features “Automatic Test Architecture Generation” and “Automatic Test Case Execution” of the Rhapsody Testing Environment. The optional IBM® Rational® Rhapsody® Automatic Test Generation Add On (ATG) supports the feature “Automatic Test Case Generation”.

In the Rhapsody Testing Environment the implementation of test cases can be chosen out of:

- ◆ Sequence diagrams
- ◆ Statecharts (only Rhapsody in C/C++/Java/Ada)
- ◆ Flow charts (only Rhapsody in C/C++)
- ◆ Pure code (only Rhapsody in C/C++/Java/Ada)

The Rhapsody Testing Environment provides the ability to test a design against its requirements. Advantages of using sequence diagrams as test cases are:

- ◆ Graphical definition
- ◆ Monitors/drivers
- ◆ Parameterized sequence diagrams
- ◆ Color-coded failure sequence diagrams

TestConductor is a model based testing environment used to debug and test object-oriented embedded software designed in Rhapsody. TestConductor supports unit testing as well as software integration testing based on graphical test definitions using sequence diagrams. In Rhapsody in C++, Rhapsody in C, Rhapsody in Java, and Rhapsody in Ada test cases can be defined also by statecharts, flow charts (only C/C++), or pure code. Using sequence diagram related test cases, TestConductor supports an advanced graphical failure analysis. These features make it easy to define and execute extensive test suites, as well as to create complex tests drivers and test monitors. TestConductor supports


Rhapsody in C++, Rhapsody in C, Rhapsody in Java and Rhapsody in Ada. Limitations regarding the different languages can be found in the chapter Restrictions.

Rhapsody UML Testing Profile

The Rhapsody UML Testing Profile contains new terms and stereotypes that can be used to model test artifacts in Rhapsody. It is based on the official UML Testing Profile. However, several elements defined in the UML Testing Profile are currently not part of the Rhapsody Testing Profile, while the Rhapsody Testing Profile contains additional elements that are not part of the UML Testing Profile. These additional elements are used for test activities that are not addressed by the UML Testing Profile, for instance stubbing.

Automatic Test Architecture Generation

The *automatic test architecture generation* - first supporting layer of the Rhapsody Testing Environment and part of TestConductor – automates the complex task of creating the test environment for e.g. arbitrary classes of the UML design.



From the Rhapsody project the user easily initiates the automatic generation of a test architecture including:

- ◆ Creation of a new test package
- ◆ Creation of a new test context including
 1. System under test (“SUT”)
 2. Test components
 3. Links between SUT and test components

Test Case Definition

A *test case* represents the smallest element that can be defined and executed by TestConductor. A test case describes a sequence of input stimuli and expected behavior, in order to verify a certain functional behavior of a system under test. Test cases can define both, black box and white box behavior.

TestConductor supports several ways to define test cases:

- ◆ Sequence diagrams

- ◆ Statecharts (only Rhapsody in C/C++/Java)
- ◆ Flow charts (only Rhapsody in C/C++)
- ◆ Pure code (only Rhapsody in C/C++)

With the optional add-on Rhapsody® Automatic Test Generation (ATG™) for Rhapsody in C++ test cases can be generated automatically.

Test Case Execution

TestConductor is a *test case execution engine* and represents the second stage of the Rhapsody Testing Environment. It enhances the testing capabilities by not only executing the automatically generated test architecture, but it also offers a test execution analysis with respect to the expected results. If the test case e.g. is implemented by a sequence diagram the expected behavior is expressed by

- ◆ The ordering of defined messages
- ◆ Parameter values of messages
- ◆ Messages from SUT to testing components
- ◆ Specified return values on operation calls

Using TestConductor

This manual assumes that Rhapsody and TestConductor are already installed on your system, and that you have a valid license. If you need assistance with installation or licensing, contact customer support.

To execute tests, TestConductor relies on the compiled and linked model code of the test architecture. Therefore, the project with the system under test must be in a state such that you can compile and run the test architecture, just as you must do to use the interactive simulation capabilities of Rhapsody. If you are using TestConductor with testing mode “AnimationBased” (property TestConductor.Settings.TestingMode), you must compile the code of at least the test components with animation instrumentation.

Note: For Rhapsody in Ada, make sure that you rebuild Rhapsody’s framework before using TestConductor. To rebuild the framework, select “Build framework” from Rhapsody’s code menu (after opening an Ada model). You only have to rebuild the framework once.

Note: If you are using TestConductor with testing mode “AnimationBased” (property TestConductor.Settings.TestingMode), make sure that you have compiled and linked an executable component with animation instrumentation.

Note: If you are using TestConductor with testing mode “AnimationBased” (property TestConductor.Settings.TestingMode), make sure that the properties `CG::Operation::Animate`, `CG::Operation::AnimateArguments`, `CG::Event::Animate`, and `CG::Event::AnimateArguments` of those messages used for test execution based on sequence diagrams are switched on.

Otherwise they are not animated and cannot be tested with TestConductor. Ensure this for the properties of these relevant messages, and also for their parent class and package properties.

This guide uses sequence diagrams that are included (or have to be additionally created) in the CashRegister sample. The chapter *Advanced Test Definition* uses sequence diagrams from the PBX sample. Both samples do not provide step-by-step information.

Rhapsody UML Testing Profile


The *Rhapsody UML Testing Profile* is based on the official UML Testing Profile. It contains new terms and stereotypes that can be utilized for model testing artifacts in Rhapsody. A couple of elements defined in the UML Testing Profile are presently not part of the Rhapsody Testing Profile. However, the Rhapsody Testing Profile includes supplementary elements that are not part of the UML Testing Profile. Stubbing, for example, is one of these additional elements that are used for test activities not addressed by the UML Testing Profile.

For further information on the Rhapsody UML Testing Profile please refer to the *TestConductor Tutorial*, where depict examples on the Rhapsody Testing Profile are provided. Hence, it is recommended to utilize the TestConductor Tutorial for training purposes prior to going into further detail in this document.


Structure Overview

The Rhapsody Testing Profile is prearranged in three major packages with additional sub-packages and the *TestingProfile* stereotype.


- ◆ Rhapsody UML Testing Profile (UML20TP)
 1. *TestArchitecture*
 2. *TestBehavior*



- ◆ Rhapsody TestConductor (RTC)
 1. *TestArchitecture*
 2. *TestBehavior*




◆ Automatic Test Generation (ATG)



Adding the Testing Profile automatically


The first usage of any TestConductor functionality automatically adds the Rhapsody Testing Profile to a model. For example this can be done by choosing the Rhapsody menu entry **Tools > TestConductor**.

In case the model does not yet contain the actual Rhapsody Testing Profile, TestConductor can add the missing Rhapsody Testing Profile automatically.



Select **Yes** to add the Rhapsody Testing Profile to the model. Select **No** to abort this process.

In case the Rhapsody Testing Profile is unloaded, TestConductor ask to load it.




Select **Yes** to load the Rhapsody Testing Profile to the model. Select **No** to abort this process.

In case a loaded profile already uses the name "TestingProfile" Rhapsody TestConductor advises the user.



Select **OK**. After removing the existing profile with name TestingProfile from the model redo the action to start Rhapsody TestConductor.


Once the Rhapsody Testing Profile has been loaded into a Rhapsody project by starting TestConductor the Rhapsody browser window will contain the above stated testing profile packages and its individual sub-packages as shown in the following picture.



Adding the Testing Profile manually

It is also possible to add the testing profile manually to a model:

- ◆ Open your project in Rhapsody
- ◆ Select the menu item **File > Add to Model...**
- ◆ Select the following **Data Type**: 'Package (*.sbs)'
- ◆ Tick the radio button **As Reference**



- ◆ Select in Rhapsody installation folder:
`'...\Share\Profiles\TestingProfile\TestingProfile_rpy\TestingProfile.sbs'`
- ◆ Press **Open** to install the Rhapsody Testing Profile

Functional Specification


The *functional specification* of the Rhapsody Testing Profile shall be explained by means of its structure stated in the previous chapter *Structural Overview*.

UML Testing Profile (UML20TP) Package

The UML20TP package contains stereotypes and new terms derived from the official UML Testing Profile. It consists of two major packages:

- ◆ *TestArchitecture* and
- ◆ *TestBehavior*

as shown in below picture.



TestArchitecture Package

The *TestArchitecture* package consists of the stereotypes

- ◆ *SUT*
- ◆ *TestComponent*
- ◆ *TestConfiguration*
- ◆ *TestContext*

The *system under test (SUT)* is the component being tested. A SUT can consist of several objects. The SUT is exercised via its public interface operations and events by the test components, the test context or the system environment (ENV).

A *test component (TestComponent)* is a class of a test system. The *test component objects (TestComponentInstances)* realizes partially the behavior of a test case. An instance of a test component may have a set of interfaces which are used to communicate via connections with other test component instances or with SUT objects. It also may have primitive operations, so called *driver operations (DriverOperations)* that can drive SUT operations or call events of the SUT and so called *stub operations (StubOperations)* which are able to generate necessary “stub” return values.

The *test configuration (TestConfiguration)* is a dependency to a code generation configuration. Depending on this configuration the code for the complete test context including its test cases can be generated, built and executed.

A *test context (TestContext)* describes the context in which test cases are executed. A test context is responsible for defining the structure of the test system, i.e., which test component objects and which SUT objects exists and how they are interconnected. The test component instances and SUT objects are normally parts of a test context. Since test cases are operations of a test context, a test case can access both the test component instances and also the SUT objects.

TestBehavior Package

The *TestBehavior* package contains two stereotypes named


- ◆ *TestCase*
- ◆ *TestObjective*

A *test case* (*TestCase*) is a specification of one case to test the system under test including what to test. It defines the input stimuli and the expected results to be observed. It implements a test objective. A test case is an operation of a test context (described above).

A *test objective* (*TestObjective*) is a named element describing what should be tested. It is associated to a test case.

TestConductor (RTC) Package

The RTC package consists of three major packages: *TestArchitecture*, *TestBehavior* and *TestDocumentation* as shown in below picture.



TestArchitecture Package

The *TestArchitecture* package contains the stereotypes:

- ◆ Subpackage *CppUnit*
 - *CppUnitConfig*
 - *CppUnitContext*
- ◆ Subpackage *CUnit*
 - *CUnitConfig*
 - *CUnitContext*
- ◆ Subpackage *Diagrams*
 - *TestContextDiagram*
- ◆ Subpackage *TestRT*
 - *TestRealTime*
 - *TestRealTimeFile*
 - *TestRealTimeResult*
- ◆ *Arbiter*
- ◆ *ArbiterInstance*
- ◆ *ControlArbiter*
- ◆ *instantiated*
- ◆ *NoConsoleApp*
- ◆ *ParameterTable*
- ◆ *replacement*
- ◆ *scheduled*
- ◆ *Scheduler*
- ◆ *SCTCInstance*
- ◆ *stubbed*
- ◆ *TestActor*
- ◆ *TestComponentInstance*
- ◆ *TestingConfiguration*
- ◆ *TestPackage*
- ◆ *TestParameter*
- ◆ *use_ParameterTable*
- ◆ *use_replacement*

Subpackages *CppUnit* and *CUnit* contain stereotypes for the integration of CppUnit and CUnit testing with Rhapsody.


Stereotype *CppUnitContext* can be applied to a class and sets some properties for CppUnit testing integration. You can change a test context to CppUnitContext – and vice versa - by right-clicking a test context and selecting “Change to > CppUnitContext”.

Stereotype *CppUnitConfig* can be applied to a configuration and provides a set of tags for customization of the CppUnit testing integration with Rhapsody.

Stereotype *CUnitContext* can be applied to a class and sets some properties for CUnit testing integration. You can change a test context to CUnitContext – and vice versa - by right-clicking a test context and selecting “Change to > CUnitContext”.


Stereotype *CUnitConfig* can be applied to a configuration and provides a set of tags for customization of the CUnit testing integration with Rhapsody.

Subpackage *diagrams*: A *test context diagram* (*TestContextDiagram*) is a structure diagram that contains the SUT instances, the test component instances and their interconnections. It is used to define the structure of the test context graphically.



The test context diagram is being generated during the test architecture generation inside the test context. It is a structure diagram stereotyped with *TestContextDiagram*.

Subpackage TestRT contains stereotypes used for the integration of IBM Rational Test RealTime. (for details see section Computing Code Coverage, Memory Profiling, and Performance Profiling with Rational TestRealTime during Test Execution on page 110 pp.)



Stereotype *TestRealTime* can be applied on configurations and provides a set of tags that can be used to control the kind of instrumentation that shall be performed on that configuration when using the tool “Rational TestRealTime” together with TestConductor. See also section [Rational TestRealTime](#).

Stereotype *TestRealTimeFile* is used to denote TestRealTime data files that are added to the model by TestConductor. This data files are needed in order to have all TestRealTime results maintained as part of the model.

Stereotype *TestRealTimeResult* denotes the result data that is added by TestConductor to the model after a TestCase execution or a TestContext execution of a configuration that with stereotype *TestRealTime*.

The *TestRT* package contains the types:

- ◆ *RTRT_CoverageBlockDefinition_Type*
- ◆ *RTRT_CoverageCondition_Type*
- ◆ *RTRT_CoverageProc_Type*
- ◆ *RTRT_Target_Type*

These four types are used for the integration between TestConductor and TestRealTime. Users do not have to care about the precise definition of these types.

Stereotype *instantiated* is used to label associations that are always instantiated with a valid link during runtime. TestConductor interprets associations labelled with this stereotype like links.

Stereotype *Arbiter* is used by TestConductor for auto generated test components that control the execution of a SD test case.

Stereotype *ArbiterInstance* is used by TestConductor for test component instances that are instances of Arbiter test components.

Stereotype *ControlArbiter* is used by TestConductor to mark a dependency from a SD test case to a Arbiter test component that controls the SD test case.

Stereotype *instantiated* is used to label associations that are always instantiated with a valid link during runtime. TestConductor interprets associations labelled with this stereotype like links.

Stereotype *NoConsoleApp* can be applied to configurations in order to suppress opening a console when running the application.

Stereotype *ParameterTable* is used to mark a controlled file as a parameter table definition that contains values for all external test parameters of a test context.

Stereotype *replacement* is used to mark a dependency from a test component to the original class that is replaced by the test component in the test architecture.

Stereotype *scheduled* is used to mark a dependency from a test context to a *Scheduler* test component that controls the starting and stopping of test cases of the test context.

Stereotype *Scheduler* is used to mark an auto generated test component that is used to control the activation and termination of test cases.

Stereotype *SCTCInstance* is used to mark a test component instance to be an instance of a statechart test case test component.

Stereotype *stubbed* is used to mark an operation of a test component to be stubbed, i.e., that the behavior of the operation has been changed for testing purposes.

New term *TestActor* is used for test components that have the role of an actor in the test architecture. Test actors replace actors for testing purposes.

New term *TestComponentInstance* is used to specify instances of test components.

Stereotype *TestingConfiguration* is used to mark a configuration that is used for testing purposes. The stereotype *TestingConfiguration* provides several tags that can be used in order to define specific settings for the generated testing code.

New term *TestPackage* represents a package that contains testing related model elements, e.g. other test packages, test contexts or test cases. It allows grouping of multiple test related elements into one package, and it can be used to separate testing related elements from design related elements.

Stereotype *TestParameter* is used to mark an attribute of a test context to be a parameter that can be controlled by a testing configuration by using a parameter table.

Stereotype *use_ParameterTable* is used to mark a dependency from a testing configuration to a parameter table in order to specify that the testing configuration shall apply the linked parameter table for the test parameters of the test context for which the testing configuration generates code for.

Stereotype *use_replacement* is used to mark a dependency from a test component instance to a test component that is a replacement of a design class for testing purposes.

TestBehavior Package

The *TestBehavior* package is composed of a number of stereotypes like:

- ◆ *CoverageResult*
- ◆ *DefaultOperation*
- ◆ *DriverOperation*
- ◆ *RTC_InstInfo*
- ◆ *RTC_MsgInfo*
- ◆ *RTC_RefInfo*
- ◆ *SDInstance*
- ◆ *StatechartTestCase*
- ◆ *StubbedOperation*
- ◆ *StubOperation*

- ◆ *TestAction*
- ◆ *TestResult*
- ◆ *TestScenario*
- ◆ *Unrealized*

A *CoverageResult* is a document that reports which model elements are covered by one or more TestCases.

A *default operation (DefaultOperation)* defines the default behavior of an operation of a test component. A test case in which the behavior of this operation is not explicitly specified uses this default behavior in the current test case execution.

A *driver operation (DriverOperation)* is an operation of a test component which is able to inject input stimuli to the SUT objects. It is generated automatically by TestConductor for the test component class that calls a message of a SUT object defined in a sequence diagram. During execution of the test case, TestConductor calls the driver operation, and as a result the test component stimulates the SUT as it is described in the used sequence diagram.

The stereotype *RTC_InstInfo* contains two tags *RTC_IgnoreSCBehavior* and *RTC_Monitor*. When adding this stereotype to an instance line of a test scenario, the user can set these tags. TestConductor uses these tags when executing the test. If the tag *RTC_IgnoreSCBehavior* is set, TestConductor ignores the normal state chart behavior of the tagged instance. If the tag *RTC_Monitor* is set, TestConductor just monitors all messages starting from the tagged instance.

The stereotype *RTC_MsgInfo* contains tags *RTC_Monitor*, *RTC_Receiver*, etc. When adding this stereotype to a message in a test scenario, the user can set these tags. If the tag *RTC_Monitor* is set, the tagged message is just monitored by TestConductor. If the tag *RTC_Receiver* is set, the tagged value is used as the real receiver instance of the tagged message. If the tag *RTC_DriverCallCode* is set, TestConductor generates the string contained in this tag instead of the standard call code TestConductor generates for driver operations. If the tag *RTC_InitCode* is set, TestConductor generates the string contained in this tag instead of the standard init code TestConductor generates for driver operations. If the tag *RTC_MsgId* is set, the specified string is used to reference the message in macros *RTC_ASSERT_SD_NAME*. If the tag *RTC_StubBodyCode* is used, TestConductor generates the string contained in this tag instead of the standard stub code TestConductor generates for stub operations. For further information please read the chapter User Defined Driving Operation Calls (for Rhapsody in C/C++/Java/Ada) at page 204.

The stereotype *RTC_RefInfo* is used internally for unique identification of messages in sequence diagrams which are referenced by other sequence diagrams.

A *sequence diagram instance (SDInstance)* represents one instance of a test scenario. When using a sequence diagram for testing purposes, several parameters must be defined that influence the behavior of a test case. A combination of a sequence diagram with such a set of parameters forms a sequence diagram instance.

Stereotype *StatechartTestCase* is used to stereotype the dependency of a statechart test case on the test component owning the statechart defining the test.

A *stubbed operation (StubbedOperation)* is an operation for which at least one test case specifies a behavior that is different from the default behavior. The different behavior is stored in a stub-operation. The stubbed operation decides at runtime depending on the

executed test case if either the default behavior should be executed or a specific stub-operation.

A *stub operation* (*StubOperation*) is a replacement of an operation of a test component class. It realizes the code for an operation call return value specified in the referenced sequence diagram. The code of the stub operation is generated automatically by TestConductor.

A *test action* (*TestAction*) is an action block that can be placed on life lines in TestScenarios. There are different kinds of test actions: <InitAction>, <PreCallAction>, <CallAction>, <PostCallAction>, <StubAction>. Inside these actions, one can place e.g. assertions to perform complex checks on output values (return or out arguments), or one can write code that initializes complex input data.

A *test result* (*TestResult*) represents an outcome of an execution of a test case. It is a textual report that contains detailed information about the test case execution, e.g. if the test case has passed or failed.

The stereotype *TestScenario* (*test scenario*) contains two tags *RTC_ActivationCondition* and *RTC_SDPParameters*. When adding this stereotype to a test scenario, the user can set these tags. With the tag *RTC_ActivationCondition* the user can specify the activation condition of the sequence diagram. With the tag *RTC_SDPParameters* the user can set the parameters of the sequence diagram.

Messages with stereotype *Unrealized* are filtered out and ignored during test execution. See also section [Ignoring Unrealized Messages](#).


TestDocumentation Package

The *TestDocumentation* package contains a Matrix-Layout *TestRequirementCoverage* and a Table-Layout *TestResultTable* in order to present test information in matrix and table notation.


The layouts are used to define two stereotypes:

- ◆ *TestRequirementMatrix*
- ◆ *TestResultTable*

A *TestRequirementMatrix* shows in an array view if and how requirements are tested by test cases. The left hand side of the array shows all existing test cases. The upper side shows all the requirements. The cells contain an entry if a TestObjective from the test case to the requirement exists in the model, for instance from test case *Code_tc_0* to requirement *REQ1*.



A *TestResultTable* shows in a table form the existing test cases and their current result values. The left column of the table shows all existing test cases. The right column shows the current test case results, for instance verdict *Passed* for test case *Code_tc_0*.



The screenshot shows a software testing tool interface. On the left is a tree view under 'TestCases' containing five entries: 'Code_tc_0()', 'Code_tc_1()', 'Code_tc_2()', 'Code_tc_3()', and 'Code_tc_0()'. On the right is a table with two columns: 'Name' and 'Verdict'.

Name	Verdict
TCon_CashRegister__Code_tc_0_0.html	Passed
TCon_CashRegister__Code_tc_1_0.html	Failed
TCon_CashRegister__Code_tc_2_0.html	Passed
TCon_CashRegister__Code_tc_3_0.html	Failed
TCon_CashRegister_0.html	Failed


Automatic Test Generation (ATG) Package

The *ATG package* consists of several stereotypes which are enhancements to the UML Testing Profile. Using these stereotypes in the model means that the optional add-on Rhapsody Automatic Test Generation (ATG) is able to interpret defined input/output interface information and constraints for setting of a test generation configuration.

Mainly two constrained stereotypes are: *argRangeConstraint* and *argValueConstraint*. *argRangeConstraint* can be used to define value range constraints. *argValueConstraint* can be utilized to define single value constraints of enumerations constraints. These constraints can be used on operation or event arguments.

Made available are also the interface stereotypes *providedInterface* and *requiredInterface*. Those stereotypes help to remove from the ATG view those classes which are not used as interface classes.

Furthermore, the ATG package contains a number of type constraint stereotypes that can be used to define range or value constraints on type definitions. Exemplarily a cutting of the ATG package is displayed in following figure.



For more information about the ATG package and its stereotypes please refer also the *Rhapsody Automatic Test Generation (ATG) User Guide*.

Using the Testing Profile

The Rhapsody Testing Profile is automatically utilized by Rhapsody TestConductor. The functionalities of the toolset are explained in the subsequent chapters of this user guide.

Model-based Unit Test Definition

The term *unit test* is often used within the software development, but interpreted quite different. Unit tests are performed on differently large software units like simple functions, simple classes up to complex function libraries. However, the goal of each unit test is in most cases the same. On the one hand the unit is tested for its functional behavior. On the other hand often additionally structural analyses are accomplished, in order to find uncovered (dead) code.

In order to prepare, execute, and assess a unit test several steps are usually performed:

1. A test architecture (or test harness or test frame) must be constructed
2. Test cases must be defined and implemented
3. Test cases must be executed on the host machine
4. Test cases must be executed on the target machine


Each of the four mentioned steps is usually time consuming and difficult to perform. TestConductor makes the preparation, execution, and the assessment of tests much easier by lifting the test process up to the level of UML models, and by offering a high degree of automation for the steps listed above.

TestConductor supports unit testing on model-level by following the UML Testing Profile. Therefore TestConductor automates the time consuming and complex task of test environment creation. The automatic test architecture generation can be used for:

- ◆ Simple classes (In SysML: Activities, blocks, Viewpoint)
- ◆ Simple classes with inheritance
- ◆ Composite classes
- ◆ Composite classes with inheritance
- ◆ Objects (In SysML: Parts)
- ◆ Files (Modules)

The other complex task of unit testing is the definition of test case or test scenarios, typically done by writing test code in the same language than the unit to be tested. Model-based unit testing with TestConductor combines the advantage of graphical test case definition via sequence diagrams or flow charts with the familiar pure code based test cases. Using the optional add-on Rhapsody Automatic Test Generation (ATG), you have also the possibility to perform automatic test case generation.

The next chapters use the CashRegister model known from the *Rhapsody “Essential” Tool Training*. The unit test will be done on the CashRegister class.



Automatic Test Architecture Generation

Testing units of a Rhapsody model using the Rhapsody Testing Profile requires certain steps to be repeatedly performed. Therefore TestConductor provides a powerful feature that creates the complete *test architecture* automatically. Automatic test architecture generation means:

- ◆ Creation of a new test package
- ◆ Creation of a new test context
- ◆ Instantiation of the selected SUT class as part of the test context
- ◆ Creation of test components
- ◆ Instantiation and 'wiring' of test component instances as parts of the test context
- ◆ Creation of an adequate code generation configuration
- ◆ Adding a test configuration (dependency-relation) to the test context referring to the created code generation configuration
- ◆ Creation and drawing of a test context diagram

TestArchitecture generation can be customized using property

`TestConductor::Settings::CreateTestArchitectureMode` (cf TestConductor settings “General Properties”, page 133).

If `CreateTestArchitectureMode` is set to ‘Standard’, then project properties are used in the generated code generation configuration while ‘Advanced’ opens a dialog that allows selection of an existing configuration from which all overridden properties, settings, and scope settings will be inherited


Using Classes

For the next steps do the following:


- ◆ Open the CashRegister Model from the ‘\Samples\CppSamples\TestConductor’ folder.
- ◆ Browse to the object model diagram folder in the package CashRegisterPkg
- ◆ Open the object model diagram ProductDatabase Overview

The *creation of a test architecture* for the class `CashRegister` can take place on two different ways:

- ◆ Right-click on the `CashRegister` class in the Rhapsody browser and select **Create TestArchitecture**




- ◆ Right-click on the `CashRegister` class in the object model diagram and select **Create TestArchitecture**




TestConductor automatically creates the complete necessary test architecture which consists of:

- ◆ A new *test context diagram* with the test context `TCon_CashRegister` containing the `CashRegister` object `itsCashRegister` itself as SUT and all necessary test component instances which are derived from the SUT associations and ports.




- ◆ A new test package **TPkg_CashRegister** which contains all generated test components, the test context **TCon_CashRegister** with the SUT **itsCashRegister**, the test context diagram and the test component instances




Using Objects

Creating a test architecture on objects is a similar workflow as shown for classes, but in order to create a test architecture for testing an object, the object can not be directly instantiated as part of a test context. If an object is instantiated as part of a test context, the object is moved into another scope and thus be modified. Hence, in order to test provide test support for the object without modification of the original design, the test contexts just references the object from the design using directed associations and directed links.

In order to do integration testing on an object, the created test context gets a directed association to the selected object, which does not modify the object.



The structure diagram defining the structure of a test context is not capable of defining a link instantiating this association, since this link could only be initiated from without the test context. In order to be able to later rely on the initialization of the association, the test context is instrumented with an additional constructor/initializer initializing the association with the address of the global variable representing the object. Furthermore, the creation of the constructor/initializer has to take into account the multiplicity of the object. The implementation of the constructor/initializer is currently limited to Rhapsody in C/C++. The association is stereotyped with the testing profile stereotype <<instantiated>>.



The test architecture for objects will not care about ports of the object, since the mapping of these ports to ports of other objects may already be defined in the design. The only way

to stimulate an object in a system test architecture is to use the association from the test context to the object.


Rhapsody offers an alternative to create a test architecture on a selected object. The user can expose the class of the selected object. For Rhapsody in C++ this alternative will set the user into the position of applying unit tests to the underlying class of the object under test. **For Rhapsody in C, in general, exposing an object's class might not be the best choice, because exposing an object's class massively affects the code representation of the object's functions.**

Note: For Rhapsody in Ada, the user has to set the <<instantiated>> association manually. This is due to the fact, that global objects are instantiated after instantiation of the initial instances specified in the Initialization tab of the code generation configuration's feature dialog. In order to set the associaton manually, the initialization code entry of the Initailization tab of the code generation configuration's feature dialog is used, e.g.:

```
Tpkg_object_0.TCon_object_0.set_itsObject_0(
    p_TCon_object_0.all,
    Default.RiA_Instances.object_0);
if object_0 is an object of object_0_Class.
```

Using Files (Modules)

Creating a test architecture on files(to be more precise: modules) is a similar workflow as shown for objects. Support of modules is useful mostly for Rhapsody in C, since Rhapsody in C++ only allows external files within the scope of a CG component. Since modules provide global declarations and definitions, test support for modules is realized by a test context referring the module using a <<Usage>> dependency.




The declaration of external (source and library) files and testing with TestConductor is discussed in the chapter Black-Box Testing of External Files and Libraries at page 212.

Using Parts


Only global (i.e. top-level) objects may be tested. There will be no support for testing parts of composite classes.

Updating TestArchitectures

For existing TestArchitectures, TestConductor provides the possibility to automatically update a TestArchitecture after changes have been made on the SUT class. For instance, consider the situation depicted in the following example:




There is a class **A** that contains a **P1** with a required Interface **I1** and a provided Interface **I2**. The interface **I1** specifies one operation **f()** that takes no arguments and has no return type, and interface **I2** specifies an operation **g()** also without arguments and return type. When selecting class **A** as the SUT, TestConductor creates the following TestArchitecture for it:




In the generated TestArchitecture, one TestComponent is created containing an appropriate port **P1** such that the instance of the TestComponent can be linked to the Port **P1** of the


SUT instance itsA. Now suppose you do some changes on the SUT class A. For instance, we can add an additional Port P2 with a required Interface I2 to A, and we add a new operation h to the Interface I1:



Because of these design changes, the previously generated TestArchitecture is not complete any more. In order to get again a complete TestArchitecture TestConductor provides the capability to update an existing TestArchitecture. To do this, select the TestContext that should be updated and select “Update TestArchitecture”:




After applying “Update TestArchitecture”, you get the following updated TestArchitecture:



To update the TestArchitecture accordingly, TestConductor did the following modifications to the existing TestArchitecture:

1. A second TestComponent is created that is connected to the new Port P2 of the SUT instance.
2. Since an additional operation was specified for Interface I2, an additional operation h is added to the TestComponent connected to port P1.



After these modifications have been made by TestConductor, the TestArchitecture is complete again.

TestArchitecures for MicroC Models

TestConductor supports testing of MicroC models with a specifically taylored TestArchitecture generation.

Per default TestConductor restricts code generation component for the generated TestArchitecture such that all design packages but only the TestPackage containing the architecture belong to its scope. Setting property TestConductor::Settings::CreateTestArchitectureMode to 'Advanced' allows inheritance of overridden properties from an already existing configuration

Since code generation for MicroC does not regard initialization settings of the configuration, i.e. no initial instance selection, TestConductor explicitly creates an object of the test context.

The MicroC profile provides two different initialization modes: 'CompileTime' and 'RunTime'. While 'RunTime' is like normal initialization for C models which requires no specific support by TestConductor, 'CompileTime' influences a set of model elements, such as e.g. accessibility of associations. In particular, this affects the generated initializers of TestContexts for objects (cf. TestArchitecture creation "Using Objects", page 35). Consequently, TestArchitectures generated for initialization mode 'RunTime' are in general not compilable with 'CompileTime' initialization and vice versa. Note, that this also affects the initializer of TestComponents generated for statechart TestCases (cf. TestCase Definition with Statecharts, page 50 ff). It is, hence, strictly recommended to check the initialization mode defined for the project before creation of a TestArchitecture and to check the initialization mode defined for the referenced configuration before creation of the first statechart TestCase.

TestArchitectures for Code centric Models

For code centric Rhapsody models, the source code of the SUT is compiled to a library and the executable with the test harness is linking this library. The code of the SUT library is not instrumented with animation code and it is built with the code centric property settings while the test harness contains animation instrumentation.

For the SUT library, it is possible to chose an already existing library of the project or TestConductor can automatically create a new library CG Component.

The TestConductor sample "CppCarRadio" demonstrates testing of a code centric model. For the next steps, please open the sample located in folder "Samples\CppSamples\TestConductor\CppCarRadio", right click class "Radio" and select "Create TestArchitecture". A dialog appears with the options to select an existing library CG Configuration or to create a new library CG Component and Configuration for the SUT. If the existing CG Configuration "RadioLib::RadioDebug" is selected, a TestArchitecture is created with another CG Component and Configuration for the generation and compilation of the test harness. This CG Configuration has some properties enabled which are usually disabled in the code centric profile, for example properties "CG::Relation::AddGenerate" and "CG::Relation::SetGenerate" are enabled and "CG::Configuration::MainGenerationScheme" is set to "Full". The scope of the newly created CG Component contains only the test harness and it has a "Usage" dependency to the CG Component of the SUT, making sure the needed header files and the library of the SUT can be found.

If the user selects to create a new CG Component for the SUT library, then TestConductor creates two CG Components in the TestArchitecture: First a library CG Component "libSUT" with the scope set to the SUT class and its associations and the default property settings of the project and second an executable CG Component for the test harness.


After creating the TestArchitecture, the user should revise the settings of the newly created CG Components and Configurations. It might be necessary for example to add more model elements to the scope of the CG Components or to modify the options for the "Additional Sources", "Include Path" etc. The user has to build the SUT library; for the CG Configuration "RadioLib::RadioDebug" this can be done by executing the shell script

“buildLib.sh” (located on the project folder) in a cygwin shell. The executable of the test harness can be build using the TestConductor menu functions “Build TestCase”, “Build TestContext” or “Build TestPackage”.

The TestArchitecture for code centric models can be used the same way as TestArchitectures for non code centric models, with some restrictions because of the not animated SUT (internal communication of the SUT cannot be observed).

TestConductor.h, TestConductor_C.h and TestConductor_C.c, TestConductor.jar, TestConductor.ads and TestConductor.adb

Since Rhapsody 7.1 the testing profile require the test context, test components, and test component instances to include the TestConductor header file by setting property `CPP.CG.Class.ImpInclude` to `TestingConductor.h`. Additionally, TestConductor adds the path '`$(OMROOT)/../TestConductor`' to the include-path of the code-generation component when creating a test architecture.



To provide an adequate assertion support for Rhapsody in C, a similar header file is provided and the testing profile was extended, such that test context, test components, and test component instances automatically include an appropriate `TestConductor_C.h` header by setting property `C.CG.Class.ImpInclude` to `TestConductor_C.h`. In contrast to the Rhapsody in C++ solution, for Rhapsody in C also an C-Implementation file was provided, which is linked only once.

-	C CG	
-	Class	
	ImpIncludes	TestConductor_C.h
-	CPP CG	
-	Class	
	ImpIncludes	TestConductor.h

For Java, the class “org.btc.TestConductor.TestConductor” is added as specification include for TestContext and TestComponents.

JAVA CG		
Class		
DescriptionTemplate	[[* \$Description]]□□[[* @author \$A	
SpecIncludes	org.btc.TestConductor.TestConductor	


For Ada, the package “TestConductor” is made visible by adding an appropriate “with” clause to the implementation of test contexts and test components.

Ada CG		
Class		
ImplementationProlog	with TestConductor;	

Generate and Build the Test Context

After generation of the new *test context* you should check whether it is complete and consistent. Therefore you should generate und build the test context to get information about potential compile or link warning or errors.

- ◆ Right-click on the test context TCon_CashRegister and select **Build TestContext** from the context menu.



If the generate, compile and link procedure are resulting in an executable you are able to execute it.

Test Case Definition

Now *test cases* for the generated test context can be defined. TestConductor provides four possible means to define test cases:

- ◆ Test case definition with pure code (only in C/C++/Java/Ada)
- ◆ Test case definition via flow charts (only in C/C++)
- ◆ Test case definition via statecharts (only in C/C++/Java/Ada)
- ◆ Test case definition via sequence diagrams

Test Case Definition with Code


One of the most used means to test units today is writing test cases in the same language than the application is written. In the C/C++/Java/Ada domain, often the complete test environment and also the test case are written in C/C++/Java/Ada with the goal of functional or coverage testing.

With Rhapsody in C/C++/Java/Ada it is also possible to write test cases manually, because test cases are stereotyped primitive operations of a test context.

Define a Code Test Case

The creation of a new test case is nearly the same than creation of a new operation:


- ◆ Right-click on the test context `TCon_CashRegister` and select **Create Code TestCase**



- ◆ Name the new test case "tc_code"



- ◆ Open the **Features** dialog of the new test case and enter the code into the implementation tab.



The objective of the test case is to verify whether the function `addProduct` correctly adds a product to the bill list (realized by the ordered association `itsProduct`).

First, the test case checks whether the bill list is empty. If not, the operation `isNoMoreProduct` returns `FALSE`. In this case the macro `RTC_ASSERT_NAME("check_1.1", i1==1)` returns a *FAILED* to TestConductor. Otherwise the result of the `RTC_ASSERT_NAME` macro is *PASSED*. In the next step a product “apple” is added. At the end the bill list is checked again.


Note: This test case is using two attributes `i1` and `i2` of type `int`. Both attributes have to be defined within the test context `TCon_CashRegister`.

Note: TestConductor provides several `RTC_ASSERT` macro types, which can be used to define assertions within test cases. A detailed description of these macros can be found in the chapter TestConductor Assert Macro on page 245.

Execute a Code Test Case

Now you are able to execute the test case by doing following steps:

- ◆ Right-click on the test case “tc_code” and select **Build TestCase** from the context menu
- ◆ Right-click on the test case “tc_code” and select **Execute TestCase** from the context menu




Name	Status	File/Iteration	Line/Progress
tc_code	✓ PASSED		
check_1.1	✓ PASSED	TCon_CashRegister.cpp	53
check_1.2	✓ PASSED	TCon_CashRegister.cpp	56

The test execution window shows the result of the checked assertions. Both are *PASSED* meaning that the tested behavior is ok.

Further information about test execution and the related results is described under chapter Test Execution on page 67.

Failure Analysis in CodeTest Cases

TestConductor lists in the execution dialog all executed assertions. To display the corresponding assertion, select in the execution dialog the item name in the column **Name** and press the button **Show Assertion**.



Further information about failure analysis can be found in chapter Failure Analysis on page 222.

Testing reactive behavior with Code Test Cases

Since code test cases are basically primitive operations of a test context, testing reactive behavior, i.e. reaction to events, can not be done without modifications to the test context. Primitive operations can't wait on events so please make the TextContext an active object and hence a separate thread. In this case, the thread executing the test context can be delayed unless the SUT has reacted to an event.

- ◆ Example code in C++:

```
itsClass_0.GEN(evX());  
OXFTDelay(1000);  
RTC_ASSERT_NAME("reaction",itsClass_0.IS_IN(reaction_state));
```
- ◆ Example code in C:

```
RiCGEN(&(me->itsClass_0),evX());  
RiCOXFDelay(1000);  
RiCIS_IN(&(me->itsClass_0),reaction_state);
```
- ◆ Example code in Java:


```
itsStopWatch.gen(new evPressKey(1));  
  
try {  
    wait(4000);  
} catch(Exception e)  
{ }  
  
TestConductor.ASSERT_NAME("Check state of  
stopwatch",itsStopWatch.isIn(ROOT.Running));
```

Test Case Definition with Flow Charts


A graphical way to describe test cases is by using flow charts. Since test cases are special operations of a test context you can use flow charts. Flow charts can be used to define the behavior of primitive operations with Rhapsody.

Define a Flow Chart Test Case

- ◆ Right-click on the test context TCon_CashRegister and select **Create FlowChart TestCase**



- ◆ Name the new test case “tc_flow_chart”
- ◆ Draw the following flow chart




The objective of the test case is the same as used in the code test case above.

First, the test case checks whether the bill list is empty. If not, the operation `isNoMoreProduct` returns `FALSE`. In this case the macro `RTC_ASSERT_NAME` ("check_2.1, Initialization failed", 0) returns a *FAILED* to TestConductor. In the next step a product "apple" is added. At the end the bill list is checked again

Execute a Flow Chart Test Case

Now you are be able to execute the test case by doing following steps:

- ◆ Right-click on the test case "tc_flow_chart" and select **Build TestCase** from the context menu
- ◆ Right-click on the test case "tc_flow_chart" and select **Execute TestCase** from the context menu




Name	Status	File/Iteration	Line/Progress
FC_tc_0	PASSED		
check_2....	PASSED	TCon_CashRegister.cpp	68

The test execution dialog shows the result of the defined assertions. The assertion "check_2.2, Product successfully added" passed the test, which means that the tested behavior is ok. Other than in the code test case here you can only see one assertion in the execution dialog. This is due to the condition connector used in the flow chart. Only when the condition `[i1==1]` is `false`, the assertion "check_2.1, Initialization failed" is executed.

Further information about test execution and the related results is described under chapter Test Execution on page 67.

Failure Analysis in Flow Chart Test Cases

TestConductor lists in the execution dialog all executed assertions. To display the corresponding assertion, select in the execution dialog the item name in the column **Name** and press the button **Show Assertion**.



Further information about failure analysis can be found in chapter Failure Analysis on page 222.

Testing reactive behavior with Flow Chart Test Cases

Since flow chart test cases are basically primitive operations of a test context, testing reactive behavior, i.e. reaction to events, can not be done without modifications to the test context. Primitive operations can themselves not wait on events. Thus, the test context has to be active, i.e. must run in a thread different from the thread executing the SUT. In this case, the thread executing the test context can be delayed unless the SUT has reacted to an event.

- ◆ Example code in C++:

```
itsClass_0.GEN(evX());
OXFTDelay(1000);
RTC_ASSERT_NAME("reaction",itsClass_0.IS_IN(reaction_state));
```
- ◆ Example code in C:

```
RiCGEN(&(me->itsClass_0),evX());
RiCOXFDelay(1000);
RiCIS_IN(&(me->itsClass_0),reaction_state);
```
- ◆ Example code in Java:

```
itsStopWatch.gen(new evPressKey(1));

try {
    wait(4000);
} catch(Exception e)

{ }

TestConductor.ASSERT_NAME("Check state of
stopwatch",itsStopWatch.isIn(ROOT.Running));
```

TestCase Definition with Statecharts

Test cases can alternatively be defined using statecharts. Due to their ability to wait on timeouts, statechart test cases are particularly suited for testing reactive behavior. In order to separate test case behavior from possible reactive behavior of the test context, statechart test cases are defined using specialized test components, which are then dynamically instantiated for test execution.

Statechart testcases are comprised of the following model elements:


- ◆ a TestCase , i.e. basically a primitive operation of the test context.
- ◆ a TestComponent owning the statechart defining the test case behavior.
- ◆ a dependency of the test case on the test component. This dependency is stereotyped <<StatechartTestCase>>.

This chapter gives a short overview about the usage of statechart test cases. It describes:

- ◆ How to define a simple statechart test case.
- ◆ How the model is populated for executing a statechart test case.
- ◆ How statechart test cases can be executed.

Define a Statechart Test Case


- ◆ Right-click on the test context `TCon_CashRegister` and select **Create Statechart TestCase**




Creation of a statechart test case adds a test case to the test context. This test case has a dependency on a newly created test component owning the statechart. The test component has a directed association to the test context, which can be used to refer to parts, variables and operations of the test context. Upon execution, the statechart test case dynamically instantiates the test component, initializes the association and starts statechart execution.

Furthermore, the test context needs to be populated with a *rtc_init()* and a *rtc_exit()* operation which are invoked by the statechart. This population is initiated by “Update TestCase”, “Update TestContext”, and “Update TestPackage”, respectively.

The following figure shows the browser after statechart test case creation:




- ◆ Name the new test case “tc_statechart”
- ◆ Draw the following statechart



Execute a Statechart Test Case

Now you are able to execute the test case by doing following steps:

- ◆ Right-click on the test case “tc_statechart” and select **Update TestCase** from the context menu
- ◆ Right-click on the test case “tc_statechart” and select **Build TestCase** from the context menu
- ◆ Right-click on the test case “tc_statechart” and select **Execute TestCase** from the context menu



The test execution dialog shows the result of the defined assertions. The assertion “evStart_received” passed the test, which means that the tested behavior is ok.

Further information about test execution and the related results is described under chapter Test Execution on page 67.

Failure Analysis in Statechart Test Cases

TestConductor lists in the execution dialog all executed assertions. To display the corresponding assertion, select in the execution dialog the item name in the column **Name** and press the button **Show Assertion**.

Further information about failure analysis can be found in chapter Failure Analysis on page 222.

Test Case Definition with Sequence Diagrams

Another option to define test cases is by using sequence diagrams. In the context of the Rhapsody Testing Profile such sequence diagrams are called *test scenarios* (*TestScenarios*). Test scenarios play a dominant role in the TestConductor test process. They are the graphical means of specifying and defining the tests, and enable TestConductor to visualize design flaws.

This chapter gives a short overview about the usage of sequence diagram based test cases. It describes:


- ◆ How to define a simple sequence diagram test case
- ◆ How the generation of driver and sub operation works (see also chapter *Model Population* on page 58)
- ◆ How sequence diagram test cases can be executed

Detailed information regarding the usage of the powerful features of sequence diagram test cases are described in chapter Advanced Test Definition on page 153 ff.


Define a Sequence Diagram Test Case

Driving the SUT using Test Components (only C/C++/Java/Ada)

- ◆ Right-click on the test context `TCon_CashRegister` and select **Create SD TestCase**




Note: TestConductor generates a new test case “SD_tc_0()” with a dependency “SD_tc_0” to a newly generated test scenario “SDTestScenario_0”.




- ◆ Rename the new test case to “tc_SimpleStart”
- ◆ Rename the new test scenario to “SDSimpleStart”

The generated test scenario looks like the following diagram. It contains lifelines for each SUT and test component object defined in the test architecture.



- ◆ Remove the lifelines `TCon_CashRegister.itsTC_For_itsProduct` and `TCon_CashRegister.itsTC_for_itsCountedProduct` from the view, because these lifelines are not used in the following test scenario
- ◆ Draw the following messages into the test scenario



In this test scenario the test component `TCon_CashRegister.itsTC_at_hw` is driving the SUT with the message `evStart()`. The expected result is the message shown below `show()`.

Note: During execution parameter values containing quotes will consistently be stripped, e.g. the expression “OK” will be converted to OK and “”OK”” will be converted to “OK”.

The scenario describes the normal way in which objects communicate among each other. Messages from an environment line are only necessary when messages have to be sent from the system boundary (e.g. an actor is sending an event to an object of the system).


Driving the SUT using ENV

Note: Driving from ENV is only supported in animation based testing mode (`TestConductor.Settings.TestingMode == AnimationBased`)

If you are testing an animated application, inputs can also originate from the ENV life line in a sequence diagram. To define a sequence diagram test case in such a manner you have to draw a slightly different test scenario.

- ◆ Create a new test case as described above
- ◆ Rename the new test case to “tc_SimpleStartENV”

- ◆ Rename the new test scenario to “SDSimpleStartENV”
- ◆ Remove the lifelines `TCon_CashRegister.itsTC_For_itsProduct` and `TCon_CashRegister.itsTC_for_itsCountedProduct` from view, because these lifelines are not used in the following test scenario
- ◆ Add an ENV line to the test scenario
- ◆ Draw the following messages into the test scenario



Execute a Sequence Diagram Test Case

Now you are able to execute the test case by doing following steps:

- ◆ Right-click on the test case “tc_SimpleStart” and select **Update TestCase** from the context menu
- ◆ Right-click on the test case “tc_SimpleStart” and select **Build TestCase** from the context menu
- ◆ Right-click on the test case “tc_SimpleStart” and select **Execute TestCase** from the context menu – Alternatively you can right-click on test scenario to “SDSimpleStart” and select “Execute TestCase of TestScenario” from the context menu.
- ◆ The test is executed, and you can see the results in the execution window.


Execution Results			
Name	Status	File/Iteration	Line/Progress
tc_sequence_diagram	FAILED		
SD_tc_0	FAILED	1	75% (3/4)

Failure Analysis in Sequence Diagram Test Cases

The execution of the test case failed. To find out why you can do the following:

- ◆ Select the item “SD_tc_0” in the execution dialog and double-click the item. Alternatively, select the item “SD_tc_0” and select “Show as SD” from the context menu.
- ◆ Press **Quit**

With **Show as SD** TestConductor has generated a new color coded sequence diagram which shows the found failure.



In this case the argument of the `show()` message sent by the SUT has a different value than expected. The expected argument value is “aMsg=OK” while the real observed value is “aMsg=Ready”. The reason for the problem is that we specified an incorrect test scenario which must be corrected now.

You can change the argument from “OK” to “Ready” in the test scenario “SDSimpleStart”. Then again perform the steps described above.

Note: During execution parameter values containing quotes will consistently be stripped, e.g. the expression “OK” will be converted to OK and “”OK”” will be converted to “OK”.

Further information about test execution and the related results is described in chapter Test Execution on page 67.

Further information about failure analysis can be found in chapter Failure Analysis on page 222.

Model Population – Create Driver Operations and Stub Operations (for Rhapsody in C/C++/Java/Ada)


Whenever test components are used to drive input messages of the SUT or to be forced to return a pre-defined value of an operation call to the test component users have to provide driver or stub operations for test components.

By using sequence diagram test cases TestConductor automates the generation of driver operations and stub operations. Simply by choosing the context menu **Update TestCase** on test case level, by choosing the context menu **Update TestContext** on test context level, or by choosing the context menu **Update TestPackage** on test package level the work is done. Choosing one of these menu entries starts the so-called “model population” process of TestConductor. It analyses each defined sequence diagram instance and the linked test scenarios to generate necessary driver and stub operations for the test components.

Driver Operations

Driver operations (DriverOperations) are created for any message going from a test component to the SUT, except for messages carrying the tag *RTC_Monitor*, or messages starting at an instance line with the tag *RTC_Monitor*. In this case TestConductor assumes the message should not be driven. Driver operations will be generated only for messages from sequence diagrams referred by a sequence diagram instance with the mode “driver and monitor”.

For example look into the generated driver operation of the test case “tc_SimpleStart”:



TestConductor analyzed the given test architecture, the ports, and the interfaces, and then TestConductor generated a new driver operation for the test component *TC_at_hw* called *tc_SimpleStart_evStart_1()*. The implementation tab of this operation shows the generated code. Beside some comments there is the code line

```
OUT_PORT(hw)->GEN(evStart());
```

This implementation realizes the sending of the message `evStart()` from the `TestComponentInstance TCon_CashRegister.itsTC_at_hw` through the port `hw` to the SUT. During test execution `TestConductor` will call the driver operation `tc_SimpleStart_evStart_1()` which in turn generates the specified input event `evStart()` using the port connection (`hw`).

The name of the driver operation is the concatenation of the name of the test case, “_”, the name of the original operation, “_” and a number to create a unique name. A comment is generated into the code of the driver operation that contains the identifier of the message and the name of the test case for which the driver operation was generated. This allows the user to identify the correct driver operation if he wants to edit it.

In the context of the model-population, the identifier of a message is the value of the tag `TestBehavior::RTC_MsgInfo::RTC_MsgId`. `TestConductor` generates such an identifier for a message when needed, using the naming scheme `'message_<unique_number>'`.

The visibility of the driver operation will be public, the property `CG.Operation.AnimAllowInvocation` of this operation will be set to “All” to make sure this operation can be invoked by `TestConductor`.

The body of the driver operation consists of a call of the original operation on the SUT (either on the destination instance itself or via a port, this is derived from the test context).

The values of any input argument for the driven operation call is derived from the specification in the sequence diagram, the specified return-value(if existent) and the specified output argument values are stored in local variables. `TestConductor` makes sure that the call is done on the correct instance of the SUT if multiple instances of the same SUT class exist.

If the sequence diagram specifies that the returned value should be checked, the macro `RTC_ASSERT_SD_NAME` is used to check if the returned value and the expected returned value are equal. The same macro is used to check if out or in/out argument values returned by the operation call are as specified in the sequence diagram. If any of these checks fails the test case fails.

The values of parameters defined for the sequence diagram instance are propagated to the driver operation this way: If any parameter is used in the argument value- or return value specification of the operation that should be driven, then in the body of the driver operation the argument-value or return-value is substituted with the value of the parameter. A corresponding substitution is taken into account, if sequence diagram parameter values are used as sequence diagram instance names.

For further information how to customize the driver operation please read the chapter *User Defined Driving Operation Calls* (for Rhapsody in C/C++/Java/Ada) at page 204.

Stub Operations

Typically *stub operations* (`StubOperations`) are used to return a special return value for an operation call that is needed to test a special behavior of the SUT that depends on this return value.


Stub operations are created for any operation call in the sequence diagram going from the SUT to a test component if a return value (or an out value for an out or in/out argument) is

specified for this operation. TestConductor needs the ability to determine and control the value returned by the operation. On the other hand there might be some calls to the same operation without a specified return value or the operation is called by a test component on a test component. Because of this TestConductor has to generate a different body for the operation, but it must still be possible to call the original operation.


Note: For assertion based testing mode (TestConductor.Settings.TestingMode == AssertionBased), for all messages from a SUT life line to a TestComponent life line, TestConductor creates a stub operation. In assertion based testing mode, these stubs are needed in order to inform the test case that a specified message has indeed occurred during test case execution.

To show this in an example you have to do some model changes:


- ◆ Open the feature dialog of operation show () of class IDisplay in package InterfacePkg
- ◆ Change the return type from void to bool




- ◆ Open the feature dialog of operation show () of the test component TC_at_hw in package TPkg_CashRegister_0
- ◆ Change the return type from void to bool




- ◆ Change the implementation of the operation `show()` from “return” to “return true”.




- ◆ Define a return value `false` for the message `show()` in the test scenario “SimpleStart”.



- ◆ Choose **Update TestCase** from the context menu of test case “tc_SimpleStart”




The result of the update and model population process can be seen in the Rhapsody browser (see following figure)




TestConductor has done some modifications within the test component TC_at_hw.

- ◆ The operation `show()` has been renamed to `original_show(..)` and is stereotyped with *DefaultOperation*.
- ◆ A new stub operation `tc_SimpleStart_stub_show_1()` has been generated. The generated stub operation returns a value `false` needed for the test case "tc_SimpleStart".



- ◆ A new stubbed operation show () has been generated.



The stubbed operation show () replaces the original operation show () and is called always when the SUT calls the operation show () on the specified test component. This operation immediately decides whether the original show message has to be called or if a stubbed value shall be generated. This behaviour is realized on a per test case and on a per message basis.

Note: Each message in a sequence diagram has a unique Rhapsody GUID. So TestConductor is able to uniquely identify each message with in a sequence diagram.


For further information how to customize the stub operation please read the chapter User Defined Stub Operation Calls (for Rhapsody in C/C++/Java/Ada) at page 209.

Creating test cases with the test case wizard

As an alternative to manually create test cases, one can also automatically create test cases with the test case wizard. The test case wizard allows to automatically create test cases based on existing


- ◆ Sequence Diagrams
- ◆ Operations and Event Reception
- ◆ Requirements

1. In order to create a test cases based on an existing Sequence Diagram, do the following:
 - In the browser or in the sequence diagram editor, rightclick the sequence diagram and select “Create TestCase...”. This opens the test case wizard dialog:




- In the test case wizard dialog, all test architectures (i.e., all test contexts) that are suitable to map the life lines of the existing sequence diagram to the life lines that are available in the test architecture (i.e., the life lines of the SUT instances and the life lines of the test component instances) are listed. A test architecture is suitable, if
 - All life lines of the existing sequence diagram can be mapped to life lines of SUT instances or test component instances s.t. all specified messages can occur also between the remapped life lines of the test architecture.

- At least one life line of the existing sequence diagram must belong to the same class (or file/object) as one of the SUT instances of the test architecture. This rule can be turned on/off by setting the property “TestConductor.Settings.MapSDToTestArchitectureMode” to “weak”. By setting this property to “weak”, no existence of a life line that has the same class as one of the SUT classes is required any more. Only the specified messages must be possible in the remapped life lines of the test architecture. This mode allows to remap an existing sequence diagram also to test architectures that contain completely disjoint classes but which have at least interfaces that are compatible. The default value for this property is “strict”.
- If no suitable test architecture is found, the list contains only the element <<new>>. When selecting <<new>>, a new dialog will open that lists all classes of all life lines of the selected sequence diagram. In this dialog, one has to choose one of the listed classes as the SUT class for the new test architecture. After pressing ok, a new test architecture will be created for the selected SUT class.
- As a result, a new sequence diagram test case will be created that contains the same messages as the original sequence diagram, but the life lines of the test architecture.



- In order to create a test cases based on an operation or an event reception, do the following:
 - In the browser, select one of the operations or event receptions of a class (or file/object) and select “Create TestCase...” from the context menu.
 - In the test case wizard dialog, all test architectures (i.e., all test contexts) that contains a SUT instance of the class (or file/object) of the selected operation/event reception are listed. Additionally, the element <<new>> is listed. Furthermore, a dropdown box can be used to select the kind of test case one wants to create. Depending of the selection of the test architecture and the test case kind, a new test case is created and added to the selected test architecture. When <<new>> is selected, a new test architecture for the class (or file/object) of the selected operation is created.



The created test case already contains a call to the selected operation with default arguments. Additionally, a dummy assertion is created that can be refined in order to check out values of the called operation.

3. In order to create a test cases based on a requirement, do the following:
 - In the browser, select a requirement and select “Create TestCase...” from the context menu.
 - In the test case wizard dialog, all test architectures (i.e., all test contexts) of the model are listed. Additionally, the element <<new>> is listed. Furthermore, a dropdown box can be used to select the kind of test case one wants to create. Depending of the selection of the test architecture and the test case kind, a new test case is created and added to the selected test architecture. When <<new>> is selected, a new test architecture (a subsequent dialogs asks for the class for which a new test architecture should be created) is created. Furthermore, the original requirement for which the new test case has been created is linked as a test objective to the test case.

Test Execution

During test execution, TestConductor drives events, operation calls, and dataflows sent from the test components, test context or environment to SUT objects, and monitors all messages between objects, actors and environment as specified in the test cases. This means that TestConductor automatically checks and reports whether the order of messages sent and received corresponds to the real order in the running application. In addition, TestConductor monitors the arguments of messages. Since TestConductor checks the application behavior (against requirements) using animation mechanisms, you must generate code for the test configuration with animation instrumentation switched on (at least for test components). See the *Rhapsody User Guide* for detailed information on animation settings.

Overview

TestConductor supports several kinds of execution modes

- ◆ Execution of code test cases
- ◆ Execution of flow chart test cases
- ◆ Execution of statechart test cases
- ◆ Execution of sequence diagram test cases
- ◆ Execution of a test context
- ◆ Execution of a test package
- ◆ Batch mode execution

The test execution is visualized with an execution dialog. Depending on the type of test cases the view and interaction possibilities of the execution dialog slightly differ.

Test Configuration


Prerequisite for each execution of an application is a defined Rhapsody code generation configuration. This configuration must be compileable and linkable.

Test Configuration for assertion based testing


In assertion based testing mode, a configuration that shall be used for test execution must have the stereotype <<TestingConfiguration>>. Such a configuration is automatically generated when using test architecture creation of TestConductor.

Test Configuration for animation based testing

This has to be fulfilled also for test execution. By using the automatic test architecture generation feature of TestConductor a new component and a related configuration is automatically added to the model for each test context. For example a component `TCon_CashRegister_Component` and a configuration “DefaultConfig” was generated automatically for the test context `TCon_CashRegister`.



Also the settings for the code generation are done.



Note: For test execution the instrumentation mode must be set to animation¹, because TestConductor needs the animation information to observe the behavior of the test context.


The animation mode is necessary for all elements around the SUT in the test context. In order to perform (black box) production code testing the animation of the SUT can be switched off. Thus, the test execution can be done in

- ◆ White box mode
- ◆ Black box mode

White box mode means that the test context and also the SUT classes are generated with animation code, while in black box mode the SUT classes are generated without any animation code information (production code).

White Box Testing (only animation based testing)


White box testing means that the internal behavior of the SUT can be observed. For example the message `startSession()` can be observed in white box mode, because the SUT was generated with animation information.




Build Test Context (White Box)

TestConductor supports the code generation for white box testing via enabling the animation of the SUT class. To enable white box testing select the property `CPPCG::Class::Animate` of the SUT class `CashRegister`.

¹ Except for `OfflineTesting`, which is aimed at asynchronous testing of non-animated applications.





After switching the property you have to build the test case in order to get animated code. The result of this process is an executable with animation code for the SUT object. TestConductor will automatically recognize that the SUT shall be tested in white box mode.

Production Code (Black Box) Testing

Production code or *black box testing* means that the internal behavior of the SUT can not be observed by TestConductor. The objective is to test the interface behavior of a SUT.


Note: You can use the same test cases defined for white box testing. In case of black box testing TestConductor ignores all messages which communicate between SUT objects. Only the input and output messages are observed.


Black Box Testing (Assertion based testing mode)

If TestConductor is working in assertion based testing mode, black box testing can be achieved by setting the instrumentation of the testing configuration to “None”.

Build Test Context (Black Box for animation based testing mode)

Rhapsody supports the code generation for black box testing via disabling the animation of the SUT class. To enable black box testing deselect the property `CPPCG::Class::Animate` of the SUT class `CashRegister`.





After switching the property you have to build the test case in order to get non animated code for the SUT. The result of this process is an executable without animated SUT objects. TestConductor will automatically recognize that the SUT shall be tested in black box mode.

Test Case Execution

Code based Execution Dialog

Flow chart , code, and statechart test cases are merely code based test cases, because TestConductor uses the code generation capabilities of Rhapsody's code generator. The execution dialog enables you to activate the actual test execution and displays the test results.


If you have modified your SUT or your test context, you must rebuild the code of the test context before you start actual test execution.

Execute any test case by using the context menu entry **Execute TestCase**. The TestConductor execution dialog will open, and the test case execution will be started.

Test Execution Window

1. TestConductor displays the assertions defined in a code, flow chart, or statechart test case at run-time of the test case. During test execution new assertions are listed as

soon as they are reached and checked by TestConductor. Each line in the dialog displays information about one particular assertion including the final results, as shown in the following figure.



Name	Status	File/Iteration	Line/Progress
tc_code	✓ PASSED		
check_1.1	✓ PASSED	TCon_CashRegister.cpp	129
check_1.2	✓ PASSED	TCon_CashRegister.cpp	132

After the test case execution has been terminated you can analyze the results of executed assertions.

Test Information

TestConductor displays information to analyze the test results. The information columns are as follows:

- ◆ **Name**—Displays the name of the assertion checked by TestConductor during test execution.
- ◆ **File/Iteration**—Shows information about the source file name in which the TestConductor assertion is specified. If a SD test case is executed, it shows the iteration number of the SDInstance.
- ◆ **Line/Progress**—Shows information about the code line within the file in which the assertion is specified. If a SD test case is executed, it shows the progress of the SD instance.
- ◆ **Result**—Shows the result of the assertion. The possible values are *PASSED* and *FAILED*.

Controlling test case execution

The test case execution dialog provides several functions that can be used to control the test case execution. The functions are available by pressing one of the icons in the top right corner of the execution dialog.


Sequence Diagram based Execution Dialog

The execution dialog enables you to activate the actual test execution and displays the test results. You can use test results in order to generate sequence diagrams for further regression testing or in order to prepare documentation.

If you have modified your SUT or your test context, you must rebuild the code of the test context before you start test execution.

Context menu entry **Execute TestCase** of a selected test case opens the execution dialog. For a sequence diagram that is exclusively referenced by only one test case, the execution dialog can alternatively be opened using the context menu entry **Execute TestCase of**

TestScenario of the selected sequence diagram. After selecting **Execute TestCase**, the execution dialog opens and the test case execution starts.




Name	Status	File/Iteration	Line/Progress
tc_sequence_diagram	EXECUTING		
SD_tc_0	ACTIVE	1	0% (0/4)

Test Execution Window

During test case execution, the test execution information is displayed in the test execution dialog.

1. TestConductor displays the first iterations of sequence diagram instances without specified ordered predecessors as the initial run-time instances in the execution dialog. During test execution new run-time instances are listed as soon as their ordered predecessors or previous iterations have been fully traversed. Each line in the dialog displays information about one sequence diagram run-time instance, including intermediate and final results, as shown in the following figure.



Name	Status	File/Iteration	Line/Progress
tc_sequence_diagram	FAILED		
SD_tc_0	FAILED	1	75% (3/4)

Since the test is still running you cannot modify it. However, you can verify the test configuration, the activation conditions of the sequence diagram instances, and so on.

Test Information

TestConductor displays information to analyze the test results. The information columns are as follows:

- ◆ **Name**—Shows the list of all run-time instances in the order of their appearance in the test. You can activate sequence diagram instances sequentially (one after another) or in parallel (independently).
- ◆ **Status**—Shows the current states of run-time instances during test execution. The possible values are “*NOT ACTIVE*”, “*ACTIVE*”, “*PASSED*”, and “*FAILED*”. In the example, the entire test executes automatically, until it eventually shows the final result “(Status - FAILED)”, because TestConductor found an error.

- ◆ **File/Iteration**—Shows the absolute number of the currently executed run-time instance of the sequence diagram instance under consideration. At each point in time, you can have at most one active run-time instance of an sequence diagram instance. However, over time you can have infinitely many invocations. In the example of the “tc_SimpleStart” test, only one run-time instance appears in this field, because you selected single iteration mode. An arbitrary number of run-time instances can be created during model execution if the execution mode of an sequence diagram instance is set to multiple iteration with a concrete number.
- ◆ **Line/Progress**—Shows the percentage of message actions that passed successfully through the tested sequence diagram instance during test execution. A message action is one of the following:
 - Event sending
 - Internal event consumption
 - Operation call
 - Condition mark validation

For example, every event arrow in an sequence diagram specifies two ordered message actions. TestConductor displays the progress as “percentage X/Y”. The X stands for the number of actions that passed; Y stands for all the actions specified in the sequence diagram. For example, this test failed at 75%, and 3 out of 4 actions passed.


Displaying Test Results

Graphical Test Sequence Diagrams

You can display the test results graphically in order to analyze the states of a run-time instance at different points in time.

For example, to display a failure in the “tc_SimpleStart”, do the following:

- ◆ To see the graphical representation of the results, select a run-time instance in the list and select **Show as SD** from the context menu. A recorded sequence diagram is displayed, showing the actual order of the messages passed through the model simulation.



The resulting sequence diagram can be used for failure analysis or can be saved for further documentation.

In the sequence diagram created for a run-time instance, the following messages are displayed:

- ◆ Messages that have already occurred in the executed application. Observed messages are shown in *green*.
- ◆ Messages that are missed. Expected but not seen messages are shown in blue.
- ◆ A message that has wrongly arrived or parameter values that do not match. Messages that are observed in not expected order (failure) are shown in *red*.

A *red* message indicates a failure. In the resulting exported sequence diagram, a red message is annotated with a short explanation of the failure, which can be one of the following:


- ◆ Sending out of order
- ◆ Event Sending - Parameter values do not match
- ◆ Event Sending - Parameter values not in range
- ◆ Consumption out of order
- ◆ Event Consumption - Parameter values do not match
- ◆ Event Consumption - Parameter values not in range
- ◆ Operation Call out of order
- ◆ Operation Call - In Parameter values do not match
- ◆ Operation Call - In Parameter values not in range
- ◆ Operation Call returned - Return value does not match
- ◆ Operation Call returned - Out Parameter values do not match
- ◆ Operation Call returned - Out Parameter values not in range
- ◆ DataFlow Message - Value does not match
- ◆ DataFlow Message - Value not in range
- ◆ DataFlow Message out of order

See page 222 for more information about failure analysis.


Automatically adding SDs to the model for failed SDInstances

Note: In assertion based testing mode, each time you do a “Show as SD”, TestConductor automatically adds a color coded SD to the model. The color coded SD is added to the model to the same owner as the original specification SD. By default, the test case operation is the owner of the specification SD.

Sometimes it is useful that SDs showing failed SDInstances are added automatically to the model after test case execution, e.g. for documentation purposes if test cases are executed in batch mode. In order to do this, switch on the property “TestConductor.TestCase.CreateSDForFailedSDInstance”:



Now, after executing a test case that has switched on this property, TestConductor automatically adds a SD to the model showing the reason of the test case failure. Additionally, a dependency is added to the TestResult of the executed test case linking the TestResult to the added SD. This dependency can be used to navigate directly from the TestResult to the SDs that have been added for the failed SDInstances.



Abort Test Execution

In order to *abort a running test* either click the **stop icon** in the Rhapsody tool bar or click the **abort icon** in the test execution window.

Execution Timeout

Execution timeout for animation based testing

The testing profile defines a global timeout, which can be overwritten for every test package, test context and test case. This default value is 600 seconds.


You may define a *timeout* for every test case separately via the property

```
TestConductor::TestCase::ExecutionIdleTimeout
```


In case a timeout is defined and the application does not show any activity for <value of timeout> seconds the execution of this test case is interrupted. In this case, this test case will be marked as “*timeout*” in the result report.

Execution timeout for assertion based testing

In assertion based testing mode, in order to define a timeout for test cases, the scheduler that actually starts and stops the test case execution must be changed. By default, a standard scheduler that is autogenerated for a test architecture has the following structure:



Now, in order to have define a test case timeout that works for all executed test cases, add the following transition to the scheduler with the timeout value you want to have for your test cases. In the depicted sampel, we choose a timeout value of 3 seconds:



Test Execution Report

After the execution of a test case has finished and the execution dialog has closed, an execution report is written into a *HTML file*. This file is added to the test case as a controlled file. If a report file already exists it is overwritten. Only the report of the last test case execution is stored in the model.



TestConductor also stores a tag *Verdict* below the linked report file, which stores the result of the test case execution.

Tag : Verdict in TCon_CashRegister__tc_SimpleStart_0.html

General Description

Name: Verdict L

Applicable to: [dropdown]

Type: String [document icon]

Value: Passed [ellipsis]

Locate OK Apply

Possible values are: "*Passed*", "*Failed*", "*Aborted*", "*Timeout*" and "*Undefined*" and "*Error*".

A double click on the test result "TCon_CashRegister__tc_SimpleStart_0.html" opens the linked HTML test report.

Test Case Result

Test Case: tc_SimpleStart

16:25:24, Tuesday, March 06, 2007

Environment Info	
Test executed on machine:	NBOSC38
Test executed by user:	rsanders
Used OS version:	Windows 2000 / Windows XP
Used Rhapsody version:	Aries, build 805506
Used TestConductor version:	2.0, build 552

Tested Project	
Project:	CashRegister
Active Component:	TCon_CashRegister_0
Active Configuration:	DefaultConfig


SDs used in test	
TPkg_CashRegister_0::SimpleStart	

Summary Info	
Total number of SDs used:	1
Total number of SD instances in test:	1
Total number of executed SD instances:	1
Total number of PASSED SD instances:	0 (0%)
Total number of FAILED SD instances:	1 (100%)
Total number of ACTIVE SD instances:	0 (0%)
Total number of NOT ACTIVE SD instances:	0 (0%)


Detailed Results	
SD instance 'SD_tc_0'	
Iterations:	SD_tc_0
Status:	failed
Progress:	75% (3/4)

Debugging test cases

When a test case fails one can use TestConductor's debugging capabilities in order to find out the reason for the fail. In order to turn on test case debugging, one has to turn on "Debugging mode" in the test case execution window:



After turning on debugging mode, one can restart the test case, e.g. by pressing the "Start" icon in the execution window. In contrast to normal test execution mode, in debugging mode the test execution does not progress automatically but can be controlled by using Rhapsody's animation toolbar. For instance, one can step through the test case by using multiple "Go Step" commands in the animation toolbar. In the execution window, one can see the current progress of the test case, and in parallel one can use Rhapsody's animation features (e.g. animated sequence diagrams or animated statecharts) to inspect the model during debugging of the test case. Besides "Go Step", also all other animation commands like "Go Idle" etc. are available, e.g. one can add tracer commands etc.



Using breaks and tracer commands during debugging (only animation based testing mode)

In debugging mode, in addition to stepping through the test case execution using Rhapsody's animation toolbar, one can also define breaks and tracer commands in the test cases. When a break command is reached, the test case execution is broken at this location. When a tracer command is reached, it is simply executed. Both breaks and tracer commands can be used in all kinds of test cases.


1. Defining breaks and tracer commands in code/flowchart/statechart test cases:

To define a break in a code, flowchart or statechart test case, one has to write the macro "RTC_BREAK" (C/C++) resp. "TestConductor.BREAK()". When the test case execution reaches the break, it is executed and the test case execution is stopped. One can proceed the test case execution by using Rhapsody's animation


toolbar (e.g. by pressing “Go Step” or “Go Idle” etc.). To execute a specific tracer command during test case execution, one has to use the macro “RTC_TRACER_COMMAND(cmd)” (C/C++) resp. the function “TestConductor.TRACER_COMMAND(cmd)”. For details about the supported syntax of the “cmd” argument please look into Rhapsody’s User Guide. When the test case execution reaches the specified tracer command, it is simply executed as any other tracer command that was entered directly in Rhapsody’s animation toolbar.

2. Defining breaks and tracer commands in sequence diagram test cases:

To define a break in a sequence diagram test case, one has to add a condition on one of the life lines in the sequence diagram. In the condition, one has to write “RTC_BREAK”. When executing the test case in debugging mode, the test case execution stops when the break is reached. In Rhapsody’s animation output tab the information “Reached TestCase breakpoint” is printed.



To define tracer commands in a sequence diagram test case, one has to add a condition on one of the life lines in the sequence diagram. In the condition, one has to write “RTC_TRACER_COMMAND”. When executing the test case in debugging mode, the test case execution executes the specified tracer command when the execution reaches the position of the tracer command.




Test Context Execution


Starting Test Execution

One kind of batch execution is the execution of a complete test context. It will then execute all test cases belonging to a test context.

- ◆ Right-click on the test context TCon_CashRegister and select **Update TestContext**. This updates all necessary driver and stub operations derived from the defined sequence diagram test cases within the test context.
- ◆ Right-click on the test context TCon_CashRegister and select **Build TestContext**. This re-generates the necessary code for all elements of the test architecture and starts the compile and link process for the test architecture.
- ◆ Right-click on the test context TCon_CashRegister and select **Execute TestContext**. This starts the batch execution for all defined test cases within the test context.



If the user selects a test context and invokes its execution, all test cases of this test context are executed in a sequence. To terminate the execution of a test context or a test package, press the **abort icon** in the test execution window.



Name	Status	File/Iteration	Line/Progress
TCon_CashRegister	FAILED		
FC_tc_0	PASSED		
check_2.2, Pro...	PASSED	TCon_CashRegister.cpp	76
tc_code	PASSED		
check_1.1	PASSED	TCon_CashRegister.cpp	93
check_1.2	PASSED	TCon_CashRegister.cpp	96
tc_sequence_diagram	FAILED		
SD_tc_0	FAILED	1	75% (3/4)

Stopping Test Execution

To terminate the execution of a test context or a test package, press the **abort icon** in the test execution window.

Execution Timeout

The testing profile defines a global timeout, which can be overwritten for every test package, test context and test case. This default value is 600 seconds.


You may define a timeout for this batch mode execution of test cases individually per test case. This can be done via the property

```
TestConductor::TestCase::ExecutionIdleTimeout
```

If a timeout is defined and the application doesn't show any activity for <value of timeout> seconds the execution of this test case is interrupted and the next test case is started. In this case, this test case will be marked as “*timeout*” in the result report.

Ordering of Test Cases

The *order of the test cases* inside the test context (similar to the “*Edit Operations Order*” in the Rhapsody browser) can be changed. In this way you can influence the execution order of the test cases.




Per default the test cases are sorted and executed in alphabetical order.

Test Execution Report

After execution of each test case its result *HTML report* is written. The file is added to the test case as controlled file.

After execution of all test cases an execution report of the test context is written into a HTML file. The file is added to the test context as controlled file.



- ◆ A double-click on the test result “TCon_CashRegister_6.html” opens the linked test report.

Test Context Result

Test Context: TCon_CashRegister

Thu Mar 08 11:24:47 2007

Environment Info	
Test executed on machine:	NBOSC38
Test executed by user:	rsanders
Used OS version:	Windows 2000 / Windows XP
Used Rhapsody version:	Aries, build 805506
Used TestConductor version:	2.0, build 548

Tested Project	
Project:	CashRegister
Active Component:	TCon_CashRegister_0
Active Configuration:	DefaultConfig


Test Context: TCon_CashRegister	Summary: FAILED
tc_activity_diagram	PASSED
tc_code	PASSED
tc_SimpleStart	FAILED

Test Package Execution

Starting Test Execution

One kind of batch execution is the execution of a complete test package. It will then execute all test cases underneath all test contexts belonging to a test package.

- ◆ Right-click on the test package TPkg_CashRegister and select **Update TestPackage**. This updates all necessary driver and stub operations derived from the defined sequence diagram test cases within the test package.
- ◆ Right-click on the test package TPkg_CashRegister and select **Build TestPackage**. This re-generates the necessary code for all elements of the test architectures and starts the compile and link process of all test architectures.
- ◆ Right-click on the test package TPkg_CashRegister and select **Execute TestPackage**. This starts the batch execution of all defined test cases within the test package.



If you select a test package and invoke its execution, each defined test context of this test package is executed one after the other. The procedure is almost like the execution of a test context, except the following differences:

- ◆ If one test context cannot be executed, this test context is skipped, the reason for the problem is written to the result report, and the next test context is executed.

Stopping Execution

To terminate the execution of a test context or a test package, press the **abort icon** in the test execution window.

Execution Timeout

The testing profile defines a global timeout, which can be overwritten for every test package, test context and test case. This default value is 600 seconds.


You may define a timeout for this batch mode execution of test cases individually per test case. This can be done via the property

```
TestConductor::TestCase::ExecutionIdleTimeout
```

If a timeout is defined and the application doesn't show any activity for <value of timeout> seconds the execution of this test case is interrupted and the next test case is started. In this case, this test case will be marked as “inconclusive” in the result report.

Test Execution Report

After the execution of all test cases, the execution report is written into a HTML file. This file is added to the test package as a controlled file. A report for each test context that has been executed was also created during execution.



- ◆ A double click on the test result “Result_0.html” opens the linked test report

Test Package Result

Test Package: TPkg_CashRegister_0

Thu Mar 08 11:31:07 2007

Environment Info	
Test executed on machine:	NBOSC38
Test executed by user:	rsanders
Used OS version:	Windows 2000 / Windows XP
Used Rhapsody version:	Aries, build 805506
Used TestConductor version:	2.0, build 548

Tested Project	
Project:	CashRegister
Active Component:	TCon_CashRegister_0
Active Configuration:	DefaultConfig

Test Package: TPkg_CashRegister_0	Summary: FAILED
Containing Packages:	
Containing Test Contexts:	
TCon_CashRegister	FAILED

Assertion based testing mode

Starting from Rhapsody 7.6, TestConductor supports so-called assertion based testing. Before Rhapsody 7.6, TestConductor only supports so-called animation based testing. In animation based testing, the scheduling and arbitration, i.e., the way TestConductor decides whether a test case is passed or failed, is based on animation messages coming from Rhapsody's animation feature. In contrast to this, in assertion based testing, both scheduling and arbitration of test cases is directly controlled by assertions that are compiled into the test executable, i.e., scheduling and arbitration of test cases is independent from Rhapsody's animation feature. In general, both animation based testing and assertion based testing provide the same set of features, however, there are still some differences because of the underlying testing approach. In this section, we highlight the characteristics of assertion based testing.

Choosing between testing modes


By default, new projects created with Rhapsody 7.6 are created with testing mode set to assertion based testing, i.e., the property "TestConductor.Settings.TestingMode" is set to "AssertionBased". For test packages that have been created with a Rhapsody version older than 7.6 this property is set to "AnimationBased", i.e., for those test packages TestConductor behaves as in 7.5.3. If you want to switch from one testing mode to another testing mode manually, please open the TestConductor main dialog by choosing "TestConductor" from the tools menu. In the upcoming dialog, select the testing mode you want TestConductor to operate:



Test architecture creation

When creating a test architecture in assertion based testing mode, the created test architecture is similar to the architecture created in animation based testing mode. However, there are some differences:


1. The created test package contains two sub test packages, one architecture sub package that actually contains the test context and the test components that are connected to the SUT, and a control test package that contains an auto generated scheduler test component and the auto generated arbiter test components that control the test execution in assertion based testing mode.



2. Inside the top level test package, two static objects are defined. One object is an instance of the created test context, and one object is an instance of the created scheduler. Since the top level package is part of the scope of the testing configuration that is used to generate and build code for the test executable, always a test context instance and a scheduler instance is defined in the test executable.
3. The configuration that is created inside the top level test package is used in order to generate and build the code of the test executable. It is stereotyped with `<<TestingConfiguration>>`. A configuration that contains this stereotype provides several tags that can be used to define several testing options.

Test scheduling with <<Scheduler>> test components


As described in the previous section, when creating a test architecture, a scheduler test component is generated that is used to control the starting and stopping of test cases. The scheduler is part of the test executable. By, default, the behavior of the scheduler is defined by the following statechart:



By default, the scheduler parses the command line when the test executable is started. Based on the specified test cases that shall be executed, the scheduler starts the selected test case(s). This default behavior can be adjusted according to your needs. For instance, if you want to e.g. add an automatic timeout mechanism for all test cases you can adjust the behavior of the scheduler as it is described in section 0.


Test arbitration with <<Arbiter>> test components

If you define the behavior of a test case by using a sequence diagram, in assertion based testing TestConductor automatically adds a so-called arbiter test component to the control sub package of your test architecture. An arbiter is a test component that contains the stereotype <<Arbiter>>. Besides the arbiter class, TestConductor also adds an instance of the arbiter class to the test context that contains the test case. During runtime, this instance is used to control the test case execution of the test case to which the arbiter belongs. The test case and its arbiter are connected by a dependency that contains the stereotype <<ControlArbiter>>:



Creating test executables with testing configurations

In order to execute test cases in assertion based testing mode, always a test executable is needed that actually contains the code for the test architecture, the scheduler and all arbiters. In order to generate the code, a Rhapsody code generation configuration is created that contains the stereotype `<<TestingConfiguration>>`. In contrast to animation based testing mode, in assertion based testing mode, the test executable always contains all the code that is necessary in order to execute test cases of the test context that belongs to the testing configuration. In particular, in assertion based testing it is not necessary any more to have animation turned on for the testing configuration. Both animated and non-animated configurations can be executed the same way. The stereotype `<<TestingConfiguration>>` contains several tags that can be used in order to control how the test executable is created, and which test execution options should be applied when executing test cases using that configuration:



- **CodeCoverageOptionsFileName**

In this tag a filename of a code coverage options filename can be specified. In the options file, one can specify compiler specific options for controlling the source code annotation tools that annotate the code of the SUT in order to compute code coverage achieved by the executed test cases.

- **ComputeCodeCoverage:**

If this option is turned on, when executing test cases TestConductor computes which parts of the code generated for the SUT are covered to what extent. TestConductor computes statement coverage, decision coverage, decision/condition coverage and modified condition/decision coverage (MC/DC). Which parts of the SUT are considered for code coverage can be controlled by the tag “CoverageKind”. **Note:** Code coverage is restricted to C and C++.

Default: false

- **ComputeModelCoverage:**

If this option is turned on, when executing test cases TestConductor computes which model elements of the SUT are covered. TestConductor computes which states, transitions and operations are executed by the test cases. Which parts of the SUT are considered for code coverage can be controlled by the tag “CoverageKind”. **Note:** Model coverage is restricted to animated configurations.

(Default: false)

- **CoverageKind :**

This tag controls which parts of the test architecture is considered by model coverage and code coverage. The possible values are

- **SUT_flat:** Only the SUT itself is considered.
- **SUT_hierarchical:** The SUT and its parts are considered.
- **TestContext_flat:** The SUT and all TestComponents are considered.
- **TestContext_hierarchical:** The SUT and its parts, and all TestComponents with all their parts are considered.

(Default: SUT_flat)

- **PopulateCompileCommandForCodeCoverage :**

If this option is turned on, the property “<lang>.<Env>.CCompileCommand” is automatically populated by TestConductor in order to call the code instrumentation tools of TestConductor that are needed when computing code coverage of test cases. If there are problems with the automatic population of this property, please turn off this option and adjust the property “<lang>.<Env>.CCompileCommand” manually.

(Default: true)

- **PopulateInvokeExecutableProperty:**

If this option is turned on, when executing test cases from within Rhapsody, TestConductor automatically overwrites the property

“<lang>.<Env>.InvokeExecutable” with the content of the tag
“rtc_testexecution_script_filename”.

(Default: true)

- **RTC_MAX_ASSERT :**

The value of this tag defines how much memory TestConductor reserves for storing the results of executed assertions. The memory for storing the results of assertions is always defined statically in order to allow test execution on targets that don't support dynamic memory allocation. If during test execution the assertion memory exceeds its limits, TestConductor stops test execution and logs an error message.

(Default: 200)

- **ResultVerification:**

Test cases can be defined by either sequence diagrams, flowcharts, statecharts or plain code. Based on the behavior specification of the test case, TestConductor populates the model with operations and statecharts that implement the behavior of the test case as specified e.g. by a sequence diagram. After model population, TestConductor uses Rhapsody's code generator in order to generate code from the populated model. Now, if Rhapsody's code generator contains an error, a test case execution could yield the wrong result since TestConductor has used Rhapsody's code generator to generate the testing code. In order to prevent such situations, TestConductor can perform a so-called result verification. Result Verification is a technique that checks the consistency of a test execution with the test case behavior specification in Rhapsody. If result verification is turned on, TestConductor will detect potential errors in Rhapsody's code generator, thus making sure that the test case result TestConductor computes is correct even if code generation errors occurred in the testing code.

(Default: true)

- **rtc_adapter_content:**

This tag allows for defining adapter code, that can be used to realize the transfer of results from the target to the host. For example, a target debugger script can be provided in this tag, that reads out the assertion array and dumps the content of the array to a file on the host.

(Default: empty)

- **rtc_adapter_filename:**

If tag rtc_adapter_content is not empty, then rtc_adapter_content is written to the denoted file for use in e.g. a target debugger.

(Default: \$CONFIGDIR/rtcadapt.txt)

- **rtc_assert_dumptofile:**

If turned on, then the contents of the assertion array will be dumped to the file denoted by tag `rtc_assert_resultfilename`.

The tag must be turned off if the target does not support files.

(Default: true)

- **rtc_assert_dumptofile_kind:**

This tag controls when the collected assertions are dumped into the result file. Possible values are

1. **at_exit:** assertions are dumped when the test executable exits.
2. **after_testcase:** assertions are dumped after one test case execution.
3. **Immediately:** assertions are dumped immediately when they are executed.

(Default: at_exit)

- **rtc_assert_mem_code:**

This tag allows for customization of the `rtc_assert_id` function. Function `'void rtc_assert_id(int e, int ln, int nr)'` is defined in `TestConductor_C.c` (for C) and `TestConductor.h` (for C++), respectively. If **rtc_assert_mem_code** is empty, the original implementation as provided by `TestConductor` is used.

The function takes 3 arguments:

- `int e` : the value of the assertion expression
- `int ln` : the linenumber of the assertion in the source code
- `int nr` : the number of the implementation file according to a `TestConductor`-internal numbering of generated files.

`TestConductor` expects a result file on the host with the following syntax:

```

Lines ::=      ε
                | Lines Line

Line ::=      ASSERTION = nr,ln,e

```

Where ϵ means the empty word, `'ASSERTION'`, `'='`, and `'.'` are token and `nr`, `ln`, `e` are integer values according to the arguments of `rtc_assert_id`. (in reversed order).

For simplicity, arbitrary text lines not starting with `'ASSERTION'` may be contained in the result file but are ignored.

Using **rtc_assert_mem_code**, the implementation of `rtc_assert_id` can be customized in any way that produces a result file in correct syntax on the host, e.g. sending the values via serial connection to a serial port server application on the host that creates the result file.

(Default: empty)

- **rtc_exit_kind:**

This tag controls how the test executable shall be exited. Possible values are:

- i. `by_system_exit`: The test executable exits by calling “exit”.
- ii. `User_defined`: The test executable exits by executing the content of the tag “`rtc_exit_user_definition`”.

(Default: `by_system_exit`)

- **rtc_exit_user_definition:**

In this tag you can specify a code sequence that shall be executed when the test executable exits. This can be useful e.g. for targets that need a special way for correctly terminating executables.

(Default: empty)

- **rtc_info_filename:**

This tag specifies the name of the so-called info file that is used by TestConductor in order to generate some test case related information into a file, e.g. name and id of test cases. The info file is used by the reporting tool `repgen` in order to generate execution reports.

(Default: `$CONFIGDIR/rtcinfo.txt`)

- **rtc_log_autogenerate**

If this tag is turned on, TestConductor automatically adds log messages to the test executable. The log messages give information e.g. which test case is currently executed. Based on the value of the tag “`rtc_log_kind`”, the generated log messages are either printed to the console or to a log file or both.

(Default: `true`)

- **rtc_log_filename**

This tag specifies the name of the log file that can be generated by the test executable. If the file is generated or not during test execution depends on the value of the tag “`rtc_log_kind`”.

(Default: `$CONFIGDIR/rtclog.txt`)

- **rtc_log_kind**

This tag specifies how log messages should be treated inside the test executable. The possible values are

- `to_console`: log messages are printed to the console

- **to_file:** log messages are printed to the file specified in the tag “rtc_log_filename”.
- **to_console_and_file:** log messages are printed to the console and are logged into the file specified in the tag “rtc_log_filename”
- **user_defined:** when log messages are executed, the code entered in the tag “rtc_log_user_definition” is executed.

(Default: to_console)

- **rtc_log_user_definition:**

In this tag you can specify a code sequence that is executed in the test executable when a log message is specified. The specified code sequence will be executed if the value of the tag “rtc_log_kind” is set to “user_defined”.

(Default: empty)

- **rtc_report_dir**

This tag specifies to which directory TestConductor generates the execution reports after test case execution.

(Default: \$CONFIGDIR)

- **rtc_result_filename:**

This tag denotes the file from which TestConductor will read the result of test case execution. If tag **rtc_assert_dumptofile** is set to true, then the results will automatically be written into this file.

(Default: \$CONFIGDIR/rtcresult.txt)

- **rtc_result_handling:**

This tag specifies how test execution results are treated in the test executable. Possible values are

- **automatic:** if set to automatic, TestConductor automatically reads in test results after test execution.
- **Manual:** if set to manual, TestConductor does not automatically reads in test results after test case execution.

- **rtc_testexecution_script_content**

This tag specifies the content of the script file that is used by TestConductor to call the test executable. The tag contains the options for the test executable that e.g. are used to select the test case that shall be executed.

(Default: "\$executable" -resultfile "\$rtc_resultfile" -logfile "\$rtc_logfile" -tcontext \$tcontext -tcase \$tcase)

- **rtc_testexecution_script_filename**

This tag specifies the name of the script file that is used in order to call the test executable.

(Default: \$CONFIGDIR/tc_run.bat)

- **rtc_testexecution_script_populate**

This tag specifies whether the content of the file specified in the tag “rtc_testexecution_script_filename” is populated with the content specified in the tag “rtc_testexecution_script_content”.

(Default: true)

- **rtc_testreport_script_content_tcase**

This tag specifies the content of the script file that is used by TestConductor to generate html execution reports for test cases from the test results computed by the test executable. The tag contains the options for the repgen tool that are used in order to generate the html reports for test cases.

(Default: "\$RTCINSTALLDIR/repgen" -infofile "\$infofile" -resultfile "\$resultfile" -outdirectory "\$RTCREFDIR" -tcontext \$fulltcontext -tcase \$fulltcase)

- **rtc_testreport_script_content_tcontext**

This tag specifies the content of the script file that is used by TestConductor to generate html execution reports for test contexts from the test results computed by the test executable. The tag contains the options for the repgen tool that are used in order to generate the html reports for test contexts..

(Default: "\$RTCINSTALLDIR/repgen" -infofile "\$infofile" -resultfile "\$resultfile" -outdirectory "\$RTCREFDIR" -tcontext \$fulltcontext)

- **rtc_testreport_script_filename**

This tag specifies the name of the script file that is used by TestConductor in order to generate html reports based on the execution results computed by the test executable.

(Default: \$CONFIGDIR/tc_rep.bat)

- **rtc_testreport_script_populate**

If this tag is turned on, the content of the file specified in the tag “rtc_testreport_script_filename” is populated with the content of the tag “rtc_testreport_script_content_tcase”, if a test case is executed, and with the content of the tag “rtc_testreport_script_content_tcontext”, if a test context is executed.

(Default: true)

Executing test cases in assertion based testing

After the test executable has been built, either individual test cases or complete test contexts can be executed. The execution is invoked the same way as for animation based testing. When invoking a test case from within Rhapsody, TestConductor calls the script specified in the tag “rtc_testexecution_script_filename” that actually calls the test executable with the parameters that select the test case that shall be executed. The chosen test case is executed, and after termination the results are dumped into the result file specified in the tag “rtc_result_filename”. However, this result file only contains the raw results, i.e., the outcome of the assertions that have been executed during test execution. In order to generate a complete test execution report based on these raw results, TestConductor uses the tool “repgen”. After test execution, when the raw results have been computed by the test executable, TestConductor calls the script that is specified in the tag “rtc_testreport_script_filename”. This script actually calls repgen with the correct parameters in order to generate both an xml report and an html report that shows the detailed test results. The generated xml report is only used internally by TestConductor in order to present the execution results in the test execution GUI when working with Rhapsody. In summary, in assertion based testing, test execution and test reporting is a process separated into 2 steps:

- test cases are executed by calling the test executable with the correct parameters. The test executable computes raw test results.
- Based on the raw test results, a call of the repgen tool with the correct parameters generates readable html reports based on these raw results.

Both of these steps can either be done from within Rhapsody (the same way as for animation based testing) or outside of Rhapsody.

Performing result verification for test case execution

When operating in assertion based testing mode, TestConductor provides the option to perform a so-called result verification after test case execution. This feature is turned on if the tag “ResultVerification” of the testing configuration is turned on. When result verification is turned on, after test case execution TestConductor checks if the raw results written to the result file by the test executable is consistent with the graphical behavior description in Rhapsody (either as sequence diagram, statechart, or flowchart). For a behavior description provided as plain code no result verification is performed. For graphical behavior description provided as a sequence diagram, TestConductor populates the model with a statechart that represents the possible allowed execution sequences specified in the sequence diagram. The result verification check made by TestConductor is independent from Rhapsody’s code generator, and can be used in order to detect defects of Rhapsody’s code generator that may influence the test case execution results. By using result verification, TestConductor makes sure that the test execution results computed by TestConductor are ALWAYS correct, even in case of errors in Rhapsody’s code generator that may affect the correctness of the testing source code that is used to build the test executable. The result verification is able to detect e.g. the following potential code generation problems that may influence the test execution result:

- The code generator wrongly ignores transitions or states in a statechart
- The code generator wrongly takes additional transitions in a statechart

- The code generator fires statechart transitions in wrong order
- The code generator wrongly ignores transitions or actions in a flowchart
- The code generator wrongly takes additional transitions in a flowcharts
- The code generator fires flowchart transitions in wrong order

When result verification is turned on (by default), the generated html test execution result always contains the information if result verification was enabled or not, and if it was successful or not. In case result verification was enabled and it was not successful, the test case status is automatically set to “Error”.

TestCase Result

TestCase: SD_with_alt

Friday, May 13, 2011 09:00:51

Environment Information	
Test executed on machine:	TSV
Test executed by user:	User
Used operating system version:	Windows 2000 / Windows XP
Used Rhapsody version:	7.6, build 2063218
Used TestConductor version:	2.4.4, build 2481

Tested Project	
Project:	CModelCodeCoverage
Active Code Generation Component:	TPkg_Calc_Comp
Active Code Generation Configuration:	CodeCoverageConfig

SequenceDiagram used in TestCase	
TPkg_Calc::TCon_Calc_Architecture::TCon_Calc.SD_with_alt::SDTestScenario_0	

Results	Summary: PASSED
SDInstance 'SD_tc_0'	
Status:	PASSED
Progress:	100% (7/7)


Result Verification	
Result verification successful	

Computing Model Coverage during Test Execution


When executing TestCases, i.e., either individual TestCases, a TestContext or a TestPackage, TestConductor provides the possibility to compute which model parts of the SUT are executed during the execution of the TestCases. This information is provided by an HTML report that is created and added to the model after the execution of the test cases. The report contains information about accumulated coverage of states, transitions, events and operations (except constructors and destructors) of all SUT classes used in the TestArchitecture.

Computing Model Coverage for single Test Cases

For animation based testing (TestConductor.Settings.TestingMode == AnimationBased), to compute the model coverage of single test cases, switch on the property “TestConductor.TestCase.ComputeCoverage”:



For assertion based testing, switch on tag “ComputeModelCoverage” of the testing configuration:



Now, each time you execute the test case, in addition to the test case execution report, TestConductor creates a model coverage report and adds it to the model:



Coverage Summary	
TestPackage:	TPkg_CashRegister
TestContext:	TCon_CashRegister
TestCase:	SD_tc_0

Detailed Coverage Summary of CashRegister (6/25)		
Operations		
not covered	identifyProduct	
not covered	addProduct	
covered	startSession	
not covered	endSession	
not covered	generateTicket	
not covered	isNoMoreProducts	
not covered	removeLastProduct	
not covered	countProducts	
EventReceptions		
covered	evStart	
not covered	evBarcode	
not covered	evEnd	
not covered	evRemove	
not covered	evKey	
not covered	evCode	
Statechart: StatechartOfCashRegister		
covered	ROOT.idle	State
covered	ROOT.active	State
covered	0	Transition
not covered	2	Transition
not covered	6	Transition
covered	1	Transition
not covered	3	Transition
not covered	5	Transition
not covered	7	Transition
not covered	8	Transition
not covered	4	Transition


Choosing the Coverage Kind for Model Coverage

TestConductor supports four different kinds of coverage measures, which can be chosen using property `TestConductor.TestCase.CoverageKind` (if `TestConductor.Settings.TestingMode == AnimationBased`) or tag “CoverageKind” of the testing configuration (if `TestConductor.Settings.TestingMode == AssertionBased`)

- ◆ SUT flat (Default): Only coverage of the toplevel class of the SUT is measured, i.e. states, transitions, and operations of parts of the SUT are not considered. Coverage of model elements of test components is also not measured.
- ◆ SUT hierachical : Coverage of the SUT is measured in a hierarchical manner, i.e. also states, transitions, and operations of parts of the SUT are hierarchically


regarded for coverage measure. Coverage of model elements of test components is again not measured.

- ◆ TestContext flat : Coverage is measured in terms of all states, transitions, and operations defined at the first decomposition level of the test context, i.e. all states, transitions, and operations of the direct parts of the test context are considered.
- ◆ TestContext hierarchical : all states, transitions, and operations in the hierarchal structure of the test context are considered in coverage measure.




Computing cumulative Model Coverage for TestContexts

To compute the model coverage for TestContexts, for at least one of the TestCases of the TestContext the property “TestConductor.TestCase.ComputeCoverage” must be switched on (if TestConductor.Settings.TestingMode == AnimationBased) or the tag “ComputeModelCoverage” (if TestConductor.Settings.TestingMode == AssertionBased) must be turned on. However, if the property is switched on for more than one test case of the TestContext, TestConductor computes the cumulative coverage of all executed test cases that have switched on this property and stores the result as a coverage report underneath the TestContext. In order to compute the cumulative coverage of all test cases of a TestContext this property has to be switched on for all test cases belonging to the TestContext. A simple way to do it is to set the property directly for the TestPackage that contains the TestContext:



Now, when executing the complete TestContext, a coverage report is generated for each of the contained test cases, and a cumulative coverage report is generated for the TestContext:




Computing cumulative Model Coverage for TestPackages

Analogously to computing the cumulative coverage of TestContexts, TestConductor also provides the possibility to compute the cumulative coverage of TestPackages. To compute

the model coverage for TestPackages, for at least one of the TestCases of the TestPackage the property “TestConductor.TestCase.ComputeCoverage” must be switched on. However, if the property is switched on for more than one test case of the TestPackage, TestConductor computes the cumulative coverage of all executed test cases that have switched on this property and stores the result as a coverage report underneath the TestPackage. In order to compute the cumulative coverage of all test cases of a TestPackage this property has to be switched on for all test cases belonging to the TestPackage. A simple way to do it is to set the property directly for the TestPackage for which the cumulative coverage shall be computed.

Computing Code Coverage (only assertion based testing mode)

Besides computing model coverage of test cases, TestConductor can also compute the achieved code coverage of test cases (for C and C++ only). In order to turn on code coverage, the tag “ComputeCodeCoverage” of the testing configuration must be turned on:



If this option is turned on, when building test cases TestConductor instruments the test executable s.t. during test execution code coverage information is computed. After test case execution, the computed results are added as an html report to the model. The result report both contains summary information (e.g. percentage of statement coverage, decision/condition coverage, modified condition/decision coverage (MC/DC)) as well as detailed information about each source line.

Similar to model coverage, four different kinds of coverage measures are supported and can be chosen by setting the tag “CoverageKind” of the testing configuration. For details, see previous section “Choosing the Coverage Kind for Model Coverage”.

Additional options for code coverage can be specified using an xml file. The location of the file has to be entered in the tag “CodeCoverageOptionsFileName” of the testing configuration. Supported for this tag is the full path of the options file or a path relative to the folder with the generated code (location of the Makefile).

The options file can be used to

- ⤴ Define additional files which shall be instrumented for code coverage (Note: Supported are only files generated for model elements)
- ⤴ Specify include paths
- ⤴ Specify defined macros
- ⤴ Specify details of the used compiler and compile environment

A template of the options file showing the supported options is located in the TestConductor installation folder: File “TCCodeAnnotationOptions.xml”.


The screenshot shows a Mozilla Firefox browser window titled "Analysis Report - Mozilla Firefox". The address bar shows a file path: `file:///C:/qa_Libra/newsamples/check/CModelCodeCoverage/TCon`. The page content includes a navigation bar with links: "Environment Info", "Table Of Contents", "Global Statistics", and "Source Code". Below this is a section titled "Global Statistics" with a "Quick Links" list and a "Coverage Statistics" table.

Quick Links

- Coverage Statistics
- Coverage Item Statistics
 - Statement, Decision, Condition
 - C/DC and MC/DC, Function, Switch-Case
 - Relational Operator, Down Cast, Division By Zero
- Coverage Entity Statistics

Coverage Statistics

	Goals	Covered	
Statement Coverage	45	27	60%
Decision Coverage	10	4	40%
Condition Coverage	0	0	n.a.
Condition/Decision Coverage	21	10	47.6%
Modified Condition/Decision Coverage	21	10	47.6%



For an example that shows how to use code coverage for C, please try sample “CModelCodeCoverage” in the folder
 <samples/csamples/TestConductor/CmodelCodeCoverage>.


For an example that shows how to use code coverage for C++, please try sample “CppModelCodeCoverage” in the folder
 <samples/csamples/TestConductor/CppmodelCodeCoverage>.

Restrictions regarding applicability of code coverage computation can be found in the document <doc/pdf_docs/CodeCoverage_Limitations.pdf>.

Computing Code Coverage, Memory Profiling, and Performance Profiling with Rational TestRealTime during Test Execution

When executing TestCases, either individual TestCases or a TestContext, TestConductor provides the possibility to apply functionality of the tool Rational TestRealTime (TestRT) during the execution of the TestCases with TestConductor. The result information computed by TestRealTime is provided by a specific controlled file that is added to the model after the execution of the test cases. When double-clicking that file, TestRealTime opens and shows the results computed during TestCase execution, for instance code coverage, memory profiling, or performance profiling information.

The integration of TestConductor with TestRT is realized using a set of stereotypes. These stereotypes are defined in subpackage RTC::TestArchitecture::TestRT of the TestingProfile.



Stereotype *TestRealTime* can be applied on configurations and provides a set of tags that can be used to control the kind of instrumentation that shall be performed on that configuration when using the tool “Rational TestRealTime” together with TestConductor. See also section [Rational TestRealTime](#).

Stereotype *TestRealTimeFile* is used to denote TestRealTime data files that are added to the model by TestConductor. This data files are needed in order to have all TestRealTime results maintained as part of the model.

Stereotype *TestRealTimeResult* denotes the result data that is added by TestConductor to the model after a TestCase execution or a TestContext execution of a configuration that with stereotype *TestRealTime*.

The *TestArchitecture* package contains the types:


- ◆ *RTRT_CoverageBlockDefinition_Type*
- ◆ *RTRT_CoverageCondition_Type*
- ◆ *RTRT_CoverageProc_Type*
- ◆ *RTRT_Target_Type*

These four types are used for the integration between TestConductor and TestRealTime. Users do not have to care about the precise definition of these types.

Applying Rational TestRealTime during Test Execution


In order to apply TestRealTime on TestCases and TestContexts, you have to do the following steps:

1. Set the stereotype <<TestRealTime>> to the TestConfiguration of the TestContext on which TestRealTime should be applied:



The stereotype <<TestRealTime>> is part of the Rhapsody UML Testing Profile.

2. Select the TestRT options you want to apply during TestCase execution. In order to do this, switch to the "Tags" tab of the configuration features dialog. The following tags can be used to select the TestRT options that should be applied during TestCase execution:



- **InstrumentedFiles:**

In this setting the files (separated by commas) which are to be instrumented by Rational TestRealTime are specified. Per default the setting is filled automatically by TestConductor (choosing the files belonging to the SUT objects). However, the user can manually specify the list of files, if the setting "InstrumentedFilesAutoset" is turned off.

- **InstrumentedFilesAutoset:**

If this setting is turned on, the setting "InstrumentedFiles" will be filled by TestConductor automatically (default). If the setting is turned off, it is in the user's responsibility to manually fill the setting "InstrumentedFiles".

- **InvokeMakeFileAutoset**

If this setting is turned off, the property "<lang>.<compile_env>.InvokeMakefile" is no longer modified by TestConductor, and no settings specified here are passed to the Rational Test RealTime instrumentation. The user has to manually specify all settings in the property "<lang>.<compile_env>.InvokeMakefile". This setting allows the user to work with targets not yet supported by TestConductor out-of-the-box by using user-defined makefiles or invoke.makefile-scripts.

- **RTRT_CoverageBlockDefinition**

With these settings the user can influence whether and with which parameters the 'BLOCK' option is used in the Rational Test RealTime instrumentation. The 'BLOCK' option only instruments simple blocks. Use the 'IMPLICIT' or 'DECISION' (these are equivalent) option to instrument implicit blocks (unwritten else instructions), as well as simple blocks. Use the 'LOGICAL' parameter to instrument logical blocks (loops), as well as the simple and implicit blocks. For detailed information about this TestRT command and the parameters see the Rational Test RealTime documentation.

- **RTRT_CoverageCall**

With these settings the user can influence whether the 'CALL' command is used in the Rational Test RealTime instrumentation (to instrument function calls). For detailed information about this command and the parameters see the Rational Test RealTime documentation.

- **RTRT_CoverageCondition**

With these settings the user can influence whether and with which parameters the 'COND' command is used in the Rational Test RealTime instrumentation. If 'COND' is used without parameters, the TestRT Instrumentor instruments basic conditions. The parameter values 'MODIFIED' or 'COMPOUND' are equivalent settings that allow measuring the modified and compound conditions. The parameter value 'FORCEEVALUATION' instruments forced conditions. For detailed information about this command and the parameters see the Rational Test RealTime documentation.

- **RTRT_CoverageProc**

With these settings the user can influence whether and with which parameters the 'PROC' command is used in the Rational Test RealTime instrumentation. If 'PROC' is used without parameters (default setting), then procedure inputs (functions) are instrumented. When set to 'RET', then procedure inputs, outputs, and terminal instructions are instrumented. For detailed information about this command and the parameters see the Rational Test RealTime documentation.

- **RTRT_MemoryProfiling**

If this setting is turned on, it activates instrumentation for the Memory Profiling analysis feature of Rational TestRealTime. For detailed information about this TestRT feature see the Rational Test RealTime documentation.

- **RTRT_PerformanceProfiling**

If this setting is turned on, it activates instrumentation for the Performance Profiling analysis feature of Rational TestRealTime. For detailed information about this TestRT feature see the Rational Test RealTime documentation.

- **RTRT_Target**

This setting specifies the Test Realtime target deployment port. Currently supported out-of-the-box by TestConductor are 'cvisual6' and 'cvisual8'.

- **RTRT_Trace**

If this setting is turned on, it activates instrumentation for the Runtime Tracing analysis feature of Rational TestRealTime. For detailed information about this TestRT feature see the Rational Test RealTime documentation.

- **RTRT_UseUserOptions**

If this setting is turned on, the contents of setting "UserOptions" are used as instrumentation options by TestRT. All other instrumentation settings (including "InstrumentedFiles") above are ignored


- **RTRT_UserOptions**


User-defined Options which will be used for the instrumentation by TestRT.

Note: if you do not manually set any of the above listed settings, then TestConductor will control TestRT with the default settings.


Applying TestRealTime on single Test Cases

After you have set the stereotype <<TestRealTime>> to the configuration that shall be executed, and after you have selected the TestRT options in the “Tags” tab, you are now ready to execute a single TestCase. In order to do this, simply select the TestCase and select “Execute TestCase”. TestConductor detects that you want to execute a <<TestRealTime>> configuration which requires TestRealTime specific instrumentation. TestConductor asks if it should update the configuration properties such that the required TestRealTime instrumentation will be performed. Select “OK” in order to set the configuration properties correctly, and to rebuild the application with the right configuration properties:






Note: You can perform an explicit update of the configuration properties according to the TestRealTime settings in the “Tags” tab of the configuration by selecting “Update TestCase” or “Update TestContext”. When TestConductor has updated the configuration properties, and after rebuilding the application, the TestCase execution starts. When the TestCase execution has finished, e.g. after executing and closing the execution dialog of a sequence diagram TestCase, the computed TestRealTime results are automatically added to the model. The results are denoted as <<TestRealTimeResult>> elements in the browser. When double-clicking this element, TestRealTime opens and shows the computed results:





In addition to the *TestRealTimeResult* elements in the browser, TestConductor also adds several controlled files to the model that are stereotyped with the stereotype <<TestRealTimeFile>>. These files are necessary in order to maintain all TestRealTime results in a self-contained way as part of the model.

Applying TestRealTime on TestContexts

After you have set the stereotype <<TestRealTime>> to the configuration that shall be executed, and after you have selected the TestRT options in the “Tags” tab, you are now ready to execute a TestContext. In order to do this, simply select the TestContext you want to execute and select “Execute TestContext”. TestConductor detects that you want to execute a <<TestRealTime>> configuration which requires TestRealTime specific instrumentation. TestConductor asks if it should update the configuration properties such that the required TestRealTime instrumentation will be performed. Select “OK” in order to set the configuration properties correctly, and to rebuild the application with the right configuration properties:



Note: You can perform an explicit update of the configuration properties according to the TestRealTime settings in the “Tags” tab of the configuration by selecting “Update TestCase” or “Update TestContext”. When TestConductor has updated the configuration properties, and after rebuilding the application, the TestCase execution starts. After all TestCases of the selected TestContext have been executed, the TestRealTime results are automatically added to the model. The results are denoted as <<TestRealTimeResult>> elements in the browser. When double-clicking this element, TestRealTime opens and shows the computed results. Since all TestCases of the selected TestContext have been executed, the TestRealTimeResult contains the accumulated results of all executed TestCases, for instance if you have 3 TestCases tc1, tc2, tc3, then the TestRealTimeResult contains the accumulated results of tc1, tc2 and tc3:



In addition to the *TestRealTimeResult* element in the browser, TestConductor also adds several controlled files to the model that are stereotyped with the stereotype <<TestRealTimeFile>>. These files are necessary in order to maintain all TestRealTime results in a self-contained way as part of the model.

Integration with CUnit/CppUnit Framework

In the area of testing, CUnit and CppUnit frameworks have become de-facto standards in recent years. Many developers and companies have already organized their testing process using these frameworks. In order to ease migration to a model driven development approach, TestConductor offers a test integration for Rhapsody with the CUnit and CppUnit frameworks.

- ◆ CUnit integration has been developed and tested using CUnit-2.1-0.
- ◆ CppUnit integration has been developed and tested using cppunit-1.12.1.

This integration is realized using stereotypes defined in the TestingProfile. The stereotypes for CUnit integration are defined in subpackage RTC::TestArchitecture::CUnit, whereas the stereotypes for CppUnit integration are defined in subpackage RTC::TestArchitecture::CppUnit.

Stereotypes for CUnit integration

Stereotype *CUnitContext* can be applied to a class and sets some properties for CUnit testing integration. You can change a test context to CUnitContext – and vice versa - by right-clicking a test context and selecting “Change to > CUnitContext”.

Stereotype *CUnitConfig* can be applied to a configuration and provides a set of tags for customization of CUnit testing integration with Rhapsody. CUnitConfig overrides property CG.Configuration.StartFrameworkInMainThread, s.t. the Rhapsody framework is started in a new thread and control returns to the main thread. Right after starting the framework either a single test case is invoked or all test cases of the test context (only for CUnitContextExecutionKind == NoRestart).

“Update TestCase”, “Update TestContext”, and “Update TestPackage” with respect to a CUnitContext (referring to a configuration stereotyped <<CUnitConfig>>) will instrument the CUnitContext with a set of operations:

- ◆ **int cunit_init()**—CUnit requires an initialization and a cleanup function for each test suite. These functions are provided by TestConductor as prototypes, which can be used to add application or test specific code.
- ◆ **int cunit_clean()**--the test suite cleanup function.
- ◆ **void cunitmain(char* tc_name)**—the main function for CUnit testing. The function consists of :
 - a framework initialization part
 - a test suite specific part – i.e. a CUnitContext specific part
 - a testoutputter definition part
 - and a execution and result computation part – referred to as tail

Each of these parts can be customized using a tag of the <<CUnitConfig>> configuration.

- ◆ **<testcontext-type>* setTestContext(<testcontext-type>* context)**—Since test cases may not have arguments in the CUnit framework,, they can not be invoked with the ‘me’-pointer by the test context. Hence, a static variable is required, that allows access to the test context data structure within test cases. Test cases can get access to this data structure using the test context function ‘theTestContext()’. Function ‘setTestContext()’ sets a static pointer variable, which then can be returned by ‘theTestContext()’.
- ◆ **<testcontext-type>* theTestContext()**— see above.
- ◆ **Init()**—initializer that, in particular, invokes ‘setTestContext()’ with the ‘me’-pointer in order to enable access to the test context data structure from within test cases (see above).

The customization tags of stereotype CUnitConfig are:

- ◆ **CUnitContextExecutionKind**-- Possible values: ‘RestartExecutable’, ‘NoRestart’. This tag defines whether the application is restarted for each testcase, or all test cases are executed within a single invocation of the application. Default is ‘RestartExecutable’.
- ◆ **CUnitIncludePath**—defines the path to the headers of the CUnit framework. For path definition, a symbolic variable \$CUNITINSTALLDIR can be used. This

symbolic variable is textually substituted by the contents of tag `CUnitInstallDir` upon “Update TestCase”, “Update TestContext”, and “Update TestPackage”, respectively. Default: “\$CUNITINSTALLDIR/CUnit/Headers”.

- ◆ **CUnitInstallDir**—the full path to the installation directory of the CUnit framework. For definition of the path, environment variables, e.g. “\$(CUNITHOME)” can be used. Default: “\$(CUNITHOME)”.
- ◆ **CUnitLibPath**—the full path to the CUnit framework library file. Default: “\$CUNITINSTALLDIR/CUnit/lib/CUnit.lib”.
- ◆ **CUnitMainInit**—the initialization part of the `cunitmain()` function that will be generated by “Update TestCase”, “Update TestContext”, and “Update TestPackage”, respectively. For the default, please consult the TestingProfile.
- ◆ **CUnitMainOutputter**—test outputter specific initializations. Default: “\$RTCAUTOGENERATE”. If `CUnitMainOutputter` contains exactly this string, `TestConductor` will automatically generate the respective code according to the chosen output format.
- ◆ **CUnitMainTail**—defines the execution and result computation part of ‘`cunitmain()`’. For the default, please consult the TestingProfile.
- ◆ **CUnitReportKind**—possible values: ‘xml’, ‘html’, ‘text’. This tag defines the result report format. Default: ‘html’
- ◆ **InvokeExecutable**—the content of this tag will be written to property `C.CG.Configuration.<activeEnvironment>` and defines how the application will be invoked. Default: “\$executable \$TestCase”, where “\$TestCase” will be textually substituted by the “Update ...” functionality with the name of the selected test case or “all”, if a test context is going to be executed.
- ◆ **PostFrameworkThreadSegment**—the contents of this tag will be written to property `CG.Configuration.PostFrameworkThreadSegment`. Using this tag it can be customized how ‘`cunitmain()`’ will be invoked. Default: “char* tname = argv[1]; `cunitmain(tname);`”
- ◆ **ReportFilename**—the filename prefix of the report generated by CUnit. Default: “\$CONFIGDIR/report”, where “\$CONFIGDIR” is a symbolic variable denoting the code generation configuration referred to by the test context. “\$CONFIGDIR” will be textually replaced by the “Update ...” functionality.
- ◆ **ResultFilename**—the filename for the overall ‘pass/fail’ result. A CUnit test case execution passes, iff all executed assertions pass; a CUnitContext execution passes, iff all test cases pass; a TestPackage passes, iff all CUnitContexts pass. Default: “\$CONFIGDIR/result.txt”
- ◆ **XSLTFile**—full path to the xslt file using which a html report can be generated from a CUnit xml report. Default: “\$CUNITINSTALLDIR/Share/CUnit-Run.xsl”

Stereotypes for CppUnit integration

Stereotype *CppUnitContext* can be applied to a class and sets some properties for CppUnit testing integration. You can change a test context to CppUnitContext – and vice versa - by right-clicking a test context and selecting “Change to > CppUnitContext”.

Stereotype *CppUnitConfig* can be applied to a configuration and provides a set of tags for customization of CppUnit testing integration with Rhapsody. CppUnitConfig overrides property CG.Configuration.StartFrameworkInMainThread, s.t. the Rhapsody framework is started in a new thread and control returns to the main thread. Right after starting the framework either a single test case is invoked or all test cases of the test context (only for CppUnitContextExecutionKind == NoRestart).

“Update TestCase”, “Update TestContext”, and “Update TestPackage” with respect to a CppUnitContext (referring to a configuration stereotyped <<CppUnitConfig>>) will instrument the CppUnitContext with a set of operations:

- ◆ **void setUp()**—CppUnit requires an initialization and a cleanup function for each test case/test suite. These functions are provided by TestConductor as prototypes, which can be used to add application or test specific code.
- ◆ **void tearDown()**--the test suite cleanup function.
- ◆ **void cppunitmain(char* tc_name)**—the main function for CppUnit testing. The function consists of :
 - a framework initialization part
 - a test suite specific part – i.e. a CppUnitContext specific part
 - a testoutputter definition part
 - and a execution and result computation part – referred to as tail

Each of these parts can be customized using a tag of the <<CUnitConfig>> configuration.

The customization tags of stereotype CppUnitConfig are:

- ◆ **CppUnitContextExecutionKind**-- Possible values: ‘RestartExecutable’, ‘NoRestart’. This tag defines whether the application is restarted for each testcase, or all test cases are executed within a single invocation of the application. Default is ‘RestartExecutable’.
- ◆ **CppUnitIncludePath**—defines the path to the headers of the CppUnit framework. For path definition, a symbolic variable \$CPPUNITINSTALLDIR can be used. This symbolic variable is textually substituted by the contents of tag CppUnitInstallDir upon “Update TestCase”, “Update TestContext”, and “Update TestPackage”, respectively. Default: “\$CPPUNITINSTALLDIR/include”.
- ◆ **CppUnitInstallDir**—the full path to the installation directory of the CppUnit framework. For definition of the path, environment variables, e.g. “\$(CPPUNITHOME)” can be used . Default: “\$(CPPUNITHOME)”.
- ◆ **CppUnitLibPath**—the full path to the CppUnit framework library file. Default: “\$CPPUNITINSTALLDIR/lib/CppUnit.lib”.
- ◆ **CppUnitMainInit**— the initialization part of the cppunitmain() function that will be generated by “Update TestCase”, “Update TestContext”, and “Update TestPackage”, respectively. For the default, please consult the TestingProfile.
- ◆ **CppUnitMainOutputter**— — test outputter specific initializations. Default: “\$RTCAUTOGENERATE”. If CUnitMainOutputter contains exactly this string, TestConductor will automatically generate the respective code according to the chosen output format.
- ◆ **CppUnitMainTail**— defines the execution and result computation part of ‘cppunitmain()’. For the default, please consult the TestingProfile.

- ◆ **CppUnitReportKind**—possible values: ‘xml’, ‘html’, ‘text’, ‘compilertext’. This tag defines the result report format. Default: ‘html’
- ◆ **InvokeExecutable**—the content of this tag will be written to property `CPP.CG.Configuration.<activeEnvironment>` and defines how the application will be invoked.
Default: “\$executable \$TestCase”, where “\$TestCase” will be textually substituted by the “Update ...” functionality with the name of the selected test case or “all”, if a test context is going to be executed.
- ◆ **PostFrameworkThreadSegment**— the contents of this tag will be written to property `CG.Configuration.PostFrameworkThreadSegment`. Using this tag it can be customized how ‘cunitmain()’ will be invoked.
Default: “p_ \$TestContext->cppunitmain(argv[1]);”, where the term “\$TestContext” will be textually substituted by TestConductor upon “Update ...”.
- ◆ **ReportFilename**— the filename prefix of the report generated by CppUnit.
Default: “\$CONFIGDIR/report”, where “\$CONFIGDIR” is a symbolic variable denoting the code generation configuration referred to by the test context. “\$CONFIGDIR” will be textually replaced by the “Update ...” functionality.
- ◆ **ResultFilename**— the filename for the overall ‘pass/fail’ result. A CppUnit test case execution passes, iff all executed assertions pass; a CppUnitContext execution passes, iff all test cases pass; a TestPackage passes, iff all CppUnitContexts pass.
Default : “\$CONFIGDIR/result.txt”
- ◆ **XSLTFile**--- full path to the xslt file using which a html report can be generated from a CppUnit xml report.
Default : “\$CPPUNITINSTALLDIR/contrib/xml-xsl/report.xsl”

Test Definition for CUnit/CppUnit

Code and flow chart test cases can be used very similar to their normal usage. Instead of the `RTC_ASSERT` macros, for CUnit and CppUnit, `CU_ASSERT` macros and `CPPUNIT_ASSERT` macros, respectively, are used.

For CUnit also statechart test cases can be used similarly to their normal usage with TestConductor, except for using `CU_ASSERT` macros instead of `RTC_ASSERT` macros.

For CppUnit, usage of statechart test cases requires some manual adaptations of the test context and the statechart defining the test. The necessary adaptations are explained below. We recommend using code and flow chart test cases also for testing reactive behavior (cf. Testing reactive behavior with Code Test Cases, Testing reactive behavior with Flow Chart Test Cases on page 46 pp.).

Both, CUnit integration as well as CppUnit integration do currently not support SD test cases.

Using Statechart Test Cases with CppUnit

In the CppUnit framework assertions like `CPPUNIT_ASSERT` are realized by throwing an exception, when an assertion fails. This exception is caught by the framework and the failed assertion is reported. The entire mechanism relies on the assumption that the test case is executed in the same thread as the framework. CppUnit integration with TestConductor utilizes a test context as test fixture, i.e. the CppUnit framework is executed in the thread of the CppUnitContext. Statechart test cases are realized using a separate test component owning the statechart, s.t. the statechart is executed in the thread of the test component. Since these threads are in general not the same, it is necessary to

catch exceptions within the statechart and add failures to the testresult maintained by the CppUnitContext.

Necessary modifications for statechart test cases with CppUnit:

1. Add public attributes

- ◆ CppUnit::TestSuite* suiteOfTests
- ◆ CppUnit::TestResult* theTestResult

to CppUnitContext

2. Overwrite tag CppUnitMainInit:

```
CPPUNIT_NS::TestResult testresult;
CPPUNIT_NS::TestResultCollector collectedresults;
testresult.addListener(&collectedresults);
std::ofstream outfile;

// Original: local variable
/* CppUnit::TestSuite *suiteOfTests = new
    CppUnit::TestSuite("$TestContext"); */

//NEW: use CppUnitContext attribute
this->suiteOfTests = new
    CppUnit::TestSuite("$TestContext");

CPPUNIT_NS::TestRunner *testrunner = new
CPPUNIT_NS::TestRunner();

//NEW: initialize attribute of CppUnitContext
theTestResult = &testresult;
```

3. add “cppunit/TestResult.h” to property CPP_CG.Class.ImpIncludes of test component referred to by <<StatechartTestCase>> dependency of statechart test case
4. Instead of simply using e.g.

```
CPPUNIT_ASSERT(
    itsTCon->getItsCalculator()->get_result_op()==42),
```

in a transition action, you now should write:

```
CPPUNIT_NS::Test* current_tcase = 0;
CppUnitVector<CPPUNIT_NS::Test*>& alltests =
    (CppUnitVector<CPPUNIT_NS::Test*>&)
    (itsTCon->suiteOfTests->getTests());
CppUnitVector<CPPUNIT_NS::Test*>::iterator it =
alltests.begin();
while (it != alltests.end()) {
    if ((*it)->getName()=="SC_tc_0") {
        current_tcase = *it;
    }
    ++it;
```

```

}
try {
    CPPUNIT_ASSERT(
        itsTCon->getItsCalculator()->get_result_op()==42);
}
catch (CPPUNIT_NS::Exception e) {
    itsTCon->getTheTestResult()->addFailure(
        current_tcase,
        new CPPUNIT_NS::Exception(e));
}

```

Command Line Execution

TestConductor can update, build, and execute test cases, test contexts or test packages from the command line. Command line execution can either be performed by using the command line feature of rhapsody.exe or by using rhapsodycl.exe.

Command Line Syntax for rhapsody.exe

You can use following syntax to execute tests from the command line:

- "<Rhapsody executable>" <model file> -cmd=call "rtc TC_COMMAND TC_ELEMENT" -cmd=save -cmd=exit
 where TC_COMMAND is one of the following testconductor commands
 - update_build_execute
 - performs an update, then a build, and then an execute on the specified test element.
 - update_build
 - performs a build, and then an execute on the specified test element.
 - update
 - performs an update on the specified test element.
 - build_execute
 - performs a build and then an execute on the specified test element
 - build
 - performs a build on the specified test element.
 - execute
 - performs an execute on the specified test element.
 - clean
 - performs a clean on the specified test element.

and TC_ELEMENT is either "all" or the full pathname of a test case, a test context or a test package.

Note: -cmd=save needs to be defined in order to permanently actualize the link to the HTML test result report (controlled file) and the Verdict tag under it. At this time

older test result files will not be overwritten, but a new file with an incremented number will be created. In case the model will not be saved before exiting, still the old or none result file will be referenced.

Examples:

- ◆ "<full Rhapsody path>\Rhapsody.exe" D:\CppCashRegister_rpy\CppCashRegister.rpy -cmd=call "rtc update_build_execute TPkg_CashRegister::TCon_CashRegister::tc_SimpleStart" -cmd=save
updates, builds, and then executes the test case "tc_SimpleStart" of the model CashRegister.

- ◆ "<full Rhapsody path>\Rhapsody.exe" D:\CppCashRegister_rpy\CppCashRegister.rpy -cmd=call "execute TPkg_CashRegister::TCon_CashRegister" -cmd=save
executes the test context TCon_CashRegister of the model CashRegister

- ◆ "<full Rhapsody path>\Rhapsody.exe" D:\CppCashRegister_rpy\CppCashRegister.rpy -cmd=call "rtc build_execute TPkg_CashRegister" -cmd=save
builds and executes the test package TPkg_CashRegister of the model CashRegister.

Command Line Syntax for rhapsodycl.exe

If you run the command line version of rhapsody, rhapsodycl.exe, you can execute the same TestConductor commands as for rhapsody.exe. In rhapsodycl.exe, the TestConductor commands are invoked by specifying

- -cmd=call "rtc TC_COMMAND TC_ELEMENT"

in the command line prompt of rhapsodycl.exe. TC_COMMAND can be one of the following testconductor commands:

- update_build_execute
 - performs an update, then a build, and then an execute on the specified test element.
- update_build
 - performs a build, and then an execute on the specified test element.
- update
 - performs an update on the specified test element.

- `build_execute`
 - performs a build and then an execute on the specified test element
- `build`
 - performs a build on the specified test element.
- `execute`
 - performs an execute on the specified test element.
- `clean`
 - performs a clean on the specified test element.

and `TC_ELEMENT` is either “all” or the full pathname of a test case, a test context or a test package.

Examples (we assume that `rhapsodycl.exe` is already started):

- `"> -cmd=call "rtc update_build_execute
TPkg_CashRegister::TCon_CashRegister::tc_SimpleStart"`

updates, builds, and then executes the test case “`tc_SimpleStart`” of the model `CashRegister`.

- `"> -cmd=call "execute
TPkg_CashRegister::TCon_CashRegister"`

executes the test context `TCon_CashRegister` of the model `CashRegister`

Test Execution Report

After test execution all test reports are written in the same manner as described under “Test Case Execution”, “Test Context Execution” and “Test Package Execution”.

Test Case Execution on Targets

In addition to executing test cases on the host environment, test cases can also be executed on the target environment. The necessary steps are target environment specific and are further described in the following documents:


- ◆ [Testing_with_RTC_on_a_Linux_Target.pdf](#) (Linux)
- ◆ [Testing_with_RTC_on_a_VxWorks_Target.pdf](#) (VxWorks)

Information about testing non-animated applications asynchronously with TestConductor can be found in section Offline Testing on page **Fehler! Textmarke nicht definiert.** pp.

Driving Operations Calls

Driving Operation Calls (for Rhapsody in C/C++/Java/Ada)

To be able to call operation calls from the environment in TestConductor, we have to set the **Enable Operation Calls** option in the dialog **Advanced Instrumentation Settings** as *Public*, *Protected* or *All* and recompile/rebuild the model.



This setting controls the property `CG:Operation:AnimAllowInvocation`. Following are the details of the options that can be used:

- ◆ **None (Default)**—do not enable calls
- ◆ **Public**—enable calls if operation is public
- ◆ **Protected**—enable calls if operation is public or protected
- ◆ **All**—enable calls in all cases

Test Management

TestConductor is a fully integrated add-on solution for Rhapsody. All relevant test data like the test architecture, test cases and their test scenarios, test configurations and test results are stored in the model. Navigation to all the elements can be done via the usual capabilities of the Rhapsody browser.

Managing Test Data



With this tight integration you have all the possibilities you already know from other elements like classes, package and so on, e.g.:

- ◆ Copy, paste, delete
- ◆ Create units for test components, test context, SUT and test component instances
- ◆ Load / unload test packages, test components, test context, SUT and test component instances
- ◆ Requirements management
- ◆ Configuration management
- ◆ Documentation


Linking Test Case to Requirements

Test cases can be linked to their requirements which are defined in the model. This can be done by using *test objectives* (*TestObjective*) to link model elements to the related requirements.

- ◆ Add a new test objective to the test case “tc_SimpleStart” and select the requirement from the listed model elements.




The result is a new test objective REQ1 as an element of test case “tc_SimpleStart” which is linked to its requirement REQ1.



TestConductor Dialog

The TestConductor main dialog provides some global TestConductor settings and help functions by selecting **Tools > TestConductor** from the Rhapsody tools menu:



The dialog offers the possibility to set some global TestConductor settings and to open TestConductor's tutorial by selecting **Help > Tutorial**. The global settings that can be changed in this dialog are explained in the next section **TestConductor Settings**.


TestConductor Settings

TestConductor provides a range of global and also test case specific settings. The settings are in most cases stored as properties in the model.

[-] TestConductor	
[-] SDInstance	
ExecutionIterations	1
ExecutionMode	Monitor
ExecutionOrder	Linear
ParameterValues	
[-] Settings	
AcknowledgeApplyChanges	<input checked="" type="checkbox"/>
CreateTestArchitectureMode	Standard
MapSDToTestArchitectureMode	Strict
OverwriteTestContextDiagram	Never
TestCaseExecutionOrder	BrowserOrder
[-] TestCase	
AnimatedSUT	Automatic
ATGTestCase	<input type="checkbox"/>
CallOperationsOnlyWhenCallstackEmpty	<input checked="" type="checkbox"/>
ComputeCoverage	<input type="checkbox"/>
CoverageKind	SUT flat
CreateSDForFailedSDInstance	<input type="checkbox"/>
ExecuteTestWithTracer	<input type="checkbox"/>
ExecutionAnimationStartedTimeout	20
ExecutionAnimationStoppedTimeout	20
ExecutionFirstIdleTimeout	20
ExecutionIdleTimeout	600
MultipleConditionCheck	<input type="checkbox"/>
ResetAppBeforeStartTest	<input checked="" type="checkbox"/>
TerminateAppOnQuitTest	<input checked="" type="checkbox"/>
Tolerances	
UseOM_RETURN	<input type="checkbox"/>
WriteTestExecutionLogFile	<input type="checkbox"/>

Sequence Diagram Properties (only animation based testing mode)

TestConductor provides settings concerning the usage and interpretation of sequence diagrams during test case execution. All following properties are the settings for the dialog **Define Test**:



These settings have to be done via properties on *SDInstance* level. Open the **Feature** dialog of a sequence diagram instance, select the **Properties** tab, switch in the dropdown combo box **View** to *All* and navigate to the metaclass `TestConductor::SDInstance`

SDInstance	
ExecutionIterations	1
ExecutionMode	Monitor
ExecutionOrder	Linear
ParameterValues	

`TestConductor::SDInstance::ExecutionIterations`

The required number of run-time instances can be set to multiple iterations with a concrete number.

Note: This property should not be set directly. Please use the **Multiple Iterations** setting in the **Define Test** dialog.

`TestConductor::SDInstance::ExecutionMode`

Driver invokes automatic driving of model execution after the test has been activated. TestConductor automatically injects events into the running Rhapsody model according to the specified sequence diagram. **Monitor** invokes manual driving of model execution. This means that, during test execution, you must inject input events manually using the Rhapsody animation tool or the project GUI (when available). TestConductor monitors the reception of these events and internal messages between system objects. **Blackbox** considers only those messages that originate at the system border (to be driven by TestConductor) or that go to the system border (to be monitored by TestConductor).

Note: This property should not be set directly. Please use the corresponding **Execute SDInstance as:** setting in the **Define Test** dialog.

`TestConductor::SDInstance::ExecutionOrder`

Linear—specifies that TestConductor should monitor the sequence diagram under test assuming that all events and messages are arranged in a strict sequence. The vertical drawing order of messages in sequence diagrams is used to compute an absolute sequence of events and messages (each message in the in sequence diagram has a unique predecessor and successor). **Partial**—specifies that TestConductor should monitor only the order of events located on the same line (instance line or message arrow).

Note: This property should not be set directly. Please use the corresponding **SD Interpretation (Order):** setting in the **Define Test** dialog.

`TestConductor::SDInstance::ParameterValues`

For a parameterized Rhapsody sequence diagram, map its parameters to concrete values.

Note: This property shall not be set directly. Please use the button **Parameter Mapping** in the **Define Test** dialog.

General Properties

TestConductor provides some general settings that change the general behavior of TestConductor. These settings have to be done via properties on test package level. Open the **Feature** dialog of a test package, select the **Properties** tab, switch in the dropdown


combo box **View** to *All* and navigate to the metaclass `TestConductor::Settings`

TestConductor	
Settings	
<code>AcknowledgeApplyChanges</code>	<input checked="" type="checkbox"/>
<code>CreateTestArchitectureMode</code>	Standard
<code>MapSDToTestArchitectureMode</code>	Strict
<code>OverwriteTestContextDiagram</code>	Never
<code>TestCaseExecutionOrder</code>	BrowserOrder

`TestConductor::Settings::AcknowledgeApplyChanges`

If this property is switched on, `TestConductor` requires an explicit acknowledge from the user each time a `SDInstance` has been changed. If the property is switched off, changes of `SDInstances` are acknowledged implicitly.

By default this property is switched on.



`TestConductor::Settings::CreateTestArchitectureMode`

This property controls the behavior of the `TestConductor` function “Create TestArchitecture”. If this property is set to “Standard”, each time “Create TestArchitecture” is performed `TestConductor` creates a component and a configuration

for the newly created TestArchitecture using the default property settings for components and configurations. If the property is set to “Advanced”, each time “Create TestArchitecture” is performed TestConductor opens a dialog which allows to specify from which of the existing components/configurations the property values of the newly created component/configuration shall be derived.

By default this property has the value “Standard”.

`TestConductor::Settings::MapSDToTestArchitectureMode`

This property controls the behavior of the test case wizard when a test case is created for an existing sequence diagram. If the value of this property is set to “Strict”, only those test architectures are considered to be suitable for the new test case that contain at least one SUT instance of one of the classes of the life lines of the original sequence diagram. If the value of this property is set to “Weak”, also all test architectures are considered to be suitable that does not contain a SUT instance of one of the classes of the life lines of the original sequence diagram, but for which the same message exchange is possible as in the original sequence diagram.

`TestConductor::Settings::overwriteTestContextDiagram`


This property controls the creation of TestContextDiagrams when performing an “Update TestArchitecture” on a TestContext. If this property is set to “Never”, each time “Update TestArchitecture” is performed a new TestContextDiagram is added to the existing TestContextDiagrams, i.e., existing TestContextDiagrams are not overwritten. If this property is set to “askUser”, each time “Update TestArchitecture” is performed TestConductor asks if an existing TestContextDiagram shall be replaced with a new one. If this property is set to “Always”, each time “Update TestArchitecture” is performed TestConductor replaces an existing TestContextDiagram with a new one.

By default this property has the value “Never”.


`TestConductor::Settings::TestCaseExecutionOrder`

This property controls the execution order of TestCases when executing a TestContext. Possible values are “BrowserOrder” and “DeclarationOrder”, where “BrowserOrder” defines that TestCases are executed in the same order as they are displayed in the browser. “DeclarationOrder” defines execution in a user defined order. The declaration order can be specified by right-clicking “TestCases” and selecting “Edit TestCases Order” from the context menu.

By default this property has the value “BrowserOrder”.



“Edit TestCases Order” opens a dialog using which the order of TestCases can be defined:



TestConductor::Settings::TestingMode

By default, new projects created with Rhapsody 7.6 are created with testing mode set to assertion based testing, i.e., the property “TestConductor.Settings.TestingMode” is set to “AssertionBased”. For test packages that have been created with a Rhapsody version older than 7.6 this property is set to “AnimationBased”, i.e., for those test packages TestConductor behaves as in 7.5.3. If you want to switch from one testing mode to another testing mode manually, please open the TestConductor main dialog by choosing “TestConductor” from the tools menu. In the upcoming dialog, select the testing mode you want TestConductor to operate:



Test Context Properties

Also some properties for test contexts can be set by the user. In order to change these properties, open the **Feature** dialog of a test context, select the **Properties** tab, switch in the dropdown combo box **View** to *All* and navigate to the metaclass

TestConductor::TestContext

[-] TestConductor	
[-] TestContext	
TestContextExecution_PostTestCaseOperation	
TestContextExecution_PreTestCaseOperation	
TestContextExecution_RestartExecutable	<input checked="" type="checkbox"/>

TestConductor::TestContext::TestContextExecution_RestartExecutable

If this property is checked (true), for each test case during execution of the test context, the executable of the test context is restarted. If the property is not checked (false), the test cases are executed without restarting the executable after the previous test case has finished its execution.

TestConductor::TestContext::TestContextExecution_PreTestCaseOperation

If this property contains a name of an operation of the test context, for each test case during execution of the test context, **before** a test case is executed the operation specified in this property is called automatically. In the operation specified in this property, one can initialize or reset some variables that are needed in the subsequent test case execution.

TestConductor::TestContext::TestContextExecution_PostTestCaseOperation

If this property contains a name of an operation of the test context, for each test case during execution of the test context, **after** a test case is executed the operation specified in this property is called automatically. In the operation specified in this property, one can reset some variables that are needed in the subsequent test case execution.

Test Case Properties (only animation based testing mode)

Also some properties for test cases can be set by the user. Some of these properties are set directly by using the execution dialog, some properties you may set using the feature dialog of a test case. Open the **Feature** dialog of a test case, select the **Properties** tab, switch in the dropdown combo box **View** to *All* and navigate to the metaclass

TestConductor::TestCase

TestConductor	
TestCase	
AnimatedSUT	Automatic
ATGTestCase	<input type="checkbox"/>
CallOperationsOnlyWhenCallstackEmpty	<input checked="" type="checkbox"/>
ComputeCoverage	<input type="checkbox"/>
CoverageKind	SUT flat
CreateSDFForFailedSDInstance	<input type="checkbox"/>
ExecuteTestWithTracer	<input type="checkbox"/>
ExecutionAnimationStartedTimeout	20
ExecutionAnimationStoppedTimeout	20
ExecutionFirstIdleTimeout	20
ExecutionIdleTimeout	600
MultipleConditionCheck	<input type="checkbox"/>
ResetAppBeforeStartTest	<input checked="" type="checkbox"/>
TerminateAppOnQuitTest	<input checked="" type="checkbox"/>
Tolerances	
UseOM_RETURN	<input type="checkbox"/>
WriteTestExecutionLogFile	<input type="checkbox"/>

TestConductor::TestCase::AnimatedSUT

This property controls the assumptions of TestConductor concerning the animation of the SUT classes. Depending on the fact that the SUT classes are animated or not, TestConductor uses different execution algorithms to control the execution of test cases that are needed in order to execute test cases properly. If this property is set to “Automatic”, TestConductor tries to automatically deduce if the SUT contains animation code or not, and chooses the right execution algorithm accordingly. If the property is set to “true”, TestConductor assumes that the SUT classes contain animation code. If the property is set to false, TestConductor assumes that there is no animation code for the SUT classes.

Per default the property is set to “Automatic”.

`TestConductor::TestCase::ATGTestCase`

Normally TestConductor injects messages that are defined in a sequence diagram without time delays directly one after the other. In case this property is enabled, TestConductor waits with injection of messages until the system is idle.

This property is enabled automatically for test cases created and exported by ATG.

Per default the property is disabled.

`TestConductor::TestCase::CallOperationsOnlyWhenCallstackEmpty`

If this property is checked, TestConductor delays operation calls that refer to inputs of TestConductor so that these operation calls are made only when the call stack of the focus thread is empty.

If the property is cleared, all operation calls are made by TestConductor immediately even if the call stack of the focus thread is not empty.

Per default the property is disabled.

`TestConductor::TestCase::ComputeCoverage`

In case this property is enabled, TestConductor automatically computes and reports the model coverage achieved when executing the test cases.

Per default the property is disabled.

`TestConductor::TestCase::CoverageKind`

If `TestConductor::TestCase::ComputeCoverage` is enabled, `CoverageKind` defines how the coverage will be measured:

TestConductor supports four different kinds of coverage measures:

- ◆ SUT flat: Only coverage of the toplevel class of the SUT is measured, i.e. states, transitions, and operations of parts of the SUT are not considered. Coverage of model elements of test components is also not measured.

- ◆ SUT hierarchical : Coverage of the SUT is measured in a hierarchical manner, i.e. also states, transitions, and operations of parts of the SUT are hierarchically regarded for coverage measure. Coverage of model elements of test components is again not measured.
- ◆ TestContext flat : Coverage is measured in terms of all states, transitions, and operations defined at the first decomposition level of the test context, i.e. all states, transitions, and operations of the direct parts of the test context are considered.
- ◆ TestContext hierarchical : all states, transitions, and operations in the hierarchal structure of the test context are considered in coverage measure.

Per default the property is set to “SUT flat”..

`TestConductor::TestCase::CreateSDForFailedSDInstance`

In case this property is enabled, TestConductor automatically creates a failure sequence diagram (**Show as SD**) and stores it in the model.

Per default the property is disabled.

`TestConductor::TestCase::ExecuteTestWithTracer`

In case this property enabled, the execution of this test case will be done with activated tracer (trace #all all).

Per default the property is disabled.

`TestConductor::TestCase::ExecutionAnimationStartedTimeout`

Defines the time (in seconds) that TestConductor waits for the animated application to connect to Rhapsody. If the application does not connect to Rhapsody within the specified time, the test case execution is aborted. The default value is 20 seconds.

`TestConductor::TestCase::ExecutionAnimationStoppedTimeout`

Defines the time (in seconds) that TestConductor waits for the animated application to terminate after receiving the terminate command from TestConductor. If the application does not terminate within the specified time, TestConductor simply proceeds. The default value is 20 seconds.

`TestConductor::TestCase::ExecutionFirstIdleTimeout`

Defines the time (in seconds) that TestConductor waits for the animated application to become idle after giving the first “Go Idle” command. If the application does not become idle within the specified time, the test case execution is aborted. The default value is 20 seconds.

`TestConductor::TestCase::ExecutionIdleTimeOut`

In case a timeout is defined (> 0) and the application does not show any activity for the defined timeout (in seconds) the execution of this test case is interrupted.

The testing profile defines a global timeout, which can be overwritten for every test package, test context and test case. This default value in the testing profile is 600 seconds.

Setting this property to zero means that no timeout is enabled.

`TestConductor::TestCase::MultipleConditionCheck`

TestConductor can be configured to check the reached condition and following conditions without system activity, until one condition mark evaluates to `FALSE`. To change the default TestConductor behaviour change the property

`TestConductor::TestCase::MultipleConditionCheck` of the test case to `TRUE`. For further information read the chapter Condition Marks at page 163.

Per default the property is `FALSE`.

`TestConductor::TestCase::ResetAppBeforeStartTest`

In case this property is enabled, TestConductor will reset the application to the initial state of the model for each test case execution. Normally this property is set using the test execution dialog for sequence diagram based test cases.

Per default the property is enabled.

Note: This property is available for sequence diagram test cases only. This property is currently not interpreted for source code, flow chart and statechart test cases.

`TestConductor::TestCase::TerminateAppOnQuitTest`

This property controls the behavior of TestConductor after quitting a test. In case this property is enabled, the application terminates after quitting the test. Otherwise only TestConductor quits.

Per default the property is enabled.

Note: This property is available for sequence diagram test cases only. This property is currently not interpreted for source code, flow chart and statechart test cases.

`TestConductor::TestCase::Tolerances`

This property is an internal property where TestConductor stores tolerance definitions defined in the sequence diagram test definition dialog. User should not set this property directly.

Note: This property should not be set directly. Please use the corresponding **Tolerances** button in the **Define Test** dialog.

`TestConductor::TestCase::UseOM_RETURN`

In case this property is enabled, TestConductor checks return values by evaluating a specific animation message that is generated by the application if the operation whose

return value should be checked uses the animation macro OM_RETURN. If this property is disabled, TestConductor can only check return values for operation calls that originate from TestComponents.

Per default the property is disabled.


TestConductor::TestCase::WriteTestExecutionLogFile

TestConductor generates a log file of the test case execution if this property is enabled. TestConductor stores this log file (RTC_log.txt) into the folder C:\tmp. The folder must exist and the user must have write access to this folder.

Per default the property is disabled.

Generating Test Reports with Rhapsody ReporterPLUS

Rhapsody ReporterPLUS is a reporting engine. The user is able to customize the content and style of a Rhapsody ReporterPLUS report by specifying a template. Rhapsody TestConductor delivers the test report template (TestReport.tpl) and the test requirement coverage report template (TestRequirementCoverage.tpl), which will be installed in the folder “reporterplus\Template” in your Rhapsody installation.



The screenshot shows a web browser window displaying a test report titled "Test Report of Model CppCashRegister". The browser's address bar shows the file path: C:\Dokumente und Einstellungen\tschriefer\Desktop\Cash\Reports\TPkg_CashRegister.htm. The report is generated at 7/17/2007 at 16:41:04.

Table of Contents

- Test Report of Model CppCashRegister
 - TCon_CashRegister
 - System Under Test (SUT)
 - Test Component Instances
 - Test Context Diagrams
 - Test Cases
 - Test Case AD_tc_0
 - Test Case Code_tc_0
 - Test Case SD_tc_0
 - Test Case atg_tc_002
 - Test Case atg_tc_003
 - Test Case atg_tc_004
 - Test Case atg_tc_006
 - Test Case atg_tc_007
 - Test Case atg_tc_008
 - Test Case atg_tc_009
 - Test Case atg_tc_010
 - Test Case atg_tc_013
 - Test Case atg_tc_014
 - Test Case atg_tc_015
 - Test Case atg_tc_016
 - Test Case atg_tc_017
 - Test Case testcase_3

Test Report of Model CppCashRegister
(Report created at 7/17/2007 at 16:41:04)

Project	CppCashRegister.rpy
Directory	C:\Programme\Telelogic\Rhapsody 7.1 \Samples\CppSamples\TestConductor\CppCashRegister
Language	C++
Description	This is the CashRegister exercise model for the Rhapsody TestConductor and ATG tutorial. It is based on the model from M.W.Richardson and shows the main aspects of the Testing Profile implementation firstly delivered with Rhapsody TestConductor 2.0.

This document contains the test contexts


TCon_CashRegister	in TPkg_CashRegister::TCon_CashRegister
--------------------------	---

Note: The report templates currently will not show pictures of subscenarios or linked subscenarios of test cases. Only the top level diagrams of scenarios and flow charts are currently displayed.

Executing the Test Report

To execute the test report template on the model containing test data:


- ◆ In case you want to create the report only for a selected test package and the containing test packages, select in the Rhapsody browser a test package and choose from the menu **Tools > ReporterPLUS > Report on selected package...**



- ◆ In case you want to create the report for all test packages in the model choose from the menu **Tools > ReporterPLUS > Report on all model elements...**
- ◆ In the Rhapsody ReporterPLUS wizard **Select Task** specify the export file format your report shall be displayed in and click **Next>**.




- ◆ In the Rhapsody ReporterPLUS wizard **Select Template** check the currently active template. In case the template “TestReport.tpl” is not active click on “...”, open it from the folder “reporterplus\Templates” in your Rhapsody installation folder and click **Next>**.




- ◆ The Rhapsody ReporterPLUS wizard **Confirmation** gives an overview about the selected options. Click the button **<Back** to change the options. Click **Generate** to start the execution of the Rhapsody ReporterPLUS report generation.



- ◆ In the dialog **Generate Document** specify a path and a name for the document to generate and click the button **Generate**.



- ◆ Rhapsody ReporterPLUS will show the progress during creating the document and start the corresponding application to show the test report.



Using the HTML Test Report

The created HTML test report is divided into two sections, the table of Contents on the left side and the content section on right side. Dependent of the selected item on the left side, the corresponding section of the report will be shown on the right side.

Note: The HTML report will only be displayed correct in the internet browsers and versions, which are shown at report startup.

Note: The table of contents will only be shown in a HTML report. To display the table of contents Java must be installed. In case these requirements are not fulfilled, please select another export file format like Microsoft Word.

Table of Contents

- [-] Test Report of Model CppCashRegister
 - [-] TCon_CashRegister
 - [-] System Under Test (SUT)
 - [-] Test Component Instances
 - [-] Test Context Diagrams
 - [-] Test Cases
 - [-] Test Case AD_tc_0
 - [-] Test Case Code_tc_0
 - [-] Test Case SD_tc_0
 - [-] Scenario SD_tc_0
 - [-] Test Case atg_tc_002
 - [-] Test Case atg_tc_003
 - [-] Test Case atg_tc_004
 - [-] Test Case atg_tc_006
 - [-] Test Case atg_tc_007
 - [-] Test Case atg_tc_008
 - [-] Test Case atg_tc_009
 - [-] Test Case atg_tc_010
 - [-] Test Case atg_tc_013
 - [-] Test Case atg_tc_014
 - [-] Test Case atg_tc_015
 - [-] Test Case atg_tc_016
 - [-] Test Case atg_tc_017
 - [-] Test Case testcase_3

Test Report of Model CppCashRegister

(Report created at 7/17/2007 at 16:41:04)

Project	CppCashRegister.rpy
Directory	C:\Programme\Telelogic\Rhapsody 7.1 \Samples\CppSamples\TestConductor\CppCashRegister
Language	C++
Description	This is the CashRegister exercise model for the Rhapsody TestConductor and ATG tutorial. It is based on the model from M.W.Richardson and shows the main aspects of the Testing Profile implementation firstly delivered with Rhapsody TestConductor 2.0.

This document contains the test contexts

TCon_CashRegister in TPkg_CashRegister::TCon_CashRegister

The first page gives an overview about the loaded model and the contained text contexts. This page is reachable from the highest entry of the table of contents.

Conceptual this report lists all test contexts of the specified test package(s) during creation. For each test context you will find information about

- ◆ the system under test
- ◆ the test component instances
- ◆ the test context diagrams
- ◆ the test cases and their execution status

Each test context and the sub-items are reachable by clicking on the corresponding item in the table of content. Click on the plus to extend the tree structure.

Using the Test Requirement Coverage Report

Table of Contents

Requirement Coverage

All Requirements

All Test Cases

All Requirements



Name	Specification	Covered by Test Case
CD_WhiteBox_002	Check that each preset can be set to the minimum and maximum frequency for each waveband. Check that these presets are remembered even after the radio has been switched off and then back on.	FCWhiteBox_002  Failed
CD_WhiteBox_003	Check that if the user starts to setup a preset that if they don't complete the setup then after 8 seconds the setup is cancelled.	not covered
CD_WhiteBox_004	Check that the display indicates the correct frequency, waveband and also the "M" symbol.	not covered
REQ001	A radio needs to be designed.	Radio  not executed
REQ002	The radio should be able to tune to four different Wavebands: LW, MW, SW & FM.	not covered






Table of Contents

Requirement Coverage


All Requirements

All Test Cases

All Test Cases

Name	Description	Test Objective	Test Execution Result
CDWhiteBox_001a	Check that the radio cannot be tuned to a frequency outside of the limits for LW waveband.	Requirement_CD_WhiteBox_001 (Requirement)	 Passed
CDWhiteBox_001b	Check that the radio cannot be tuned to a frequency outside of the limits for MW waveband.	Requirement_CD_WhiteBox_001 (Requirement)	 Failed
CDWhiteBox_001c	Check that the radio cannot be tuned to a frequency outside of the limits for SW waveband.	Requirement_CD_WhiteBox_001 (Requirement)	 Passed
CDWhiteBox_001d	Check that the radio cannot be tuned to a frequency outside of the limits for FM waveband.	Requirement_CD_WhiteBox_001 (Requirement)	 Passed
FCWhiteBox_002	Check that each preset can be set to the minimum and maximum frequency for each waveband. Check that these presets are remembered even after the radio has been switched off and then back on.	CD_WhiteBox_002 (Requirement)	 Failed

Execute the test requirement coverage template (TestRequirementCoverage.tpl) to get a statement about the relation between a requirement and the corresponding test cases, which cover a requirement in the model. The testing profile defines the stereotype <<TestObjective>> which shall be used to setup a relation between a test case and a requirement, which it covers. In general a test objective is a stereotyped dependency, which can link on every element in the model.








This requirement coverage report focus especially on the dependency between a requirement and a test case. The test requirement coverage report gives another view on the model. At a glance the user is able to verify, that e.g. the requirement “Requirement_CD_WhiteBox_001” is covered by the test cases CDWhiteBox_001a, CDWhiteBox_001b, CDWhiteBox_001c and CDWhiteBox_001d, where CDWhiteBox_001b is currently FAILED and in result the requirement “Requirement_CD_WhiteBox_001” is not fulfilled.

Table of Contents			
<ul style="list-style-type: none"> Requirement Coverage All Requirements All Test Cases 			
REQ018	When the Radio is switched on, it should tune to the previous Waveband and Frequency.	not covered	
Requirement_CD_WhiteBox_001	Check that the radio cannot be tuned to a frequency outside of the limits for each waveband.	CDWhiteBox_001a (Passed) CDWhiteBox_001b (Failed) CDWhiteBox_001c (Passed) CDWhiteBox_001d (Passed)	
SD_WhiteBox_001	Check that the radio can be switched on and off.	SDWhiteBox_001 (Passed)	
SD_WhiteBox_002	Check that when the radio is switched on, that it remembers the waveband and frequency that had previously been selected.	SDWhiteBox_002 (Aborted)	
SD_WhiteBox_003	Check that the Radio can be automatically tuned forwards and backwards.	SDWhiteBox_003 (not executed)	

In opposite to the view “All Requirements”, the report also shows a table with “All Test Cases” of the model. The “All Test Cases” view is assistant to check, whether a test case has a test objective.

Some items in HTML report e.g. requirements, test cases test results etc. are linked, so the user can easily browse to more detailed information pages.

<div>  </div>		Requirement Requirement_CD_WhiteBox_001	
Requirement_CD_WhiteBox_001		Description	no description
		Specification	Check that the radio cannot be tuned to a frequency outside of the limits for each waveband.
		Package	Radio_TestPlan
		Full Path	RequirementsPkg::Radio_TestPlan.Requirement_CD_WhiteBox_001
		Covered by Test Case	CDWhiteBox_001a ( Passed), CDWhiteBox_001b ( Failed), CDWhiteBox_001c ( Passed), CDWhiteBox_001d ( Passed),
		Anchored Elements	CDWhiteBox_001a (Operation), CDWhiteBox_001b (Operation), CDWhiteBox_001c (Operation), CDWhiteBox_001d (Operation),

Customizing the Test Report

The test report template is customizable to fit specific users requirements. Follow the Rhapsody ReporterPLUS documentation how to adapt it to your needs.

Using the TestConductor API

Similar to Rhapsody, TestConductor provides an API that can be used to access TestConductor functionality from

- VBA Scripts
- Programs using the Rhapsody COM API
- Programs using the Rhapsody Java API

In order to use the TestConductor API the Rhapsody API function “IRPApplication::runHelper(String)” must be used. In order to apply this function correctly, one has to provide as an argument a valid TestConductor command. Additionally, before the “runHelper” function can be executed, an appropriate model element (e.g. a TestCase) must be selected by using the Rhapsody API. A typical sequence would look as follows (using VBA):

```
...
Set app = GetObject(, "rhapsody.Application")
Set proj = getProject()
Set testcase = proj.findElementsByFullName("TestPackageA.TestContextB.TestCaseC")
' highlight the selected element
testcase.highLightElement();
' now one can execute a TestConductor command
app.runHelper("Execute TestCase Sync")
...
```

The sample “CppSamples/TestConductor/TestConductorAPI” shows how to access the TestConductor API from within VBA scripts and Java programs. Additionally, the sample “CppSamples/TestConductor/CppTestAutomationSample” shows how to use the API in order to automate your testing workflows..

Available TestConductor API Commands

The following TestConductor API commands are available and can be called by using the “runHelper” Rhapsody API function:

Applicable to TestCase elements:

- “Edit TestCase SDInstances”
- “Update TestCase”
- “Build TestCase”
- “Execute TestCase”
 - Performs asynchronous TestCase execution, i.e., the function returns immediately and the execution of the TestCase is performed in a separate thread. The API script has to ensure itself (e.g. by waiting a specified amount of time) that the TestCase execution has finished before additional TestConductor API commands can be executed.
- “Execute TestCase Sync”
 - Performs synchronous TestCase execution, i.e., the function returns only after the execution of the TestCase has finished. This ensures that subsequent TestConductor API commands are only performed after the TestCase execution has finished. This is the preferred way of executing TestCases via the TestConductor API.

Applicable to TestContext elements

- “Create SD TestCase”
- “Create Flowchart TestCase”
- “Create Code TestCase”
- “Update TestContext”
- “Build TestContext”
- “Execute TestContext”
 - Performs asynchronous TestContext execution, i.e., the function returns immediately and the execution of the TestContext is performed in a separate thread. The API script has to ensure itself (e.g. by waiting a specified amount of time) that the TestContext execution has finished before additional TestConductor API commands can be executed.
- “Execute TestContext Sync”

- Performs synchronous TestContext execution, i.e., the function returns only after the execution of the TestContext has finished. This ensures that subsequent TestConductor API commands are only performed after the TestContext execution has finished. This is the preferred way of executing TestContexts via the TestConductor API.
- “Execute TestPackage”
- “Update TestArchitecture”

Applicable to TestPackage elements

- “Create TestContext”
- “Update TestPackage”
- “Clean TestPackage”
- “Build TestPackage”
- “Execute TestPackage”
 - Performs asynchronous TestPackage execution, i.e., the function returns immediately and the execution of the TestPackage is performed in a separate thread. The API script has to ensure itself (e.g. by waiting a specified amount of time) that the TestPackage execution has finished before additional TestConductor API commands can be executed.
- “Execute TestPackage Sync”
 - Performs synchronous TestPackage execution, i.e., the function returns only after the execution of the TestPackage has finished. This ensures that subsequent TestConductor API commands are only performed after the TestContext execution has finished. This is the preferred way of executing TestPackages via the TestConductor API.


Applicable to Class elements

- “Create TestArchitecture”

Defining Callbacks for TestConductor functions

In addition to using the TestConductor API directly, one can also execute automated scripts after certain TestConductor actions like e.g. creating test architectures. In order to do this, one can use triggered helpers as provided by Rhapsody. For instance, to specify that after test architecture creation a certain helper should be activated automatically, one has to do the following steps:

- Define a helper with the Helper Trigger “After Add Element”. The helper can be implemented e.g. using a VBA script or by an external program that uses the Rhapsody API.



- Now, when doing “Create TestArchitecture”, after the test architecture has been created the specified helper is invoked automatically.

Besides “Create TestArchitecture”, helpers with helper trigger “After Add Element” are also invoked automatically for all other TestConductor functions that create new elements, like e.g. “Create Code TestCase”.

Advanced Test Definition

Specifying Requirements with Sequence Diagrams

Sequence diagrams play a dominant role in the TestConductor test process. They are a key means for the graphical specification of tests, and enable TestConductor to visualize design flaws.

Graphical Feature Support


TestConductor supports the standard UML sequence diagram elements, as available in the Rhapsody sequence diagram editor. However, some of these elements are not yet fully supported.

TestConductor supports the following graphical features:

- ◆ Test component lines, which specify classes with driver operations or stub operations
- ◆ Test context lines, which specify the boundary of the system under test including their test components
- ◆ Environment lines, which specify the boundary of a system under test (only animation based testing mode)
- ◆ Actor instance lines for reactive actor classes (those containing state charts). These classes represent external behaviour against the system under test.
- ◆ Object instance lines, which specify the communication behaviour inside the system under test
- ◆ Horizontal and slanted message arcs between object instances (including actor instances), which specify events, triggered operations, operation calls, and their argument values. Unspecified messages (messages with realization *unspecified*) and unrealized message (messages with Stereotype *unrealized*) are ignored.
- ◆ Messages to itself, which specify that the source and the target of events and operation calls is the same object instance.
- ◆ Dataflow messages among object instances.
- ◆ Condition marks, which specify synchronization points in a sequence diagram (only animation based testing mode)
- ◆ Events originating at the environment axis, which specify that external events trigger the system under test.
- ◆ Only assertion based testing mode: Interaction operators “opt”, “alt”, “loop”, “break”, “consider”, “parallel”

Synchronous and Asynchronous Messages

Rhapsody supports the concepts of *synchronous* and *asynchronous* messages. Both of these concepts can be used when you define and execute tests.



Note the following:


- ◆ Only event messages, which are asynchronous, can be interfered by another message.
- ◆ Operation calls are synchronous and do not admit any interference.

TestConductor associates for every event message in a sequence diagram two actions—sending and receiving. In opposite to event messages TestConductor associates only one action to operation calls and dataflows. During a test execution with TestConductor, you can drive a specified sequence diagram and monitor (in the execution dialog) the total number of actions and those that passed successfully.

Linear and Partial Order (only animation based testing mode)

TestConductor can interpret a sequence diagram either in *linear order* or in *partial order* mode. To understand why partial order interpretation of sequence diagrams is sometimes necessary to specify monitors, consider the following example. Assume that the companies `CompanyA` and `CompanyB` want to set up a conference call. You want to monitor the situation that both parties are eventually connected to the conference call. The following sequence diagram specifies that each party dials a conference `CallNr()`. Regardless of the order the parties dial and connect, the monitor must be fulfilled whenever both parties have connected. In the sequence diagram every message `CallNr()` specifies two ordered actions:

- ◆ Sending the `CallNr()` event by a party
- ◆ Consumption of the `CallNr()` event by the telephone corresponding to the calling party




If you had only linearly ordered monitor sequence diagrams, you could not express the required independency of the connection order. Note that there are six possible dialing-and-connection orders for the parties:

```

(CompanyA_Dial - CompanyB_Dial - CompanyA_Connect -
CompanyB_Connect)
(CompanyA_Dial - CompanyB_Dial - CompanyB_Connect -
CompanyA_Connect)
(CompanyA_Dial - CompanyA_Connect - CompanyB_Dial -
CompanyB_Connect)
(CompanyB_Dial - CompanyA_Dial - CompanyB_Connect -
CompanyA_Connect)
(CompanyB_Dial - CompanyA_Dial - CompanyA_Connect -
CompanyB_Connect)
(CompanyB_Dial - CompanyB_Connect - CompanyA_Dial -
CompanyA_Connect)
  
```

Every sequence diagram interpreted in linear order could specify only one of these possible connection orders (for example, the linear order of the connections shown in the sequence diagram considered above is "CompanyA_Dial - CompanyB_Dial - CompanyB_Connect - CompanyA_Connect", because the evaluation order is from top to bottom). Hence, with linear order you must define six different monitor sequence diagrams. Note that five of these monitors would lead to a failure during testing; only one would pass in every test execution. If you interpret this sequence diagram in partial order, it represents all the possible (six) orders. This is due to the fact that you do not enforce any order between pair wise independent sending and receiving of the `CallNr()` events. Sending and receiving of an event on the `CompanyB` side is independent from the `CompanyA` side.

Test execution with partial order might result in extreme compilation times. TestConductor has a facility to interrupt the execution when it takes too long.



By pressing the “Abort” icon in the icon toolbar aborts the compilation and test case execution.

Note: Partial order set together with the **driver and monitor** option implies that driving the input events is independent from monitoring the internal messages. To avoid the arising nondeterminism, TestConductor first drives inputs and then monitors internal messages. **TestConductor chooses one valid order of messages to be driven (in particular, this order changes in general when the same sequence diagram test case is executed repeatedly).** Such nondeterminism does not exist for linear order interpretation, because it is a precise order between all messages in a sequence diagram. Also note that there is no nondeterminism for monitor only, because you decide when you inject all inputs, and TestConductor monitors internal messages as they appear in the running model.


Parameters

One of the most important aspects of reusing sequence diagrams is the possibility to parameterize them. By using *parameters* such as “X” and “Y” as object names for sequence diagram instances, all combinations of objects of the corresponding classes can be treated within one sequence diagram. You must instantiate these parameters with different concrete objects of the system.

Parameters are used to specify sequence diagrams, which can be used as test patterns or as generic sequence diagrams in test definitions. Parameterized sequence diagrams can be used more than once in the same test configuration, or they can be used in various contexts in different test configurations. Parameters can be applied for instance names and for argument lists of events and operations. Instance names in a Rhapsody sequence diagram must be either concrete names or parameters. For example, if an instance line is labelled “X1:Telephone”, X1 is a parameterized object instance name of class Telephone that will be mapped to a concrete object instance name when the sequence diagram is instantiated as part of a test definition. In other words, X1 can be mapped to PBX[0] -> itsTelephone[0]. Parameters are useful when you are defining multiple tests with a similar structure, such as the PBX sample where Telephone 1 can connect to Telephones 2, 3, and 4. Using parameters, you can specify sets of similar tests by

specifying one common sequence diagram for these cases. To manually generate multiple test cases, simply bind the sequence diagram parameters to various concrete values.

In the following example, the sequence diagram contains the parameters `caller`, `receiversLine`, `receiver`, `nr1`, and `nr2`. The first three parameters represent parameterized instance names, whereas the last two describe attribute values for parameterized events. Due to the concept of parameters, this sequence diagram can be used as a test pattern to specify and execute caller-receiver tests for the pairs of telephones. This is done by instantiating the sequence diagram several times.




Defining Parameters


TestConductor supports test definitions based on sequence diagrams, whose instances either have a concrete or *parameterized name*. Parameterized name means that it is not a valid, or concrete, object name as usually used in Rhapsody. You can also use *an anonymous class name* that is without a concrete name or parameter. In this case, in accordance with Rhapsody, the class name is internally expanded to the unique concrete object instance. During test execution, sequence diagrams are animated in relation to the default names. Note that parameters have no default values. You can specify parameters for a sequence diagram by declaring them in the Tag *RTC_SDPParameter* which is available for each test scenario sequence diagram.

To declare parameters for a sequence diagram do the following:


1. Open a Rhapsody sequence diagram in a Rhapsody project.
2. In the names pane, specify the objects names of the classes `Telephone` and `Line`. Give a parameterized name, such as `caller:Telephone`. Give the concrete names for another instance depicted in the sequence diagram like `PBX[0] -> itsTelephone[0]: Telephone`. You can leave an instance “anonymous” like `Line`. Rhapsody considers such a specification as a concrete class instance with the default name `PBX[0] -> itsLine[0]:Line`.



3. In the Rhapsody browser, click on the cross beside of the name of the test scenario sequence diagram to open the tag view.



4. Open the **Feature** dialog of the corresponding RTC_SDPParameters tag
5. Click into the **Value** field and type the name of the parameter.



Note: Make sure that you type the identical names of parameters as specified in the current sequence diagram. TestConductor cannot determine misspelling.


Note: TestConductor adds properties to the sequence diagrams when models are opened, in case these properties were not added before. This is why existing models with sequence diagrams are marked as changed (red icon) along with the sequence diagrams when projects are loaded for the first time after TestConductor was installed.

If a sequence diagram contains two or more parameters, separate their names using commas, then click **OK**. The following figure shows how to specify multiple parameters.

You can apply parameters to message argument lists to specify more flexible, generic sequence diagrams as templates in test definitions. Parameterized arguments of messages are used, for example, when input stimuli correspond to parameterized object names in the same sequence diagram or in the same test configuration.

To extend the parameter list of a sequence diagram with parameterized arguments, do the following:

1. Open the sequence diagram in the Rhapsody sequence diagram editor and specify event or operation arguments as parameters inserting their parameterized names in the object pane. As an example, in the following figure, values of the `Digit` argument of the `evDigitDialed` event are specified as parameters `nr1` and `nr2`



2. Using the Rhapsody browser, open the **Feature** dialog of the corresponding `RTC_SDPParameters` tag and extend the list of the parameters typing “`nr1, nr2`” in addition to the existing parameters in the **Value** field.
3. Click **OK** to accept the change of the parameter list.

The specification defined with the generic “`Ringing_Another_Party`” sequence diagram, says that whenever a calling telephone is taken off the hook and dials an extension, the receiving telephone rings. Note that the sequence diagram does not specify which telephone is calling, which one is the receiver, nor the extension dialed.

Parameter Mapping

You can consider Rhapsody sequence diagrams with parameters as “classes of sequence diagrams”, whereas sequence diagrams with parameters mapped to real objects represent “instances of sequence diagram classes.” One parameterized sequence diagram can be used in various contexts: in different test configurations, or in the same test configuration with different parameter mappings. It catches several requirements similar in structure (order of messages) and different only in the names of the involved instances.

As an example, the “`Ringing_Another_Party`” sequence diagram can specify that `Telephone 1` calls `Telephone 4`. To do this, map its parameters to the following object names in the PBX model:

```

caller: PBX[0]->itsTelephone[0]
receiversLine: PBX[0]->itsLine[3]
  
```

```
receiver: PBX[0]->itsTelephone[3]
nr1: 1
nr2: 4
```

The following table lists the extension for each telephone.

Telephone	Extension
Telephone 1	11
Telephone 2	12
Telephone 3	13
Telephone 4	14

In this example, mapping parameter `nr2` to 3 instead of 4 leads to the “concrete” specification corresponding to “Whenever Telephone 1 dials the extension of Telephone 3, Telephone 4 rings”. TestConductor will show that this specification cannot be met by the real behaviour of the model.

Note: During execution parameter values containing quotes will consistently be stripped, e.g. the expression “OK” will be converted to OK and “”OK”” will be converted to “OK”.

Using Time Interval for Delay Driving from Environment and TestComponents

TestConductor provides capabilities to automatically drive messages (events, operations or triggered operations) with a certain delay. Users can specify that TestConductor should drive external messages or messages from a TestComponent to the SUT with a certain time delay. Whenever a message must be driven, users can specify that TestConductor waits for a certain amount of time (`ms`, `sec`, `min`) in order to delay actual message generation. This is expressed on the sending instance line (either the system border or a TestComponent) with the time interval notation of the sequence diagram editor.


Note: TestConductor will regard only time intervals between messages, if driving messages are defined from the ENV line and the time interval definition is also specified on the ENV line or if driving messages are defined from a TestComponent instance line and the time interval definition is specified on the same TestComponent instance line.
Any Time Interval on a SUT instance line will be ignored.

Time delays will be specified with the time interval notation in sequence diagrams. TestConductor supports time intervals if they are associated with system border or TestComponent instance lines. The label of a time interval specifies the time unit (`ms`, `sec`, `min`) and a time value. Essentially, there are two slightly different Time Interval annotations with a slightly different execution semantics. The first variant uses the following syntax:

Syntax: > 5 sec

Here, TestConductor must wait at least 5 seconds before it may drive the next message. Other time interval formats are “> 500 ms” and “> 5 min”. TestConductor creates a timer in the tested application which elapses after the amount of time specified in the Time Interval.

The start point of a time interval is always associated with the next message point above the time interval (on any instance line). The end point of a time interval is always associated with the next message point below the time interval (again on any instance line).



After driving `evOffHook()` and observing `evOriginateCall()` TestConductor must wait 5 seconds before it may drive `evDigitDialed(Digit=1)`.

TestConductor must monitor all system reactions before `evDigitDialed(Digit=1)`, including `evDialTone()`.

The second variant of Time Intervals are those which uses the following syntax for time annotations:

Syntax: >> 5 sec

When using this syntax, in contrast to the “> 5 sec” case TestConductor does not create an own application timer when starting the time interval. Instead TestConductor will use the time of the tested application. As a result, TestConductor will only proceed if the tested application time increases at least the specified amount of time. In contrast to the “> 5 sec” syntax TestConductor may proceed later than the specified amount of time, since the tested application time might increase to a larger amount of time than the specified time interval.

TestConductor also allows that time intervals overlap if several messages to be driven are constrained via time intervals. This means, TestConductor will manage several timers for the driven messages at the same time, no matter if they are specified on the same instance line or on different instance lines. For every time interval there always exists a unique predecessor and successor message to be driven in the sequence diagram.

Activation Conditions (only animation based testing mode)

Activation conditions are used to specify the point in time during model execution when sequence diagram instances become activated. You can use activation conditions to model a predecessor order between several sequence diagram instances in a test definition. Activation conditions can specify a starting point of sequence diagram instance

simulation, such as event sending or event receiving, which in turn can be a result of the behavior defined by another sequence diagram. TestConductor supports conditional expressions for events and conditions in the following form:

ObjectName->CondName (Parameters)

In this syntax:

- ◆ ObjectName is a parameterized or concrete name of a class instance or an ENV (environment variable), which can be represented by the system border.
- ◆ CondName is a particular kind of event, state, or method action.
- ◆ Parameters is a state of a state chart, or the name of an event or method, and the receiver of this event or method, depending on the CondName.

The exact syntax is described under Syntax for Activation Conditions / Condition Marks (see page 250) in the appendix.


Note: Rhapsody does not perform any static syntax checks on these conditions.

You can associate exactly one activation condition with every sequence diagram. The trivial activation conditions are *TRUE* and *FALSE*. Every sequence diagram instance used in a test inherits the activation condition specified in the property dialog of the sequence diagram.


Defining an Activation Condition

Activation conditions are stored as additional tag *RTC_ActivationCondition* in the corresponding test scenario sequence diagram. Activation conditions can be defined with respect to the condition language definition, as follows:

1. In the Rhapsody browser, click on the cross beside of the name of the test scenario sequence diagram to open the tag view.



2. Open the **Feature** dialog of the corresponding *RTC_ActivationCondition* tag
3. Click into the **Value** field and type the condition. You can specify one activation condition.



5. Click **OK**.

Note: To make activation conditions visible in the sequence diagram, you can draw notes with their descriptions.


Condition Marks (only animation based testing mode)

TestConductor enables you to specify conditions for condition marks on instance lines with the same syntax as activation conditions. Condition marks in sequence diagrams can play the following two roles:

- ◆ Synchronize several sequence diagram instances executed concurrently.
- ◆ Specify a stubbing behaviour which can appear during execution.

As an example, you can add the following condition mark for the instance of the class `Line` in the “Ringing_Another_Party” sequence diagram:

```
receiversLine->IsIn(ROOT.InService)
```




Testing the requirements specified by this sequence diagram, TestConductor will drive the first three events. After that, it will proceed only if the condition of the condition mark has the value `TRUE`. Otherwise, some other activities in the system must be performed to

change the value of the condition. You can specify these activities using other sequence diagrams driven by TestConductor. They can also be driven manually, if it has not been yet implemented as a part of the system. Changing the value of the specified condition to `TRUE` will trigger TestConductor to continue monitoring and driving this sequence diagram.

In case there are two or more condition marks defined in a row, TestConductor will check the first only. TestConductor will evaluate each of the following condition marks with a new system activity, if the previous condition mark was `TRUE`. This is the default TestConductor behaviour.

TestConductor can be configured to check the reached condition and following conditions without system activity, till one condition mark evaluates to `FALSE`. To change the default TestConductor behaviour change the property


`TestConductor::TestCase::MultipleConditionCheck` of the test case from `FALSE` to `TRUE`.



Note: TestConductor will ignore condition marks during test execution when the syntax of the condition mark is not valid.

Preconditions (for SysML/Harmony)

For SysML/HARMONY models, i.e for SysML models that contain the HARMONY profile, TestConductor provides a special kind of condition, so-called preconditions. With preconditions, in SysML/HARMONY models one can set attributes of SUTs to specified values. This is useful whenever the behavior of the SUT depends on values of local attributes. In order to define a precondition in a test scenario, add a condition on the life line of the SUT instance that contains the attribute, and specify the value the attribute should have:



In the example depicted above, a precondition is specified that defines value “12” for the attribute “i1” and value “Peter” for attribute “s1” of block A. When executing the test case, and TestConductor reaches the precondition, it sets the specified values for the attributes. When the test case continues, now the behavior of the SUT reflects the new values for the attributes. Currently, the usage of preconditions is restricted to SysML/HARMONY models. If multiple attributes should be set by a precondition, the attribute value specification must be separated by newlines in the condition mark.


Use Cases of Activation Conditions

This section describes some examples that use activation conditions. The main three purposes of activation conditions are as follows:

- ◆ To specify the starting point of sequence diagram simulation.
- ◆ To specify that one sequence diagram can be activated only when another sequence diagram has already been activated or fully traversed (during simulation).

Specifying the Starting Point of Simulation

Activation conditions specify a point in time when the corresponding sequence diagrams must be activated. Consider the parameterized “Answering_Call” sequence diagram shown in the following figure:



This sequence diagram can be used to test, whether any telephone can properly answer a call. This property will be checked starting in the system state specified in its activation condition:

- ◆ When the object defined as `receiversLine` has sent the event `evRing()` to the corresponding `Telephone` receiver.
- ◆ When the object defined as `receiver` stays in its basic state `Idle`.


Specifying Ordered Predecessors (only animation based testing mode)

Through activation conditions, you can define a *predeccessing order* between instances of different sequence diagrams checked during the same test execution.

Example 1: Exact Predeccessing

Consider two sequence diagrams that will be stimulated one after another:

- ◆ “Ringing_Another_Party” (shown on page 157)
- ◆ “Receive_X”, shown in the following figure:



Note that the exact order can be set only between “concrete” sequence diagram instances, rather than parameterized sequence diagrams. Consider the following parameter mapping for the “Receive_X” sequence diagram:

```

receiver: PBX[0]->itsTelephone[2]
receiversLine: PBX[0]->itsLine[2]
  
```


The activation condition of this sequence diagram specifies the starting point when Line 3 has sent the `evRing` event to its Telephone 3. This condition can become `TRUE` when the corresponding instance of the “Ringing_Another_Party” sequence diagram (with the similar parameter mapping) has been fully traversed.

Although the sequence diagrams “Ringing_Another_Party” and “Receive_X” have similar parameter names—`receiver` and `receiversLine`—they can be mapped to different values. In such a case, two sequence diagram instances will be unordered. Therefore, parameter names in sequence diagrams can be considered as local variables with values in the scope of the corresponding sequence diagrams.

Example 2: Interleaving the Execution of Two Sequence Diagrams

The following two sequence diagrams are activated during a test execution one after another:

The “X_calls_Y” sequence diagram, shown in the following figure:




This can be used to test whether any telephone can start and finish a communication. Moreover, this property will be checked only starting from the specified state of the system—when the object defined as `callersLine` has not received the event `evRing` from the corresponding telephone `caller`.

An instance of the “Receive_X” sequence diagram, described on before can be activated after the corresponding instance of the “X_calls_Y” sequence diagram has been partially traversed. To obtain this order between sequence diagram instances, the mapping for the parameters `receiversDigit1` and `receiversDigit2` from the “X_calls_Y” sequence diagram must correspond to the extension number of the `Line` name mapped to the parameter `receiversLine` from the “Receive_X” sequence diagram.


Note that the predeccessing order is defined implicitly. During test execution, containing instances of these two sequence diagrams, Test Conductor first activates an instance of “X_calls_Y”, drive the events `evOffHook`, `evDigitDialed`, and monitor the event `evDialTone`. After driving the event `evDigitDialed(Digit= receiversDigit2)`, TestConductor activates the corresponding instance of the “Receive_X” sequence diagram. It monitors the event `evRelease` only after the instance of the “Receive_X” sequence diagram has been fully traversed. The exact order of the sequence diagram instance execution is derived from the system behaviour, but is also bounded by the activation condition.

Specifying Return Values and Output Values

Users can specify expected return values and output values for operation calls. To specify a return value for an operation, open features dialog of an operation in a sequence diagram. Specify the expected return value in the **Return Value** field.



Consider operation 4 =op_int(a = [3..4], b = 2, c = In:9;Out:3) in the following sequence diagram. It returns integer values. Assume we specify integer value 4 as the return value.



TestConductor will monitor the actual values as specified in the dialog when an operation call returns and will check if the actual return value conforms to the specified value or not.

Note: Using Macro `OM_RETURN()`: TestConductor is using Rhapsody's animation capabilities to perform test execution. If an operation returns a value then this value is by default *not animated* in Rhapsody. In order to get animation information about returning operations it is *mandatory* to use a special Rhapsody macro `OM_RETURN()` instead of statement `return()` for the purpose of test execution. The macro is pre-defined in "`\\Share\\LangCpp\\aom\\aommacro.h`". In the above example suppose that operation body of `op_int(int a, int b, int c)` simply contains one statement `„return 4;“`. This must be replaced by `OM_RETURN(4);` to be able to check such return values with TestConductor. Since this special macro is only needed for testing purposed it is already embedded into `#ifdef`-statements. The `#ifdef` statement guarantees that the

macro is only used for testing purposes, while the standard return-statement is used when generating non-animated code.

Note: Using Macro `OM_RETURN_VOID`: If an operation returns with a void value, then TestConductor can check that the return indeed happens when using `OM_RETURN_VOID`.

Note: Using Macro `OMREPLY()`: Triggered operations returning values is realized using `reply()`. TestConductor can check that the return indeed happens when using `OMREPLY()`.

Note: output parameters of type `uchar` and `long double` are not supported.

Note: range specification for return values (e.g. "`[1..4]`") are not supported.

If an actual return value does not conform to a specified value, then a red message is drawn. The message is labelled with

```
"<Specified operation and its parameter> Operation Call returned -
Return value does not match. Expected values are: <Expected
operation and its parameter list>".
```

For example:

```
"4=op_int(a=1,b=2,c=3) Operation Call returned - Return value does
not match. Expected values are: 5=op_int(a=1,b=2,c=3)".
```

Note: If we have pointer types or structures as output and in/out parameter types then serialization functions must be added to the macro in order to be able to test the value with TestConductor.

Note: If we have pointer types or structures as return types then serialization functions must be added to the return macro in order to be able to test the value with TestConductor

Specification of the Output and in/out Values

Suppose we consider an operation `m(int p1, int p2, int p3, int p4)`, where `p1` and `p2` are input parameters and `p3` is an output parameter, and `p4` is an in/out parameter. In a sequence diagram users can specify the expected input parameter values and the expected output and in/out parameter values. Output and in/out Test Execution parameters are realized with call-by-reference. For instance, a sequence diagram message "`m(p1= 3, p2 = 5, p3 = 7, p4 = 9)`" specifies that operation `m()` is called in the model with input values `p1=3` and `p2=5`, and with references to `p3` and `p4`, i.e. `m(3, 5, &p3, &p4)`. Note that `&p4` is an in/out parameter and hence is used as an input in the operation `m()`, too. Here, `&p4` provides the value '9' for the call. The call returns with value `p3=7` and `p4=?`.

The in/out parameter is specified in a sequence diagram with both input and output parameters. The format of specifying an in/out parameter is

```
<parameter> = In:<in_value>;Out:<out_value>
```

Message `m(p1 = 3, p2 = 5, p3 = 7, p4 = In:9;Out:12)` specifies that `m()` is called with "Input p1=3", "Input p2=5", "in/out p4=9". Message `m()` returns with "Output p3=7, in/out p4=12". Both values for in/out parameter `p4`, the input part and the output part are specified.

Output value checking can not be done for operations which originate from the environment line and are generated by `TestConductor`. Checking of output values is supported for all operations that originate from `TestComponents`, and for all operations that do not start at the environment line and whose called operation uses `OM_RETURN` to return values to the caller.

Users can record animated sequence diagrams. The animated sequence diagrams trace the parameter values when operations are called, but they do not show the values of output and in/out parameters when operations return. Hence, animated sequence diagrams can not be used to check values of output parameters and in/out parameters. Users have to modify animated sequence diagrams in order to extend it with relevant output information which is not provided by Rhapsody's sequence diagram animation.

Suppose we consider an operation `m(int p1, int p2, int p3, int p4)`, where `p1` and `p2` are input parameters and `p3` is an output parameter, and `p4` is an in/out parameter. An animated sequence diagram might show `m(p1 = 3, p2 = 5, p3 = *, p4 = 9)`. In order to check output parameter `p3` and the output value of `p4` when `m()` returns users must add the required information. Example: `m(p1 = 3, p2 = 5, p3 = 7, p4 = In:9;Out:12)`.


Note: Out or in/out values are only taken into account by `TestConductor` if also a return value is given in the message specification (value or "don't care"-star). That must also be done for operations that do not have a specified return type (void operations). Hence, the `In...;Out:...` specification should only be used if a return value has been defined, too. Otherwise the test execution will fail.

Note: Out values for some specific out arguments are currently not usable if the corresponding setting of the property `CPP_CG::Type::Out` specifies a pointer-type instead of a reference-type.

Note: During execution parameter values containing quotes will consistently be stripped, e.g. the expression "OK" will be converted to OK and ""OK"" will be converted to "OK".

Ignoring Unrealized Messages

Messages with stereotype *unrealized* are filtered out and ignored in the test execution.



Open the **Features** dialog of the message then specify **Stereotype** as *Unrealized*. When you are executing the test, we get a user warning that the message is ignored in the test execution.


Note: TestConductor only supports single-stereotyped elements, but not yet elements with multiple stereotypes.

Reference Sequence Diagram


Interaction occurrences and their corresponding reference sequence diagrams are specified within Rhapsody. Defining tests with TestConductor is not affected by interaction occurrences, since interaction occurrences are features inside sequence diagrams, while tests are defined on the basis of sequence diagrams listed in the Rhapsody browser. If sequence diagrams used in a TestConductor test contain interaction occurrences, then this is not relevant for the test definition but it clearly has impact on the test execution.

TestConductor will substitute interaction occurrences with the scenarios specified in the corresponding reference sequence diagrams for test execution. For TestConductor, it is logically the same if users specify a scenario within one sequence diagram or if the scenario is specified with interaction occurrences and reference sequence diagrams. Whenever an interaction occurrence is reached, then the scenario as specified in the reference sequence diagram is tested. Test control starts with the main sequence diagram, and when a reference sequence diagram is reached, the control goes into a reference sequence diagram, and as the execution of the reference sequence diagram is completed, the control returns back into the main sequence diagram.

Consider the following main sequence diagram, “SD_A”, which has a reference to the sequence diagram, “SD_B”.



This interaction occurrence refers to a sequence diagram with name “SD_B”, as seen below.



In the sample sequence diagrams above testing sequence diagram “SD_A” with reference sequence diagram “SD_B” leads to the same result as if the interaction occurrence would have been replaced with the scenario in “SD_B”.

The scenario which is going to be tested is:

- EvOffHook (SD_A)
- EvOriginateCall (SD_B)
- OpenConnection (SD_B)
- OpenConnection (SD_B)
- EvOriginateCall (SD_B)

- EvDialTone	(SD_B)
- EvRing	(SD_A)
- EvDigitDialed	(SD_A)
- EvDigitDialed	(SD_A)
- EvDigitDialed	(SD_A)
...	

Note: Interaction occurrences are drawn on lifelines. Those lifelines have to be contained in the reference sequence diagram.

TestConductor does not care if:

- ◆ reference sequence diagram *does not contain the same life lines* as surrounded by the interaction occurrence
- ◆ reference sequence diagram contains *fewer* life lines
- ◆ reference sequence diagram contains *more* life lines
- ◆ reference sequence diagram contains *other* life lines

TestConductor just considers the provided life lines and the specified messages as relevant test scenario and expects exactly those messages when the SUT is executed. For instance, if the above shown sequence diagram “SD_B” does not contain the life line to the right hand side, then message `evOriginateCall` going to this life line is not part of the test.

Show As SD draws one new sequence diagram with all the messages which have been monitored (*green* colour) or which are supposed to be monitored (*blue* colour), and also failed messages (*red* colour). If a test contains a sequence diagram with one or more interaction occurrences, then TestConductor draws still only one new sequence diagram which shows all the relevant messages of the main sequence diagram and also the messages from the entire referenced sequence diagram.

In case a TestConductor test is executed in linear order a situation which must be taken care of is, when there is an additional message on the same level as of the reference sequence diagram. Consider sequence diagram “SD_A” with the interaction occurrence. To the right hand side of the interaction occurrence there is an additional message `evRing`, which is independent from the interaction occurrence. In partial order execution this will be considered as parallel. In linear order execution, TestConductor must determine a total order on all messages. In sequence diagrams without interaction occurrences, this order is determined graphically from top to bottom in a sequence diagram. In the case above, the graphical order between messages in “SD_B” and between `evRing` is not specified. Hence, TestConductor can not establish a total order based on the graphical information. In this situation, TestConductor follows the following rules:

1. TestConductor considers all messages from top to bottom in total order unless the upper boundary (graphically) of an interaction occurrence is reached.
2. Then all messages in the reference sequence diagrams are considered in total order
3. Then the messages to the right hand and left hand side of an interaction occurrence are considered in total order (if those messages do exist).

4. If reference sequence diagrams contain new interaction occurrences then the same rules apply.

If several interaction occurrences appear in one sequence diagram then the same rules apply, i.e. there is a total order on interaction occurrences which is derived from the graphical order.

If an interaction occurrence is not yet realized by a reference sequence diagram, then this interaction occurrence is ignored for actual test execution.

If reference sequence diagrams are used to specify lifeline decomposition, then this is also ignored by TestConductor for test execution.

Life Line and Part Decomposition

Life Line Decomposition Support for Testing (only animation based testing mode)

Life line decomposition and their corresponding reference sequence diagrams are specified in Rhapsody. For instance, consider sequence diagram “MainSD” (Figure 1) which references “RefSD” (Figure 2).

The system border life line specifies the environment of the sequence diagram. Here, we have four messages from the system border going to a logical object `Tel0`. `Tel0` has not been realized to a concrete class or object in the model. It is just a logical name for an arbitrary telephone (<unspecified>). It is a decomposed life line. We set the decomposed life line to “RefSD” as shown in the diagram. Messages `evOffHook`, `evDigitDialed` and `evOnHook()` are sent to `Tel0` (the messages are also <unspecified>). The `MappingPolicy` property of its life line is set to `ObjectAndDerivedFromRefSD`.




Figure 1 : MainSD

In the “RefSD”, we can see that the messages that come from the system border of this “RefSD” do match with the messages in the “MainSD” (`evOffHook()`, `evDigitDialed()`, `evOnHook()`). In the “MainSD”, these messages go from the system border to the `Tel0` life line. `Tel0` is internally realized by the concrete objects `PBX[0]->itsTelephone[0]`, `PBX[0]->itsLine[0]` and `PBX[0]->itsConnection[0]` which also exchange some internal messages.




Figure 2 : RefSD

We consider only the “MainSD” while defining the test in TestConductor. For actual test execution, TestConductor will execute the “MainSD” and check if the messages sent to/from Tel0 in the “MainSD” are received/sent by any of the instances in the “RefSD”. TestConductor knows only senders/receivers of the “RefSD”, i.e., TestConductor knows only the instances in the “RefSD” but TestConductor does not know about the internal messages between the instances in the “RefSD”. When message are sent to/from Tel0 in the “MainSD”, Testconductor only checks if these messages are received/sent by the instances present in the “RefSD”.

In the sample, testing “MainSD” with reference sequence diagram “RefSD” leads to the following order of messages that will be checked by TestConductor

- ◆ System border sends `evOffHook()` to Tel0 in the MainSD
- ◆ `evOffHook()` is received by one of the instances in the RefSD

- ◆ System border sends `evDigitDialed(Digit = 1)` to `Tel0` in the `MainSD`
- ◆ `evDigitDialed(Digit = 1)` is received by one of the instances in the `RefSD`
- ◆ System border sends `evDigitDialed(Digit = 2)` to `Tel0` in the `MainSD`
- ◆ `evDigitDialed(Digit = 2)` is received by one of the instances in the `RefSD`
- ◆ `evRing()` is sent by one of the instances in the `RefSD`
- ◆ `evRing()` is received by `PBX[0]->itsLine[1]` in `MainSD`
- ◆ Messages `evRing()` and `evAlerting()` occur in the `MainSD`
- ◆ `evAlerting()` sent by `PBX[0]->itsline[1]` to `Tel0` in `MainSD`
- ◆ `evAlerting()` is received by one of the instances in the `RefSD`
- ◆ Messages `evOffHook()` and `evAnswerCall()` occur in the `MainSD`
- ◆ `evAnswerCall()` sent by `PBX[0]->itsline[1]` is sent to `Tel0` in `MainSD`
- ◆ `evAnswerCall()` is received by one of the instances in the `RefSD`
- ◆ System border sends `evOnHook()` to `Tel0` in the `MainSD`
- ◆ One of the instances in the `RefSD` receives `evOnHook()` in `RefSD`

Note: Limitation - Type of message arguments going to decomposed life lines are not known. All arguments are treated as input arguments.

In order to drive messages that are directed to decomposed life lines, a receiver instance must be specified. Open the features dialog of the decomposed life line, click on **Tags** tab, add a new tag `RTC_receiver` (if not available) and also a value like `Telephone[0]` as shown in Figure 3.




Figure 3 : Features dialog

The following rules are applied by TestConductor in order to drive those messages.

1. If an instance line is not decomposed
 - ◆ not realized messages to such a life line are filtered out with a warning
 - ◆ if the life line is not realized the test is not executed

2. If a life line is decomposed into *ObjectAndItsParts*

- ◆ if the life line is not realized the test is not executed
- ◆ if the life line is realized then for each driven message the tag RTC_receiver is used to define the proper receiver of the message.
- ◆ if the tag is not defined then the message is sent to the instance the life line is realized to.

3. If an instance line is decomposed into *ObjectAndDerivedFromSD*

- ◆ tag RTC_receiver is used to define the receiver instance of driven messages
- ◆ if the tag is not defined then the message is sent to the instance the life line is realized to
- ◆ if the tag is not defined and the message is not realized then the message is filtered out

4. If an instance line is decomposed into *Smart*

- ◆ if a reference sequence diagram has been defined then see 3.
- ◆ otherwise see 2.

Part Decomposition Support for Testing




Figure : ObjectSD

Life lines can represent objects and its parts. Consider the Sequence diagram “ObjectSD” above. In the features tab for life line PBX, we have class PBX as Realization and ObjectAndItsParts as MappingPolicy. Instance line PBX represents object PBX and its parts. evOffHook() and evOnHook() are sent to the parts of PBX from the environment. TestConductor treats these messages as going to object PBX or any of it parts. evOriginateCall() is an internal message of PBX, which is sent between the internal parts of PBX. In other words, TestConductor takes a black box view for life lines with part decomposition.

Advanced Sequence Diagram Test Definition

The TestConductor test definition dialog enables you to define and configure advanced sequence diagram test cases. Using the dialog box, you can define a name of the test, a description and you can add several sequence diagram instances to the test case. The sequence diagram instances are marked as **Monitor Only**, **Driver** and **Monitor** or **Black-Box** and parameters are bound to concrete values. In addition, for every sequence diagram instance, you choose the interpretation order (**Linear** or **Partial**) and execution mode. The

Execution Mode specifies whether the sequence diagram instance must be tested one time or repeatedly in a cycle. You can order sequence diagram instances with **Single Iteration** or in an **Ordered Predecessor** order.

Defining a Sequence Diagram Test

There are four steps in defining a test using the **Define Test** dialog:

1. Create the sequence diagram test case.
2. Define a new sequence diagram instance.
3. Map the parameters.
4. Close the dialog.

The following sections describe these steps in detail.

Creating a Sequence Diagram Test Case

There are three possible ways to define a sequence diagram test case:

1. Right-click on the test context and select **Create SD TestCase**. This creates automatically a new test scenario sequence diagram with lifelines of all classes (SUT and test components) of the test context.
2. Right-click on the test context and select **Add New > TestingProfile > TestCase**.


For the second way you have to use the **Define Test** dialog (shown on page 181). Use sequence diagrams could be sequence diagrams from the analysis phase, a recorded animated sequence diagram from manually driven animation, or a newly drawn test scenario sequence diagram.

Adding a New Sequence Diagram Instance

When you add an sequence diagram instance to a test case definition, you select and reference a sequence diagram from the Rhapsody repository, define a name for that particular instance in the test configuration, and bind the parameters to concrete values (if parameters are used in the sequence diagram). TestConductor automatically extracts the defined activation condition of the referenced sequence diagram from the Rhapsody repository and displays it in read-only mode in the text field.

To add a sequence diagram instance to the list, do the following:

1. In the **Define Test** dialog box, click **Add SD Instance**.
2. The fields **SD-Instance Name**, **Sequence Diagram**, and **Description of SD-Instance**, and the radio buttons **Execution Mode**, **SD Interpretation (Order)**, and **Execute SD-Instance** become enabled so that you can enter data.
3. In the **SD-Instance Name** field, type a descriptive name. For example, “Tel 1 calls Tel 2”.
4. The **Sequence Diagram** drop down list includes all the sequence diagrams from all packages specified in the project. From this list, select one sequence diagram. The following figure shows the list of sequence diagrams for the PBX example.



Note: You do not have to save the sequence diagrams before using them to define and execute tests because the created sequence diagrams are immediately part of the model. The read-only field **Activation Condition** shows the corresponding value

for the specified sequence diagram. You can change this value by editing the tag *RTC_ActivationCondition* of the corresponding sequence diagram.

5. In the field **Execute SD-Instance as**, select one of the following options:
 - ◆ **Driver and Monitor**—Invokes automatic driving of model execution after the test has been activated. In other words, TestConductor automatically injects events into the running Rhapsody model according to the specified sequence diagram.
 - ◆ **Monitor Only**—Invokes manual driving of model execution. This means that, during test execution, you must inject input events manually using the Rhapsody animation tool or the project GUI (when available). TestConductor monitors the reception of these events and internal messages between system objects.
 - ◆ **Black-Box**—Considers only those messages that originate at the system border (to be driven by TestConductor) or that go to the system border (to be monitored by TestConductor). The remaining messages are not considered because they are internal to the system.
6. In the field **SD Interpretation (Order)** select one of the following options:
 - ◆ **Linear**—Specifies that TestConductor should monitor the sequence diagram under test assuming that all events and messages are arranged in a strict sequence. The vertical drawing order of messages in sequence diagrams is used to compute an absolute sequence of events and messages (each message in the sequence diagram has a unique predecessor and successor).
 - ◆ **Partial**—Specifies that TestConductor should monitor only the order of events located on the same line (instance line or message arrow).

Note that partial order set together with driver and monitor implies that driving the input events is independent from monitoring the internal messages. To avoid the arising nondeterminism, TestConductor first drives inputs and then monitors internal messages. **TestConductor chooses one valid order of messages to be driven (in particular, this order changes in general when the same sequence diagram test case is executed repeatedly).** Such nondeterminism does not exist for linear order interpretation, because it is a precise order between all messages in a sequence diagram. See chapter Linear and Partial Order (on page 154), for the explanation of partial order. Note that there is no nondeterminism for monitor only, because you decide when you inject all inputs, and TestConductor monitors internal messages as they appear in the running model.

7. In the **Execution Mode** field, select one of the radio buttons:
 - ◆ **Single Iteration**—Drives the sequence diagram instance only once. TestConductor will generate only one run-time instance of the sequence diagram.
 - ◆ **Multiple Iteration**—Drives the sequence diagram instance in a cycle. This option is defaulted to 0 which implies infinite execution of an sequence diagram instance if the activation condition of the corresponding sequence diagram is set to `TRUE`. When a concrete number is supplied here, it implies the number of times the sequence diagram instance will be executed. In batch mode execution, the number 10 helps to avoid infinite looping of tests.
 - ◆ **Ordered Predecessor**—Specifies the execution order between two sequence diagram instances. From the drop-down list, select an available sequence diagram


instance that must be executed before the current sequence diagram instance is activated.

8. If desired, specify a description in the **Description of SD-Instance** field. This field does not influence test execution, but can be used to describe the purpose of the specific sequence diagram instance.


Mapping Parameters

For a parameterized Rhapsody sequence diagram, map its parameters to concrete values as follows:

1. Click **Parameter Mapping** to display the parameter mapping list for the sequence diagram. For a “concrete” sequence diagram, this list is empty. The following figure shows the parameter list for the Tel 1 calls Tel 2 sequence diagram.




2. Double-click on the name of the parameter to map. The **Define Parameter** dialog is displayed, which enables you to bind the parameter to a concrete value in the current sequence diagram instance.
3. In the **Value** field, type an object name of the corresponding class, or a value for a message argument.



Click **OK** to add the specified parameter value to the list of the parameter mappings or click **Cancel** to discard the changes.

3. Repeat *Step 2* and *Step 3* to bind all the parameters in the list to concrete values. The following figure shows the completed list.



5. Click **Apply** to bind the values to the parameters and dismiss the dialog, or click **Close** to dismiss the dialog without binding the parameters to new values. You return to the **Define Test** dialog.
6. To add the current definition of the created sequence diagram instance to the test, click **Apply SD**. The sequence diagram instance is accepted as part of the test configuration.

If you do not apply the instance to the test, but continue with another sequence diagram instance, TestConductor automatically applies the first instance for you. If you dismiss the complete test case definition dialog, the sequence diagram instance definition is discarded.

Note: For each sequence diagram in the repository, you can add many sequence diagram instances to a test (for example, with different parameter values). At any time, you can easily modify any of the information specified for a given test. For example, you could add other sequence diagram instances, or specify another instance testing mode.

Tolerances

Don't Care Values

In some cases you might not be interested in checking actual parameter values. If


- ◆ Messages carry values that change whenever you re-run your application (sensor values, etc.). TestConductor should not compare the actual values with the specified values.
- ◆ Message parameter is a pointer to a structure. TestConductor can not compare the actual values in the structure.
- ◆ Some specific parameter values are not interesting at all for your test. You can switch on/off monitoring and checking of actual parameter values. For every message playing a role in your test you specify don't care either
- ◆ For a whole test, or
- ◆ For a single message instances in the used scenarios.

You can even switch on/off monitoring of parameter values for every single parameter of a message




To specify tolerances as don't care values:

- ◆ Replace the parameter values for message instances in the sequence diagrams with the '*' symbol (see picture above), or
- ◆ Press the **Tolerances** button within the **Define Test** dialog



- ◆ The table lists all messages of all sequence diagrams used in the test
- ◆ The don't care values in the table 'override' concrete values in sequence diagrams
- ◆ Double-click on a parameter to set/unset '*' for the parameter
- ◆ Double-click on a message to set/unset '*' for all parameters of the message
- ◆ Click on **(Un-)Set All "*"** to set/unset '*' for all parameters of all messages
- ◆ Don't care information are stored with the test
- ◆ **Show As SD** also shows use of don't care values

Don't care '*' can also be assigned to the variables used in sequence diagrams. Open the parameter mapping window and assign '*' to the variables which you want to set as don't care which is equivalent to specifying '*' in the sequence diagram.



Note: Do not use '*' for messages that are driven by TestConductor!

Note: You must not inject an event into your application with '*' as value for an input parameter

Range Setting


Range setting allows monitoring and checking if concrete values of message instances are in a given specified range. Checking ranges is required if messages have parameters that carry values which deviate from run to run. Speed and temperature are good examples since it is unlikely that the values are always the same. Usually temperature is in a certain range, e.g. between 36.5 and 36.9 degree Celsius for humans. Users must be able to specify that they do not care about specific single values, but about certain value ranges throughout testing. Similar to 'don't care' settings shown in the previous section, we use the same **Tolerances** dialog to specify the ranges also.

1. For every single message instance in a sequence diagram users can specify which parameter should be treated as range of values. A special notation will be used to indicate ranges instead of specific values. Notation:


```
[<lower_value> .. <upper_value>]
```

Users can express "m(p1=1, p2=*, p3=[1.5 .. 1.7])" to state that p1 must equals '1', p2 is "don't care", p3 must be in the range between '1.5' and '1.7'. In the PBX model, we could use the range of [0..4] for the digit of the message evDigitDialed in specified sequence diagram.


Note: *lower_value* and *upper_value* may be of scalar types like integer, long, double etc.



- Alternatively, users may want to specify one specific range of values for a given message parameter for a whole test. This might for instance be desired if a certain measured sensor value globally must be in a certain range. E.g. a measured temperature must always be in the range between 0 and 100 degree celsius. Otherwise it is considered to be an error. For the PBX model, we set the range of [0 .. 4] for the digit of the message evDigitDialed() in the **Tolerances** dialog as shown below.



The range for the messages which has a parameter as a variable can also be specified in the parameter mapping dialog as shown in the figure below. If we have n1 and n2 as variables in the sequence diagram, we can set the range for variables in the parameter setting dialog.



Tolerances


Users may want to specify a tolerance for a message parameter for the whole test. Suppose that a model contains a message $M(\text{temperature } p)$. In a recorded animated sequence diagram several instances of M might occur, because temperature is measured periodically. E.g. $M(p=27.6)$, $M(p=29.2)$, $M(p=31.1)$, etc. If such a recorded sequence diagram is used for a test, the user must either manually specify a range of values for every single message instance of M in the recorded sequence diagram, e.g. $M(p=[27.4..27.9])$, $M(p=[29.0..29.8])$, $M(p=[31.0..31.5])$ or we could define a global tolerance for parameter p of message M in the whole test, e.g. " $p = \pm 0.5$ ", meaning that the concrete values in the message instance might have a deviation of ' ± 0.5 ' from the specified values.

Note: Tolerances can be specified on a per test basis in the table. Users cannot specify parameter tolerances in the sequence diagram.


Note: Tolerances cannot be specified in the parameter mapping dialog.

Note: Tolerances apply to both the parameter values and to parameter ranges.

Setting the tolerance of ' ± 2 ' for the parameter digit in the PBX model is shown in the following figure. Message $\text{evDigitDialed}(\text{Digit} = 1)$ is seen by TestConductor as $\text{evDigitDialed}(\text{Digit} = [-1..3])$, which is a range of ' ± 2 ' and $\text{evDigitDialed}(\text{Digit} = 2)$ is seen by TestConductor as $\text{evDigitDialed}(\text{Digit} = [0..4])$, which is a range of ' ± 2 ' as specified as the tolerance.



Range of '+-2'
set for the Digit



Priority rules for the Tolerances

TestConductor will apply priority rules on the parameter values for test execution in the following order:

1. If in the Tolerances table a parameter is set as don't care '*' this will be applied for test execution
2. If don't care '*' is set in the sequence diagram, this will be applied
3. If a range of values has been specified in the **Tolerances** dialog, it will be applied for test execution
4. If a tolerance has been specified in the **Tolerances** dialog this will be applied for test execution

5. Range setting in the parameter mapping dialog or the range setting in the sequence diagram will be applied.
6. Next the value setting in the parameter mapping window or values as specified in the sequence diagrams are used for testing

Note: Value ranges and tolerances can not be applied to messages driven by TestConductor, since driving always requires concrete values.

Note: Value ranges and tolerances can be used only for pre-defined scalar types `int`, `long`, `float`, etc. such that TestConductor can apply standard compare operations (`<`, `>`, `=`) for the checking.

Note: Ranges of values and tolerances can not be applied to structured types or user defined enumeration types.

Syntax for Tolerances

The syntax for specifying don't care values, range values and tolerances is as follows:

- ◆ Don't care: `*`
- ◆ Range value: `[<lower_value> .. <upper_value>]`
- ◆ Tolerances: `<tolerance_value>`

where *lower_value* and *upper_value* and *tolerance_value* can be of pre-defined scalar types `int`, `long`, `float`, etc. such that TestConductor can apply standard compare operations (`<`, `>`, `=`) for the checking. While don't care values and range values can be specified in specification sequence diagrams, in the **Parameter mapping** dialog and in the **Tolerances** dialog, tolerance values can be specified only in the **Tolerances** dialog.

Exiting the Define Test Dialog Box

There are two ways to exit the **Define Test** dialog:

- ◆ Click **OK** to save the test.
If you click **OK**, TestConductor automatically adds all your test modifications to the current model.
Alternatively, you can add the current test to the model and exit the editor by pressing Enter, but only if the **Description of Test** and **Description of SD-instance** fields are not currently active. If you press Enter in the description fields, it adds a line-feed in the description.

Note that the TestConductor dialog accepts any test definition, even if it is incomplete (for example, you did not specify a sequence diagram instance). If you try to execute an incomplete test configuration, TestConductor displays an error message.

- ◆ Click **Cancel** to discard the test.
To ignore all changes made during the test definition session, click **Cancel**. TestConductor prompts you to confirm the lost changes; click **Yes**.


Note: It is *not* longer possible to execute tests directly from the **Define Test** dialog.

Use Cases of Sequence Diagram Test Cases

This section shows some sample test cases including different combinations of sequence diagram instance settings (execution mode, sequence diagram interpretation order with monitor or driver), as well as combinations of different sequence diagram instances to be executed in one test with different modes.

Simple Monitor


This example explains how to define a simple watchdog. The following figure shows a test configuration with independent sequence diagram instances to be driven manually, infinitely many times. TestConductor monitors whether the computed order of messages corresponds to that specified in the sequence diagrams.



To define this watchdog, do the following:

1. Modify the "A telephone calls Telephone[0]" sequence diagram to make it generic:

- ◆ In the sequence diagram editor, replace the concrete object name PBX[0] -> itsTelephone[1]:Telephone with the parameter caller:Telephone.
2. Select in the Rhapsody browser the test scenario “A telephone calls Telephone0_Variables” and click on the cross beside of the name of the test scenario sequence diagram to open the tag view.



3. Open the **Feature** dialog of the RTC_SDPParameters tag
4. Select the **General** tab, click into the **Value** field and type `caller`, the name of the parameter.



5. Apply the changes and close the **Feature** dialog

To define a new test case and connect the sequence diagram, do the following:


6. Select the test context and choose from the context menu **Add New > TestingProfile > TestCase**
7. Rename the newly created test case to “All_call_Tel1”

8. Select the test case “All_call_Tel1” and choose from the context menu **Edit TestCase SDInstance**
9. Verify the name of the test “All call Tel1” and add the description “All telephones call Telephone[0] independently.”
10. Click **Add SD-Instance**. Type the name of the sequence diagram instance “Tel2 calls Tel1” and select the sequence diagram “A telephone calls Telephone[0]” from the drop-down list.
11. Select the following radio buttons:
 - Monitor Only** execution
 - Partial** order, to set manual driving
 - Multiple Iteration**, to have TestConductor check this property several times during test execution
12. Click **Parameter Mapping** to display the list of parameters for the sequence diagram and double-click `caller`.
13. Insert the formal name of `Telephone 2`, “PBX[0]->itsTelephone[1]”, then click **OK**.
14. In the **Parameter Mapping List**, click **Apply** to bind the parameter with the concrete name.
15. If desired, add a description of the sequence diagram instance in the field at the bottom of the dialog box. For example, you could describe the requirements specified in the corresponding sequence diagram.
16. Click **Apply SD-Instance**. TestConductor adds the specified sequence diagram instance to the **SD-Instances in Test** list.
17. Repeat Step 1 to Step 6 to create two other sequence diagram instances with similar settings and parameter mappings that correspond to `Telephone 3` and `Telephone 4`.

The completed test checks that `Telephones 2, 3, and 4` can call `Telephone 1` in any order. You can execute the test infinitely many times by injecting events manually, as specified in the “A telephone calls Telephone[0]” sequence diagram.

Automatic Driver

This example shows how to define an automatic driver with several independent sequence diagram instances. The following figure shows a test configuration with independent sequence diagram instances of the “X_calls_Y” sequence diagram (see page 168) and the “Receive_X” sequence diagram (see page 167). You specify the implicit order enforced between some of the sequence diagram instances using the activation conditions and parameter mappings. TestConductor drives events sent from the environment axis and monitors whether the order of “internal” messages corresponds to that specified in the sequence diagrams.



Mapping the parameters of the "X_calls_X" sequence diagram to different concrete names for different sequence diagram instances makes these sequence diagram instances completely independent. To define the automatically driven independent calls test, add four sequence diagram instances with the settings described in the following summary of the test.

```

Independent Calls_info.txt - Notepad
File Edit Format Help
TEST:      Mainfolder\Independent Calls
COMMENT:   "Two telephones call other two telephones at the same time"

INSTANCES:
-----

1. Tel1 calls Tel2
COMMENT:   ""
DEFINITION:
    SD <X_calls_Y>, DRIVER, LINEAR, SINGLE ITERATION
    AC <NOT(callersLine->EventReceived(caller, evRing()))>
    PARAMETERS:
        receiversDigit1 = 1,
        receiversDigit2 = 2,
        callersLine = PBX[0]->itsLine[0],
        caller = PBX[0]->itsTelephone[0]

2. Tel3 calls Tel4
COMMENT:   ""
DEFINITION:
    SD <X_calls_Y>, DRIVER, LINEAR, SINGLE ITERATION
    AC <NOT(callersLine->EventReceived(caller, evRing()))>
    PARAMETERS:
        receiversDigit1 = 1,
        receiversDigit2 = 4,
        callersLine = PBX[0]->itsLine[2],
        caller = PBX[0]->itsTelephone[2]

3. Tel2 receives a call
COMMENT:   ""
DEFINITION:
    SD <Receive_X>, DRIVER, LINEAR, SINGLE ITERATION
    AC <receiversLine->EventSent(receiver, evRing())>
    PARAMETERS:
        receiversLine = PBX[0]->itsLine[1],
        receiver = PBX[0]->itsTelephone[1]

4. Tel4 receives a call
COMMENT:   ""
DEFINITION:
    SD <Receive_X>, DRIVER, LINEAR, SINGLE ITERATION
    AC <receiversLine->EventSent(receiver, evRing())>
    PARAMETERS:
        receiversLine = PBX[0]->itsLine[3],
        receiver = PBX[0]->itsTelephone[3]

```

This test checks that Telephone 1 can call Telephone 2, and Telephone 3 can call Telephone 4 independently at the same time. In addition, it checks that Telephones 2 and 4 can reply and complete calls independently. The test can be executed only one time due to the selected **Single Iteration for all SD instances** in the test configuration. Setting **Multiple Iteration** to 0, with driver and monitor mode can lead to infinite test execution. In this case, you should specify adequate activation conditions for the corresponding sequence diagrams.

Ordered SD Instances

Using activation conditions, you can specify a predecessor order implicitly. This order might depend on the parameter mapping, and is an order of sequence diagram instance activations. For example, during execution of the test described in the previous section, the “Tel2 receives a call” sequence diagram instance is activated before the “Tel1 calls Tel2


SD” instance has been fully traversed. The following example shows the usage of explicit ordering of sequence diagram instances within a test configuration.

Note: Currently, TestConductor does not support ordered predecessors with multiple iterations.

The “Calling_All_Telephones” test configuration contains the following instances:

- ◆ Four instances (Receiver_1, Receiver_2, Receiver_3, and Receiver_4) of the “Answering_Call” sequence diagram. These sequence diagram instances are specified as driver and monitor with linear order and multiple iterations. They have disjointed parameter mappings (different concrete names bound to their parameters).
- ◆ Six instances of the “Ringing_Another_Party” sequence diagram (see the section “Condition Marks”). They are set as driver and monitor with linear order. They specify calls from Telephone 1 to Telephones 2, 3, and 4, and from Telephone 4 to Telephones 1, 2, and 3 with predecessor order as follows:
 - The “Tel_1 calls Tel_2” sequence diagram instance has single iteration.
 - The “Tel_1 calls Tel_3” sequence diagram instance has “Tel_1 calls Tel_2” as its Ordered Predecessor.
 - The “Tel_1 calls Tel_4” sequence diagram instance has “Tel_1 calls Tel_3” as its Ordered Predecessor.
 - The “Tel_4 calls Tel_1” sequence diagram instance has “Tel_1 calls Tel_4” as its Ordered Predecessor.
 - The “Tel_4 calls Tel_2” sequence diagram instance has “Tel_4 calls Tel_1” as its Ordered Predecessor.
 - The “Tel_4 calls Tel_3” sequence diagram instance has “Tel_4 calls Tel_2” as its Ordered Predecessor.

The following figure shows the corresponding settings in the **Define Test** dialog.



During test execution, each of the last five sequence diagram instances can be activated only when the following two conditions are fulfilled:

- ◆ The sequence diagram instance specified in the test configuration as its predecessor has been fully traversed (passed or failed).
- ◆ Its activation condition becomes TRUE.

The specified test checks the following:

- ◆ Telephone 1 can call all other telephones consecutively.
- ◆ Telephone 4 can call all other telephones consecutively.
- ◆ Telephones 1, 2, 3, and 4 can answer calls as many times as they get the event `evRing` (as specified in the activation condition of the “Answering_Call” sequence diagram).


Driver-Assisted Monitor

The following examples show how to use driver-assisted monitors.

Example 1: Monitors and Drivers Specified as Sequence Diagram

This example shows how to define a combination of drivers and monitors. The “Driver_Assisted_Monitor” test configuration contains instances of the “Receive_X” sequence diagram (see page 167) and the “X_calls_Y” sequence diagram (see page 168). The sequence diagram instances have the following settings:

- ◆ Four instances (Receive_1, Receive_2, Receive_3, and Receive_4) of the “Receive_X” sequence diagram are specified as driver and monitor with linear order and multiple iteration. Their parameter mappings correspond to Telephones 1, 2, 3, and 4 and Lines 1, 2, 3, and 4, respectively.
- ◆ Four instances (“Tel_1 calls Tel_2”, “Tel_2 calls Tel_3”, “Tel_3 calls Tel_4”, and “Tel_4 calls Tel_1”) of the “X_calls_Y” sequence diagram are specified as monitor only with partial order, single iteration, and the corresponding parameter mappings. The following figure shows the example of the parameter mapping for the “Tel_2 calls Tel_3” sequence diagram instance.




The test checks that every telephone can call the next telephone, and the telephone can reply and finish the communication. This test can be done for every specified pair of the telephones, independent of the order of the pairs. During test execution, you must drive

the model manually, as specified in the instances of the “X_calls_Y” sequence diagram. TestConductor completes the execution of the instances of the “Receive_X” sequence diagram whenever they have been activated.

Example 2: Unspecified Manual Driving

You can drive your model manually in an order not specified in any sequence diagram. This means that you do not check this part of a behaviour. For example, you can specify only communications between actor instances and internal objects when the actors have behaviour (code has been generated for them). The following sequence diagram shows such a specification for a new model. In this case, the new events `evSuspend` and `evRestart` are sent to the `Line` class from the `Administrator` actor.



The following “Check Administrator” test configuration defines a driver with an instance of the “testActor” sequence diagram.

```

TEST:      Check Administrator
COMMENT:   "First Administrator sends events to Line 1.
After that User can make a call from Telephone 1."

INSTANCES:
-----

1. Tel1 calls Tel2
COMMENT: ""
DEFINITION:
    SD <testActor>, DRIVER, LINEAR, SINGLE ITERATION
    AC <TRUE>
        PARAMETERS:
            callersLine = PBX[0]->itsLine[0],
            caller = PBX[0]->itsTelephone[0],
            nr2 = 2


```

This test checks that a new feature added to the system as the `Administrator` behaviour does not change the main behaviour of the model (in other words, `User` can make a call as previously specified). During test execution, you must inject input events for `Administrator` and `User` to stimulate them to send events specified in the “testActor” sequence diagram. `TestConductor` monitors all messages between the actors and internal objects specified in the sequence diagram under test.

Choosing Between Alternatives in a Cycle


The predecessor ordering of sequence diagram instances provides a means to construct a tree or a forest (set of trees) of the related sequence diagram instances, but does not allow any cycle or choice between alternatives. Activation conditions/condition marks serve as another way to set causal dependencies between sequence diagram instances. The following test configuration explains how to combine predecessor ordering with multiple iteration to specify cycles with choice.

Consider the “X_and_Y_call_together” sequence diagram, with partial order interpretation.




The specification says that two telephones can dial any numbers independently of each other whenever the environment sends them the `evOffHook` event. If these telephones call each other (specified by the corresponding mapping of the parameters `nr1` and `nr2`), the continuation depends on the order in which you have injected events from the environment to the telephones. A callee can be busy or answer the call.

The “Stop_Busy_Call” sequence diagram, shown in the following figure, specifies that a caller put the telephone on the hook if it gets the `evBusy` event. The “Busy_or_Free” test includes instances of the “X_and_Y_call_together” sequence diagram, the “Stop_Busy_Call” sequence diagram, and the “Answering_Call” sequence diagram.



The following figure shows the corresponding settings in the **Define Test** dialog.



The following information file of the test case definition summarizes the complete test description.

```

TEST: MainFolder\Busy_or_Free\
COMMENT: "Tel2 and Tel3 call each other at the same or different
time. Check whether a call free or busy."

INSTANCES:
-----
1. Tel2 stops
COMMENT: ""
DEFINITION:
SD <STOOP_Busy_Call>, DRIVER, LINEAR, MULTIPLE ITERATIONS
AC <TRUE>
PARAMETERS:
CLine = PBX[0]->itsLine[1],
nr1 = PBX[0]->itsTelephone[1]

2. Tel3 stops
COMMENT: ""
DEFINITION:
SD <STOOP_Busy_Call>, DRIVER, LINEAR, MULTIPLE ITERATIONS
AC <TRUE>
PARAMETERS:
CLine = PBX[0]->itsLine[2],
caller = PBX[0]->itsTelephone[2]

3. Tel2 answers
COMMENT: ""
DEFINITION:
SD <Answering_Call>, DRIVER, LINEAR, MULTIPLE ITERATIONS
AC <receiversLine->ES(receiver, evRing())>
PARAMETERS:
receiversLine = PBX[0]->itsLine[1],
receiver = PBX[0]->itsTelephone[1]

4. Tel3 answers
COMMENT: ""
DEFINITION:
SD <Answering_Call>, DRIVER, LINEAR, MULTIPLE ITERATIONS
AC <receiversLine->ES(receiver, evRing())>
PARAMETERS:
receiversLine = PBX[0]->itsLine[2],
receiver = PBX[0]->itsTelephone[2]

5. Tel2 and Tel3 call
COMMENT: ""
DEFINITION:
SD <X_and_Y_call_together>, MONITOR, PARTIAL, MULTIPLE
ITERATIONS
AC <TRUE>
PARAMETERS:
callersLine2 = PBX[0]->itsLine[2],
caller1 = PBX[0]->itsTelephone[1],
caller2 = PBX[0]->itsTelephone[2],
nr1 = 3,
nr2 = 2,
callersLine1 = PBX[0]->itsLine[1]

```

The test checks the following:

- ◆ Telephone 2 and Telephone 3 call each other independently.
- ◆ If a callee (Telephone 2 or Telephone 3) is free, it answers the call.
- ◆ If a callee is busy, the caller hangs up.

You can execute the test continuously, injecting events to Telephone 2 and Telephone 3. TestConductor monitors the “Tel2 and Tel3 call” sequence diagram instance and drives the remaining ones, selecting those relevant to the current situation. Note that the instance of the “X_and_Y_call_together” sequence diagram is the predecessor for the remaining four instances in the test configuration. This means that the sequence diagram instances “Tel2 stops”, “Tel3 stops”, “Tel2 answers”, and “Tel3 answers” can be activated only after the Tel2 and Tel3 call instance has been activated and partially traversed. This order (and the choice between alternatives) is specified with the activation conditions and Condition Marks, but become valid only after the parameters have been bound to the corresponding names.

User Defined Driving Operation Calls (for Rhapsody in C/C++/Java/Ada)

The default implementation of a driver operation generated by TestConductor may be overwritten and customized by the user, by stereotyping the message with stereotype <<RTC_MsgInfo>> in the sequence diagram and setting the corresponding values for the tags

```
TestBehavior::RTC_MsgInfo::RTC_DriverCallCode,
TestBehavior::RTC_MsgInfo::RTC_DriverCallCodeAdditional,
TestBehavior::RTC_MsgInfo::RTC_DriverInitCode,
TestBehavior::RTC_MsgInfo::RTC_DriverInitCodeAdditional,
```

Message : evStart	
General Description Relations Tags Properties	
[-] TestBehavior	
[-] RTC_MsgInfo	
RTC_DriverCallCode	
RTC_DriverCallCodeAdditional	
RTC_DriverInitCode	
RTC_DriverInitCodeAdditional	
RTC_Monitor	<input checked="" type="checkbox"/>
RTC_MsgId	
RTC_Receiver	
RTC_StubBodyCode	

Usually, if the user modifies driver operations in the model, then this information is lost if the user updates a test case. The user can influence the generated code for driver operations and stub operations. Using the tags

```
TestBehavior::RTC_MsgInfo::RTC_DriverCallCode,
TestBehavior::RTC_MsgInfo::RTC_DriverCallCodeAdditional,
TestBehavior::RTC_MsgInfo::RTC_DriverInitCode,
TestBehavior::RTC_MsgInfo::RTC_DriverInitCodeAdditional,
```

the content of these tags is not lost during update of a test case.

The value for `RTC_DriverInitCode` is taken as the beginning of the driver operation body containing the initialization of necessary variables, whereas the value for `RTC_DriverCallCode` is taken as the trailing part of the driver operation body containing the call of the function to be driven.

```
void SD_tc_0_evBarcode_1()
{
    01 /*****
    02     DriverOperation generated by TestConductor
    03
    04     TestCase   : SD_tc_0
    05     Message    : message_2
    06
    07     The Driver Initialisation Code contains the value of the
    08     Message Tag TestBehavior::RTC_MsgInfo::RTC_DriverInitCode,
    09     if the Tag value is not empty. Otherwise, the Driver
    10     Initialisation Code is automatically generated.
    11
    12     The Driver Call Code contains the value of the
    13     Message Tag TestBehavior::RTC_MsgInfo::RTC_DriverCallCode,
    14     if the tag value is not empty. Otherwise, the Driver
    15     Call Code is automatically generated.
    16 *****/
    17
    18 //-----
    19 // Driver Initialisation Code:
    20 //-----
    21
    22 int osc_arg_1 = 12345;
    23 //-----
    24 // Driver Call Code:
    25 //-----
    26
    27 OUT_PORT(hw) -> GEN(evBarcode(osc_arg_1));
    28
}
```

Note that both properties can be overwritten separately by the user. In case the user wants to customize the initialization section only, only the property `RTC_DriverInitCode` has to be overwritten; TestConductor will continue to automatically generate the code for the driver call section (and vice versa).


The value for `RTC_DriverInitCodeAdditional` is taken as additional initialization code that is generated in addition to the initialization code generated by TestConductor.

The content of this tag is generated directly after the auto generated initialization code. Similarly, the value for `RTC_DriverCallCodeAdditional` is taken as additional call code that is generated in addition to the auto generated call code. The content of this tag is generated directly after the auto generated call code.

RTC_DriverInitCode and RTC_DriverInitCodeAdditional

The user can influence the initialization of arguments before the message is driven using the tags `RTC_DriverInitCode` and `RTC_DriverInitCodeAdditional`. To do this uses have to add the stereotype `RTC_MsgInfo` to the SD message. This adds automatically the tags `RTC_DriverInitCode` and `RTC_DriverInitCodeAdditional` to the message. The user can fill these tags with code which will be used as initialization code of the driver operation when the test case is updated. Important is that the context of `RTC_DriverInitCode` completely replaces the initialization code that would be generated by TestConductor automatically, whereas the content of `RTC_DriverInitCodeAdditional` is simply added to the auto generated initialization code.

In some cases it is advisable that the user copies all or the needed parts of the automatically generated *driver initialization code* section and paste it into the tag `RTC_DriverInitCode` before starting to implement his own changes.




RTC_DriverCallCode and RTC_DriverCallCodeAdditional

The user can also influence the call of the driven operation using the tags `RTC_DriverCallCode` and `RTC_DriverCallCodeAdditional`. To do this he users have to add the stereotype `RTC_MsgInfo` to the sequence diagram message. This adds automatically the tags `RTC_DriverCallCode` and `RTC_DriverCallCodeAdditional` to the message. The user can fill these tags with code which will be executed after the initialization of arguments. Important is that the content of `RTC_DriverCallCode` completely replaces the code that would be used to invoke the driven operation if TestConductor generated the code automatically, whereas the content of `RTC_DriverCallCodeAdditional` is simply added to the auto generated call code.


Note, in this scenario the user has the responsibility that the sequence diagram test case is indeed executable after customization. Basically, the specified message of the sequence diagram test case, which now is present as source code, has to be represented in the user defined code.

In some cases it is advisable that the user copies all or the needed parts of the automatically generated *driver call code* section and paste it into the tag `RTC_DriverDriverCode` before starting to implement his own changes.



Clean TestComponent

Driver and stub operations can be deleted manually, but TestConductor provides the functionality to delete the automatically generated operations of a test component at once. To clean a test component select the test component und choose from the context menu the item **Clean TestComponent**.



Clean TestPackage


Driver and stub operations can be deleted manually, but TestConductor provides the functionality to delete the automatically generated operations of all test components of a TestPackage at once. Furthermore, **Clean TestPackage** also deletes all results and coverage results from the TestPackage.

To clean a test package select the test package and choose from the context menu the item **Clean TestPackage**.

To regenerate the driver and stub operations select the test case or the test context or the test package and choose from the context menu the item **Update TestCase/TestContext/TestPackage**.

Deleting User Defined Driver Operation Calls

TestConductor uses user defined operation calls if the tags `TestBehavior::RTC_MsgInfo::RTC_DriverInitCode` and `TestBehavior::RTC_MsgInfo::RTC_DriverCallCode` are not empty, even if the tags are overwritten. To delete the user defined operation call and use the auto generated driver operations from TestConductor, reset the tags to delete the content of the tag.



User Defined Stub Operation Calls (for Rhapsody in C/C++/Java/Ada)


Stub operations are created for any operation call in the sequence diagram going from the SUT to a test component if the following items are all true:

- ◆ a return value (or a returned value for an out or in/out argument) is specified for this operation
- ◆ the tag `TestConductor::RTC_MsgInfo::RTCMonitor` for the sequence diagram message is set to false
- ◆ the tag `TestConductor::RTCInstInfo::RTCMonitor` for the To-sequence diagram instance line is false

TestConductor needs the ability to determine and control the value returned by the operation. On the other hand there might be calls to the same operation without a specified return value or the operation is called by a test component on a test component: because of this TestConductor has to generate a different body for the operation, but it must still be possible to call the original operation.

To ensure this, TestConductor creates a copy of the original operation with the name `original_` followed by the operations name, having the same signature. In the implementation body of this so called *DefaultOperation* the original function is called non-virtually. For every occurrence of the operation where it should be stubbed, a new operation is added to the test component with the same signature of the original operation. This so called *StubOperation* returns the specified return value, out and in/out arguments. The name of the stub operation is the concatenation of the name of the test case, the string `"_stub_"`, the name of the original operation followed by a number to make it unique.

The body of the original operation is deleted completely and a new implementation is generated this way: The operation does a call to a special TestConductor operation and uses the `OMString` value returned by TestConductor in a switch statement to select which operation should be called. If a stub operation has to be invoked TestConductor returns its GUID, if the original operation has to be called TestConductor returns an empty string.



The actual values of formal parameters defined for the sequence diagram or sequence diagram instance are propagated to the stub operation this way: If any parameter is used in the return value or out or in/out arguments of the operation that has to be stubbed, then in the body of the stub operation this parameter is exchanged with the value of the parameter.

RTC_StubBodyCode

Normally, if the user modifies stub operations in the model, then this information is lost if the user updates a test case. The user can influence the code of the stub using the tag `RTC_StubBodyCode`. To do this he has to add the stereotype `<<RTC_MsgInfo>>` to the sequence diagram message, this adds automatically the tag `RTC_StubBodyCode` to the message. The user can fill this tag with code which will be used as body of the stub operation when the test case is updated. Important is that this code completely replaces the body that would be generated by TestConductor automatically.

An important limitation is: only virtual operations can be stubbed. Since the SUT is implemented, in the SUT code operations of other design classes are called. For instance, a class A which is the SUT class may call a operation “f” of a class B. Now, in a given test architecture, a new test component class BT is introduced that inherits from B in order to be able to use an instance of class BT instead of an instance of class B directly. However, the SUT code still calls the operation “f” of B, since the SUT code remains untouched. But when “f” is a virtual operation, the virtual dispatching mechanism of *UML* ensures that the most specialized variant of the operation is called, i.e., if class BT implements a new version of the called operation “f”, then this function is called. This function can be stubbed, since it is defined in the testing component BT. However, if the SUT calls a non-virtual function, it cannot be stubbed since this operation is in general not defined in a testing component.


If an operation is stubbed multiple times in the same test component in the same sequence diagram instance, then for each occurrence an individual stub operation is generated.

If an operation is stubbed multiple times in the same test component in the same SUT in different test cases respectively sequence diagram instances, then for each occurrence an individual stub operation is generated.

Tip: In case TestConductor has not created stub operations for a sequence diagram message, the at the beginning mentioned conditions are not fulfilled. To “inspire” TestConductor to create such stubbing functionality anyhow, the user can define “*” as expected return value for the sequence diagram message followed by an update on the test case. In some cases TestConductor will then create the customizable stubbing functionality as shown in the above picture.

Clean TestComponent

Driver and stub operations can be deleted manually, but TestConductor provides the functionality to delete the automatically generated operations of a test component at once. To clean a test component select the test component and choose from the context menu the item **Clean TestComponent**.



Clean TestPackage

Driver and stub operations can be deleted manually, but TestConductor provides the functionality to delete the automatically generated operations of all test components of a TestPackage at once. To clean a test package select the test package and choose from the context menu the item **Clean TestPackage**.

To regenerate the driver and stub operations select the test case or the test context or the test package and choose from the context menu the item **Update TestCase/TestContext/TestPackage**.

Deleting User Defined Stub Operation Calls

TestConductor uses user defined operation calls if the tags

`TestBehavior::RTC_MsgInfo::RTC_StubBodyCode` are not empty, even if the tags are overwritten. To delete the user defined operation call and use the auto generated stub operations from TestConductor, reset the tags to delete the content of the tag.

Using Test Actions in SD Test Cases

In the previous section, the tags of the `<<RTC_MsgInfo>>` stereotype have been used in order to customize the driver code and stub code generation of TestConductor. Alternatively, the same can be done in a more graphical fashion by using so-called test actions. A test action is an action that can be placed on one of the test component life lines in the sequence diagram. The test action contains code that is considered by TestConductor when the model is populated with test code, and it can be used to e.g.

- ◆ create complex input data
- ◆ access e.g. global variables of the test architecture
- ◆ create complex checks for complex output values
- ◆ define complex behavior of stubs


In order to support the use cases mentioned above, TestConductor provides the following kinds of test actions:

- ◆ A general test action: a general test action is a sequence of statements that is executed by TestConductor if test execution reaches the test action. In order to define a general test action, just add a test action block to one of the test component lifelines in the test scenario. In contrast to the message-related test actions described further below, a general test action is not related to another message in the test scenario.
- ◆ `<InitAction>`: An init action is a test action that can be used to initialize test data. The code contained in the init action is handled as the tag `RTC_DriverInitCode` of the stereotype `<<RTC_MsgInfo>>` (cf. section “`RTC_DriverInitCode` and `RTC_DriverInitCodeAdditional`” on page 201).
- ◆ `<PreCallAction>`: A pre call action is a test action that can be used to either initialize test data or to do some other test related activities before a message is sent from a test component to a SUT instance. The code contained in the pre call action is handled as the tag `RTC_DriverInitCodeAdditional` of the stereotype `<<RTC_MsgInfo>>` (cf. section “`RTC_DriverInitCode` and `RTC_DriverInitCodeAdditional`” on page 201).
- ◆ `<CallAction>`: A call action is a test action that can be used to call a particular operation or to send a particular event. The code contained in the call action is handled as the tag `RTC_DriverCallCode` of the stereotype `<<RTC_MsgInfo>>` (cf. section “`RTC_DriverCallCode` and `RTC_DriverCallCodeAdditional`” on page 202).


- ◆ **<PostCallAction>**: A post call action is a test action that can be used to perform any kind of actions after a particular call to an operation or a sending of an event, e.g. code for checking output values of the called operation. The code contained in the call action is handled as the tag `RTC_DriverCallCodeAdditional` of the stereotype `<<RTC_MsgInfo>>` (cf. section “RTC_DriverCallCode and RTC_DriverCallCodeAdditional” on page 202).
- ◆ **<StubAction>**: A stub action is a test action that can be used to define the behavior of stubbed operations, e.g. checking arguments of the called operation or returning specific values. The code contained in the stub action is handled as the tag `"RTC_StubBodyCode"` of the stereotype `<<RTC_MsgInfo>>` (cf. section “RTC_StubBodyCode” on page 205).

In order to add a test action to a sequence diagram test case, do the following:

- ◆ On the test scenario toolbar, select the the test action icon
- ◆ Place the test action on one of the test component life lines in the test scenario



After adding the test actions to the test scenario, one has to update the test case (select “Update TestCase” on the test case. After the update, the test actions are populated into the driver operations and stub operations in the model. For instance, the `<PostCallAction>` in the test scenario depicted above is populated to the driver operation for the message “f2” that is specified directly above the `<PostCallAction>`:



After building the test case, the test case can be executed. The code in the test actions is executed when the test case reaches the specified test actions. For instance, the assertion specified in the <PostCallAction> of the test scenario depicted above is executed directly after the message “f2” was called on the SUT. If the assertion fails, after doing “Show as SD” one can see that the specified assertion has failed.

As an example of how to use test actions for specifying the behavior of SD test cases, please have a look at the sample “CppTestActions” in the folder “Samples/CppSamples/TestConductor”

Using Interaction operators in sequence diagram test cases (only assertion based testing mode)


In assertion based testing mode (if TestConductor.Settings.TestingMode == AssertionBased), so-called interaction operators can be used in specifying the behavior of a test case. TestConductor supports the following SD interaction operators

- Opt
- Alt
- Loop
- Break
- Consider
- Parallel


As an example of how to use interaction operators for specifying the behavior of SD test cases, please have a look at the sample “CSDOperators” in the folder “Samples/Csamples/TestConductor”

Black-Box Testing of External Files and Libraries

TestConductor comes with the C++ sample CppTestingExternalFiles. This project contains the package PkgUseExternalFiles, where two files are defined. The declared external file ExternalFile_ArithmeticCPP consists of a source file arithmetic.cpp and the corresponding header file arithmetic.h. The file ExternalLib_LogicLib consist of the library LogicLib.lib and a corresponding header file LogicLib.h. Further information on how to define files can be found in the *Rhapsody User Guide*.



Open the feature dialog of a file, select the Properties tab and browse the overwritten properties of ExternalFile_ArithmeticCPP.



CG.Class.UseAsExternal is set to TRUE.

CG.Class.FileName determines the basename of the referenced external file. This property defines ExternalFile_ArithmeticCPP to refer to arithmetic.h in the project's ExternalSrc-directory.

CPP_CG.Class.Animate is set to FALSE. Whatever the library or the external source file contains Rhapsody animated code, the property has to be set to FALSE. Setting this property to FALSE means, that the file, which will become in this example the SUT, will not be animated. Furthermore, disabling the animation of the SUT means to perform a black-box test.


In order to use external header and implementation in code-generation, component `UseExternalFiles` defines the additional include-path `"../.."`, which refers to the project's root-directory. The implementation of the external functions is made available to code-generation by defining additional source `"../..../ExternalSrc/arithmetic.cpp"`. In order to link the library the configuration `UseExternalFiles::Default` defines under **Libraries** `"../..../LogicLib/NotInstrumented/LogicLib.lib"`.

To use this example and the provided test cases in the test packages `TPkg_ExternalFile_ArithmeticCPP` and `TPkg_ExternalLib_LogicLib` the user has first to generate/build the `LogicLib.Lib` and the header file `LogicLib.h`. Browse the package `PkgLogicLib`, set the containing configuration `LogicLib::NotInstrumented` active and build the configuration by using the **Generate/Make/Run** button.

Test Packages

The example comes with pre-defined test architecture for the file `ExternalFile_ArithmeticCPP`. The test architecture was created as follows:


For testing external file `ExternalFile_ArithmeticCPP`, select `ExternalFile_ArithmeticCPP` and choose **Create TestArchitecture** in the context menu. A new test package `TPkg_ExternalFile_ArithmeticCPP` will be created




In order to make test context

`TPkg_ExternalFile_ArithmeticCPP::TCon_ExternalFile_ArithmeticCPP` compilable and linkable, the user has to modify code generation component `TPkg_ExternalFile_ArithmeticCPP::TPkg_ExternalFile_ArithmeticCPP_Comp`:

1. enter `"../..../ExternalSrc/arithmetic.cpp"` into entry **Additional Sources** in the **General** tab.
2. extend the include path in entry **Include Path** to `"$(OMROOT)/../TestConductor,../.."`




The example comes with a pre-defined test architecture for the file ExternalFile_ArithmeticCPP and the library ExternalLib_LogicLib. Also the following sequence diagram test cases have already been defined:




To execute the test case SD_tc_0 select the test case in the Rhapsody browser and choose from the context menu **Update Test Case, Build Test Case, Execute Test Case**. In the TestConductor execution dialog click on the button **Activate Test**. TestConductor shows that the test case SD_tc_0 passed. For further information select in the TestConductor execution dialog the entry SD_tc_0 and click on the button **Show as SD**. The animated


sequence diagram displays the text execution result and states, that all return values occurred as specified.



Now execute the test case SD_tc_0 in the test context TCon_ExternalLib_LogicalLib. The test will fail and the **Show As SD** sequence diagram will state, that the check of the return value failed.



Open the test scenario SDTestScenario_0 of test case SD_tc_0 in the test context TCon_ExternalLib_LogicalLib.




The expected value in the expression “0=lNot (a=0)” is wrong. The correct return value has to be “1=lNot (a=0)”. Correct the test scenario and re-run the test. It will pass.

Using Serialize/Unserialize Functions for User Defined Types


Rhapsody can animate (display) the values of simple types and one-dimensional arrays. However, if you want to animate a more complex type, the type must be converted to a string (char *) for Rhapsody to display it. This can be done generally in two different ways, either by using auto-generated serialization/unserialization functions or by using manually defined serialization/unserialization functions.

Using auto generated serialization /unserialization functions

For enum types and structure types that are explicitly defined in the model, Rhapsody provides the possibility to use automatically generated serialization/unserialization functions in order to display values of these types e.g. in animated sequence diagrams. In order to use the auto generated serialization/unserialization functions for a specific type that is defined in the model, the property “<Lang>.Type.GenerateSerializationFunctions” must be set to “SerializationAndUnserialization”:



If this property is set correctly, for arguments with enum type one can use the literals of the enum definition in the test scenarios, and for arguments with structure type one can specify each attribute defined in the structure type. The following test scenario shows two message “f” and “g” that both have two arguments, one of enum type and one of a structure type:



Using manually defined serialization /unserialization functions


Besides using the auto generated serialization/unserialization functions of Rhapsody, one can also manually define serialization/unserialization functions. These functions are global

instrumentation functions, that takes one argument of the type you want to display, and returns a char *. Further information can be found in the chapter *Guidelines for Writing Serialization Functions* of the Rhapsody User Guide. The usage of serialization functions for Testing is demonstrated by the sample model “Samples/CppSamples/TestConductor/CppListUsage”. Please note that serialization functions can only be used for testing purposes if the type that should be serialized is selected directly as an “existing type” in Rhapsody. If only the type signature is used to specify the type of an argument type or return type, serialization functions cannot be used for testing.


In case of non fault tolerant programming of these (un-)serialize function the application/model may probably work during normal operation, but can crash, if the user executes a test case on the same model. The following example shows a Sting32 type.



The user defined the following serialize function:



And connected it correctly to the corresponding property




During normal operation everything will work properly. But during execution of a test case on the unchanged model the execution will crash.



The reason for the crash is the serialization function for String32, it causes a crash if it is called with a not initialized string. If TestConductor registers as an observer the framework notifies TestConductor about operation calls. To do this the framework serializes the arguments of the constructor (== conversion to string).

If the serialize function for String32 is modified this way the application will not crash:



Failure Analysis

TestConductor detects and reports a *failure* if a message contained in the message set of a sequence diagram does not appear in the specified order or if a *RTC_ASSERT* isn't fulfilled during test execution. A message from the message set is specified by its name, the value(s) of its argument(s), the names of sending and receiving objects.

Failure analysis is an important but sometimes difficult task. This is due to the fact that industrial-sized models show very complex behavior, with many messages flowing during test execution.

All possible failures monitored by TestConductor can be caused:

1. By errors in the model – the computed model behavior does not meet requirements specified by an sequence diagram
2. By inconsistencies in the test configuration or/and in the requirements

In case of using sequence diagrams for test definitions, the task of model debugging is simplified by using TestConductor's graphical failure reports. You can use a combination of diverse Rhapsody analysis capabilities (for example, state chart animation, sequence diagram animation, and sequence diagram comparison) with TestConductor to show test executions as sequence diagrams. The colors and percentage information in the **Execute Test** dialog are useful indicators in determining where the failure occurred.

Remember that during model execution TestConductor ignores all messages which are not specified in the sequence diagram instances of the executed test. This implies that TestConductor meets failure in the following two cases:

3. The real order of message actions during model execution does not correspond to specifications in sequence diagram instances.
4. The real argument values of messages during model execution do not correspond to those specified in sequence diagram instances.

During test compilation, TestConductor translates every sequence diagram instance into internal sequence(s) of message actions specified in the sequence diagram instance. As you activate a test, TestConductor starts the model execution and creates the first iteration copies of sequence diagram instances without specified ordered predecessors as the original run-time instances. During test execution, TestConductor checks the activation condition of each created run-time instance until it gets value `TRUE` (that is a run-time instance becomes active). After that, TestConductor checks every messages appearing in the model execution. For every currently active run-time instances from the **Execute Test** dialog, it compares the following:

1. Whether the current message belongs to the message set of the corresponding sequence diagram.

2. Whether all message actions preceding the current message in the corresponding run-time instance have already occurred.

If the first condition does not hold, TestConductor ignores the current message. If both conditions hold, TestConductor marks the current message as green. If only the first condition is fulfilled – one or more actions preceding current one in the corresponding run-time instance have not yet appeared in the model execution – TestConductor creates a red message, reports failure and stops to traverse the run-time instance with erroneous message action. After that it continues to generate run-time instances with respect to the specified execution mode, check activation conditions and new message actions.

Failure Reporting

TestConductor draws a green horizontal message arrow for operation calls that have been monitored. Events that have been monitored in-order are drawn as slanted messages as in sequence diagram animation. The starting point of the slanted message is where the event has been sent. The end point refers to the point where this event must be consumed according to the original sequence diagram specification.

Note: In our green, blue, red approach one could consider the dashed line as half-green (event has been sent) and half-blue (consumption not yet monitored).

Following classes of errors can be detected by TestConductor:

1. Sending out of order
2. Event Sending - Parameter values do not match
3. Event Sending - Parameter values not in range
4. Consumption out of order
5. Event Consumption - Parameter values do not match
6. Event Consumption - Parameter values not in range
7. Operation Call out of order
8. Operation Call - In Parameter values do not match
9. Operation Call - In Parameter values not in range
10. Operation Call returned - Return value does not match
11. Operation Call returned - Out Parameter values do not match
12. Operation Call returned - Out Parameter values not in range
13. DataFlow Message - Value does not match
14. DataFlow Message - Value not in range
15. DataFlow Message out of order
16. Assertion failed


TestConductor draws a red horizontal message to visualize a failure. The red arrow refers to a point where a message was monitored out-of-order or where parameter values did not match. The red message is labeled with a text (M() represents the failed message):

- ◆ M():Sending out of order
- ◆ M():Event Sending - Parameter values do not match
- ◆ M():Event Sending - Parameter values not in range
- ◆ M():Consumption out of order
- ◆ M():Event Consumption - Parameter values do not match
- ◆ M():Event Consumption - Parameter values not in range
- ◆ M():Operation Call out of order
- ◆ M():Operation Call - In Parameter values do not match
- ◆ M():Operation Call - In Parameter values not in range
- ◆ M():Operation Call returned - Return value does not match
- ◆ M():Operation Call returned - Out Parameter values do not match
- ◆ M():Operation Call returned - Out Parameter values not in range
- ◆ M():DataFlow Message - Value does not match
- ◆ M():DataFlow Message - Value not in range
- ◆ M():DataFlow Message out of order
- ◆ M():Assertion <SD_instance_X: message Y> failed

TestConductor draws blue messages for messages that have not yet monitored, neither sending nor consumption of events. Such a drawn sequence diagram contains the original sequence diagram specification used for the test. All green and blue messages represent the messages of the original sequence diagram. Green and blue messages, together with the red arrow make failure analysis much easier. If the red message is erased, then the drawn sequence diagram can be used to reproduce the same failure.

Note: Red messages can not be erased automatically from a failure sequence diagram used in a new test. Workaround is to erase it manually if such a sequence diagram shall be used in a test. Following samples explain the failure cases.

Event sending out-of-order




In this example, according to the specification: TestConductor must

1. Monitor the self message `OpenConnection()`
2. Monitor the operation call `OpenConnection()`
3. Monitor the sending of `evDialTone()`
4. Monitor the sending of `evOriginateCall()`


TestConductor sees, sending of event `evOriginateCall()` occurs before the sending of `evDialTone()`. Thus TestConductor gives the warning "Sending out of order".

Event sending in-order, but parameter values do not match




In this example, according to the specification, TestConductor must monitor the event `evDigitDialed(Digit = 1)`, but TestConductor is seeing `evDigitDialed(Digit = 2)`. Thus TestConductor reports a failure "Event Sending -Parameters values do not match"

Event sending in-order, but parameter values not in range



In this example, according to the specification, TestConductor must monitor the event `evDigitDialed(Digit = 1)`, but TestConductor is seeing `evDigitDialed(Digit = [3..5])`. Thus TestConductor reports a failure “Event Sending - Parameters values not in range”.

Event consumption out-of-order



In this example, according to the specification, TestConductor must monitor

1. The operation call `OpenConnection()`
2. The sending of `evOriginateCall()`
3. The sending of `evDialTone()`
4. The consumption of `evDialTone()`
5. The consumption of `evOriginateCall()`

TestConductor sees consumption of `evOriginateCall()` before the consumption of `evDialTone()`. Thus TestConductor gives the warning "Consumption out of order".

Event consumption in-order, but parameter values do not match





Figure 1: SD with message “Event Consumption – Parameter value do not match”

In this example, according to the specification, TestConductor must monitor

1. The sending of `evDigitDialed(Digit=1)`
2. The sending of `evDigitDialed(Digit=2)`
3. The consumption of `evDigitDialed(Digit=2)`
4. The consumption of `evDigitDialed(Digit=1)`

TestConductor sees, event consumption of `evDigitDialed()` came in-order, but the value of the parameter does not match. Thus TestConductor gives the warning “Event Consumption - Parameter values do not match”.

Event consumption in-order, but parameter values not in range




In this example, according to the specification, TestConductor must monitor

1. The sending of `evDigitDialed(Digit=[0..1])`

2. The sending of `evDigitDialed(Digit=[2..3])`
3. The consumption of `evDigitDialed(Digit=[2..3])`
4. The consumption of `evDigitDialed(Digit=[0..1])`

TestConductor sees, event consumption of `evDigitDialed()` came in-order, but the values in the event consumption does not fall in range specified. Thus TestConductor gives the warning “Event Consumption - Parameter values not in range”.

Operation call out-of-order



In this example, according to the specification above, TestConductor must monitor

1. The self message `OpenConnection()`
2. The sending of `evOriginateCall()`
3. The operation call `openConnection()`

Operation call `OpenConnection()` from Line to CallRouter should occur after sending of the event `evOriginateCall()`. Thus TestConductor reports the failure "Operation Call out of Order".

Operation call in-order, but parameter values do not match




Figure 2: SD with message “Operation call – In Parameter value do not match”



In this example, according to the specification, TestConductor

1. Should monitor the operation call DialingDone()

2. Must monitor the operation call `NextDigit (Digit=2)`

TestConductor sees that operation call `NextDigit (Digit=1)` instead of operation call `NextDigit (Digit=2)`. Here the operation call has come in order but the parameter value is incorrect. Thus TestConductor gives the warning “Operation Call:In Parameter values do not match”.

Operation call in-order, but parameter values not in range




In this example, according to the specification, TestConductor

1. Should monitor the operation call `DialingDone()`
2. Must monitor the operation call `NextDigit(Digit=2)`

TestConductor expects operation call `NextDigit(Digit=[3..4])` as specified in the tolerance in the test definition, but sees operation call `NextDigit(Digit=2)` which is out of the range. Here the operation call has come in order but the parameter value is incorrect. Thus TestConductor gives the warning “Operation Call:In Parameter values not in range”.

Operation call returned - Return value does not match



Here TestConductor expects a return value of 5 as of the specification but sees a 4. Thus TestConductor gives the warning message “4=op_int(a=1,b=2,c=3) Operation Call returned - Return value does not match. Expected values are: 5=op_int(a=1,b=2,c=3)”

Operation call returned - Out Parameter values do not match





Figure 3: SD with message “Operation call returned – Out Parameter value do not match”


Here TestConductor expects a value of 3 as of the specification but sees 1. Thus TestConductor gives the warning message “4=op_int(a=1,b=2,c=3) Operation Call returned - Out Parameter values do not match. Expected values are: 4=op_int(a=3,b=2,c=3)”

Operation call returned - Out Parameter values not in range




Here TestConductor expects the value in the range of `[3..4]` as of the specification but sees `1`. Thus TestConductor gives the warning message “`4=op_int(a=1,b=2,c=3)` Operation Call returned - Out Parameter values not in range. Expected values are: `4=op_int(a= [3..4],b=2,c=3)`”

DataFlow Message - Value does not match




TestConductor expects dataflow ‘`y=8`’ but actually observed ‘`y=7`’.

DataFlow Message - Value not in range




TestConductor expects `y` to be within range `[8..10]` but actually observed '`y=7`', i.e. outside the expected range.

DataFlow Message out of order



TestConductor expects dataflow order '`z=6`' before '`y=6`' but actually observed '`y=6`' before '`z=6`'.

Assertion failed



When using test components to call operation from a SUT, TestConductor can observe return values from this operation via an assert marco. TestConductor automatically generates the *RTC_ASSERT_SD* macro in the driver operation of the test component:

```
//-----
// Driver Initialisation Code:
//-----


int osc_ret;
int osc_arg_1 = 5;
//-----
// Driver Call Code:
//-----

osc_ret = itsA->f(osc_arg_1);
RTC_ASSERT_SD("SD_tc_0", "message_0", osc_ret==7);
```

In this test scenario TestConductor expects a return value of 7 when calling f(I=5) on the SUT, but the actual returned value is different. Thus, TestConductor gives the warning message “Assertion <SD_tc_0:message_0>”. The second message “f(i=5) Operation Call did not return yet.” Occurs, because TestConductor interrupts the execution after detecting a failing assertion.

Using TestConductor from Eclipse

As an alternative to the standalone Rhapsody application, Rhapsody can also be used directly from Eclipse (v. “eclipse_platform_user_guide.pdf” in doc/pdfbooks). Also TestConductor can be used directly from Eclipse. In general, all TestConductor functionality can be used when working with Eclipse. Similar to the standalone Rhapsody application, almost all TestConductor functionality is available in context menus of Rhapsody elements, and this holds also when working from Eclipse as can be seen in the following picture:



However, there are some differences that needs to be considered when using TestConductor from Eclipse:

- In contrast to executing TestConductor from the standalone Rhapsody application, the test execution windows of TestConductor are not always in front of the Eclipse main window. Selecting the Eclipse main window may hide the TestConductor test execution windows.
- In Eclipse, when creating a new test architecture, TestConductor automatically creates a new Eclipse configuration instead of a normal Rhapsody configuration. Additionally, TestConductor automatically launches the Eclipse New Project Wizard that can be used to create a new Eclipse project that is connected to the created Eclipse configuration.


Using TestConductor from Rational Quality Manager

TestConductor test cases can be referenced and executed from Rational Quality Manager. A detailed description how to integrate Rational Quality Manager and TestConductor can be found


- For RQM 2.x in the document “RQM_2.0_TestConductorAdapter_HowTo.pdf” in doc/pdfbooks.
- For RQM 3.x in the document “RQMTestConductorAdapter_HowTo.pdf” in doc/pdfbooks.

Automatic Test Case Generation

Rhapsody ATG is the Automatic Test Generation engine in the Rhapsody Testing Environment. The general intention of this tool is to generate test cases in order to thoroughly verify the functionality of the system under test. This capability completes the use cases of Rhapsody® TestConductor™ described above.



An UML model specified in Rhapsody is used as basis for generating the test cases. An in-depth automatic white box model analysis is performed in order to gain detailed knowledge of the internal structure and behavior of the UML model. This knowledge is used for the computation of a large number of test cases. Test cases are sequences of external stimuli and expected system reactions over time. They can be used in order to apply unit testing (class testing) as well as for black box integration testing. Test cases are stored in formats which enable tests to be executed in a wide range of specific target and testing environments.



Features of Rhapsody Automatic Test Generation (ATG):

- ◆ Model-based test case generation for Rhapsody in C++ models
- ◆ Structural testing, also referred to as coverage testing
- ◆ Model coverage, statement coverage, MC/DC coverage
- ◆ Incremental creation of test suites
- ◆ Export of test cases into test formats and testing environments
- ◆ Generation of statistics and reports
- ◆ Easy interfacing with third-party coverage measurement tools

Appendix

TestConductor Assert Macros (C/C++), TestConductor assert methods (Java), TestConductor assert functions (Ada)

As described in chapter Test Case Definition with Code on page 43 and in chapter Test Case Definition with Flow Charts on page 46 and in chapter Test Case Definition with Statecharts on page 50, pre-defined assertion macros are used to get results from a test case execution.

TestConductor defines several assertion macros (C/C++) listed below. Each macro might have one up to four arguments with the following notation:

`n` = Name of the assertion (String, e.g. „Check 1“)

`e`, `e1`, `e2` = Boolean Expression (e.g. `i != 23`)

`p` = text of message printed in the sequence diagram

`sd_instance_name` = Reference to the instance name of the sequence diagram

`msgid` = Reference to the message id of a message in the sequence diagram

- ◆ **RTC_ASSERT(`e`)**
Assertion with default name `e`. The assertion is *PASSED*, if the result of the boolean expression is *TRUE* (`e!=0`), otherwise the assertion *FAILED*.
- ◆ **RTC_ASSERT_FATAL(`e`)**
Assertion with default name `e`. The assertion is *PASSED*, if the result of the boolean expression is *TRUE* (`e!=0`), otherwise the assertion *FAILED*. If it is failed, the test case is aborted immediately without executing further assertions.
- ◆ **RTC_ASSERT_NAME(`n`, `e`)**
Named assertion. The user can define the name of the assertion within the argument `n`. The assertion is *PASSED*, if the result of the boolean expression is *TRUE* (`e!=0`), otherwise the assertion *FAILED*.
- ◆ **RTC_ASSERT_NAME_FATAL(`n`, `e`)**
Named fatal assertion. The user can define the name of the assertion within the argument `n`. The assertion is *PASSED*, if the result of the boolean expression is *TRUE* (`e!=0`), otherwise the assertion *FAILED*. If it is failed, the test case is aborted immediately without executing further assertions.
- ◆ **RTC_ASSERT_SD(`sd_instance_name`, `msgid`, `e`)**
Assertion that can be used within a sequence diagram. If such an assertion is used

in e.g. a driver operation or a stub operation, and `sd_instance_name` refers to a sequence diagram instance, and `msgid` refers to a message id of a message in the sequence diagram of the sequence diagram instance, then the assertion is executed and attached to the specified message.

- ◆ `RTC_ASSERT_SD_NAME(sd_instance_name, msgid, p, e)`
Similar to `RTC_ASSERT_SD`. The user has to define the string argument `p`, which will be concatenated with the result of the assert macro (*PASSED*, *FAILED* etc.) and printed as result message, e.g. “Check of return value failed.”
- ◆ `RTC_ASSERT_TRUE(n, e)`
This assertion is *PASSED*, if `e == TRUE`. Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_FALSE(n, e)`
This assertion is *PASSED*, if `e == FALSE`. Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_EQUAL(n, e1, e2)`
This assertion is *PASSED*, if `e1 == e2`. Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_NOT_EQUAL(n, e1, e2)`
This assertion is *PASSED*, if `e1 != e2`. Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_PTR_EQUAL(n, e1, e2)`
This assertion is *PASSED*, if pointer `e1` and pointer `e2` are equal (`e1 == e2`). Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_PTR_NOT_EQUAL(n, e1, e2)`
This assertion is *PASSED*, if pointer `e1` and pointer `e2` not equal (`e1 != e2`). Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_PTR_NULL(n, e1)`
This assertion is *PASSED*, if the pointer `e1` is `NULL`. Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_PTR_NOT_NULL(n, e1)`
This assertion is *PASSED*, if the pointer is not `NULL`. Otherwise the result of the assertion is *FAILED*.

- ◆ `RTC_ASSERT_CPTRSTRING_EQUAL (n, e1, e2)`
This assertion is *PASSED*, if the string compare is equal (`strcmp (e1, e2) == 0`). Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_CPTRSTRING_NOT_EQUAL (n, e1, e2)`
This assertion is *PASSED*, if the string compare is not equal (`strcmp (e1, e2) != 0`). Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_STRING_EQUAL (n, e1, e2)`
This assertion is *PASSED*, if the comparison of the strings `e1` and `e2` is equal (`e1 == e2`). Otherwise the result of the assertion is *FAILED*.
- ◆ `RTC_ASSERT_STRING_NOT_EQUAL (n, e1, e2)`
This assertion is *PASSED*, if the comparison of the strings `e1` and `e2` is not equal (`e1 != e2`). Otherwise the result of the assertion is *FAILED*.

For Java, `TestConductor` defines several assertion methods in the class `TestConductor`. The following methods are available for Java (the semantics is analogues to the C/C++ macros):

- ◆ `public static void ASSERT_NAME(String n, boolean p)`
- ◆ `public static void ASSERT_SD(String s, String n, boolean p)`
- ◆ `public static void ASSERT_SD_NAME(String s, String n, String m, boolean p)`
- ◆ `public static void ASSERT(boolean e)`
- ◆ `public static void ASSERT_TRUE(String n, boolean e)`
- ◆ `public static void ASSERT_FALSE(String n, boolean e)`
- ◆ `public static void ASSERT_EQUAL(String n, boolean e1, boolean e2)`
- ◆ `public static void ASSERT_NOT_EQUAL(String n, boolean e1, boolean e2)`
- ◆ `public static void ASSERT_STRING_EQUAL(String n, String e1, String e2)`
- ◆ `public static void ASSERT_STRING_NOT_EQUAL(String n, String e1, String e2)`

For Ada, `TestConductor` defines several assertion procedures in the package `TestConductor`. The following procedures are available for Ada (the semantics is analogues to the C/C++ macros):

- `procedure ASSERT_NAME(n : in String; p : in BOOLEAN; sfile : String := File; iline : integer := Line);`

- `procedure ASSERT_NAME_FATAL(n : in String; p : in BOOLEAN; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_SD(s : in String; n : in String; p : in BOOLEAN; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_SD_NAME(s : in String; n : in String; m : in String; p : in BOOLEAN; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT(e : in BOOLEAN; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_TRUE(n : in String; e : in boolean; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_FALSE(n : in String; e : in boolean; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_EQUAL(n : in String; e1 : in boolean; e2 : in boolean; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_NOT_EQUAL(n : in String; e1 : in boolean; e2 : in boolean; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_STRING_EQUAL(n : in String; e1 : in String; e2 : in String; sfile : String := File; iline : integer := Line);`
- `procedure ASSERT_STRING_NOT_EQUAL(n : in String; e1 : in String; e2 : in String; sfile : String := File; iline : integer := Line);`


Using IntelliVisor for TestConductor Assert Macros

TestConductor supports the usage of the IntelliVisor functionality of Rhapsody. To be able to use this for the defined TestConductor Assert Macros, you have to prepare Rhapsody's site.prp file. Please do the following steps:

- ◆ Close Rhapsody if it is open.

- ◆ Copy the file rtc.prp from the ..\TestConductor folder to the ..\Share\Properties folder of your Rhapsody installation.
- ◆ Open the site.prp file and add Include "rtc.prp".
- ◆ Save the site.prp file and open Rhapsody.

Using Ctrl+Space in a code based test case definition (Flowchart TestCase or Code TestCase) the known IntelliVisor list box opens. With the modifications above you are able to select one of the defined TestConductor Assert Macros. Selecting one of the macros also shows a hint that gives you information about the parameters of the macro.



A double-click on the macro adds this to the code. For example you have chosen the RTC_ASSERT_NAME macro the following code will be added:

```
RTC_ASSERT_NAME("assertion name", bool-expr);
```

Now you have to replace the string "assertion name" and the expression to that expression you want to check.

Syntax for Activation Conditions / Condition Marks

TestConductor uses the following scheme of event activation conditions:

```
ObjectName1->eventAction (ObjectName2, eventName)
```

The scheme of a state activation condition can be represented as follows:

```
ObjectName->stateAction (stateName)
```

The scheme of a method activation condition is as follows:

```
ObjectName1->methodAction (ObjectName2, methodName)
```

In this syntax:

- ◆ eventAction is EventSent or EventReceived
- ◆ stateAction is StateEntered, StateExited or IsIn
- ◆ methodAction is MethodCalled or MethodReturned

Note: The syntax of the activation condition is case sensitive. TestConductor checks only the syntax and not for static semantics.

For example:

- ◆ PBX[0]->itsLine[0]->EventSent (PBX[0]->itsTelephone[0], evRing())
This activation condition is TRUE at the moment when object PBX[0]->itsLine[0] sends the event evRing() to object PBX[0]->itsTelephone[0]. In a sequence diagram, this corresponds to the origin of the message arrow.
- ◆ PBX[0]->itsLine[0]->EventReceived (PBX[0]->itsTelephone[0], evDialTone())
This activation condition is TRUE at the moment when the object PBX[0]->itsTelephone[0] receives the event evDialTone() from object PBX[0]->itsLine[0]. In a sequence diagram, this corresponds to the end point of the message arrow.
- ◆ line->MethodCalled (callRouter, OpenConnection())
The activation condition is TRUE at the moment when the line object calls the OpenConnection() method of the callRouter object.
- ◆ line->MethodReturned (callRouter, OpenConnection())
The activation condition is TRUE at the moment when the callRouter object returns the OpenConnection() operation call to the line object.
- ◆ telephone->StateEntered (ROOT.Ready.Calling)
The activation condition is TRUE at the moment when object telephone enters its "Calling" state chart state.

- ◆ `telephone->StateExited(ROOT.Ready.Calling)`
The activation condition is `TRUE` at the moment when the telephone object exits its “Calling” state chart state.
- ◆ `telephone->IsIn(ROOT.Ready.Calling)`
The activation condition is `TRUE` as long as the telephone object is in its “Calling” state chart state.

Note: You must specify the full state chart state name (the state path), e.g. “`ROOT.Ready.Calling`.” You can combine these expressions with `AND`, `OR`, and `NOT`.

For example:

```
(NOT (callersLine->EventReceived(caller, evRing()))) OR
(caller->StateEntered(ROOT.Ready.Idle))
```

Do not use two different event conditions with the conjunction `AND` as a combined activation condition. Such expressions can never have the value `TRUE`, because TestConductor and the Rhapsody animation tool work sequentially. At most, one event can be sent or received at every point in time. In addition, be careful when combining several state conditions by the conjunction `AND`: every object can stay in one “basic” state at every point in time, if its state chart does not contain a hierarchical state with orthogonal components. In addition, you can use the name `ENV` as an object name to specify event sending to and receiving from the system’s environment.

Activation conditions use the following shortcuts:

- ◆ `ES` for `EventSent`; `ER` for `EventReceived`
- ◆ `MC` for `MethodCalled`; `MR` for `MethodReturned`
- ◆ `SE` for `StateEntered`; `SX` for `StateExited`; `II` for `IsIn`

TestConductor Messages

Errors/Warnings regarding messages in Sequence Diagrams

Some sequence diagram features are not supported by TestConductor. They will be ignored and a warning comes up, but the test will be executed.

- ◆ Timeouts will be ignored.
- ◆ Cancelled timeouts will be ignored.
- ◆ Reply messages will be ignored.
- ◆ Execution occurrences will be ignored.
- ◆ Rhapsody in C initializers will be ignored.
- ◆ Rhapsody in C++/ Rhapsody in Java constructors will be ignored.
- ◆ Rhapsody in C cleanup operations will be ignored.
- ◆ Rhapsody in C++/ Rhapsody in Java destructors will be ignored.
- ◆ <name> : Unspecified messages will be ignored.
- ◆ <name> : Unrealized messages to an internal instance will be ignored.
- ◆ Messages with wrong syntax will also be ignored in test execution:
- ◆ Condition : <name> is not a valid expression.
- ◆ Time interval with a lower bound of 0 will be ignored.
- ◆ Time intervals are only supported on system border. Other time intervals will be ignored.
- ◆ <name> : Wrong syntax of time interval. Time interval will be ignored.
- ◆ Time intervals are only allowed for driver or black box tests. In monitor tests time intervals will be ignored.
- ◆ <name> : Method not supported by method broker. Remove message from sequence diagram. (only Rhapsody in Java)

Errors Regarding Complete Sequence Diagrams and Test (test will not be executed)

In Rhapsody in Java a method broker is needed to drive operation calls/triggered operations. If there is no method broker in the model or if the method broker is not valid anymore due to changes in the model, the test will not be executed.

- ◆ Sequence diagram contains operation calls from environment (only for Rhapsody in Java).
You must create a method broker in order to run this test. Please press "Create MethodBroker" in the TestConductor dialog to create a MethodBroker and rebuild your active configuration.
- ◆ Sequence diagram contains operation calls from environment (only for Rhapsody in Java).
The MethodBroker for the active configuration is not valid any more. Please press "Create MethodBroker" in

the TestConductor dialog to create a new MethodBroker and rebuild your active configuration.

- ◆ In a black box test only messages from or to the system border are used for the test. If a sequence diagram only has internal or unsupported messages, a black box test will not be executed.
SD has only internal Messages or unsupported elements.
Black-Box test will not be executed.
- ◆ If a sequence diagram is empty or only has unsupported messages, the test will not be executed
SD contains only unsupported elements. Compilation aborted. SD without any constructs is not supported.
- ◆ In some cases executing a test with a sequence diagram which has more than 2000 messages leads to a crash due to a small stack size. In this case, please refer to the release notes how to increase the stack size of your system.
Due to the actual size of this SD, test execution can lead to a crash. In such a case, please contact support to get a patch or refer to the release notes and use the mentioned workaround.
- ◆ If two messages of a sequence diagram start/end at the same point TestConductor can not get correct information about the messages so the compilation fails. If this happens, make sure that there is only one message starting/ending on each message point.
TEST: <name>
Sequence Diagram: <name>
ERROR: Compilation error - Test will not be executed.
This error can have different reasons. Known reasons are:
 - Sequence Diagram contains a time interval beginning or ending on other message points.
 - Sequence Diagram contains unspecified messages.
- ◆ If the activation condition of a test has the wrong syntax the test will not be executed.
TEST: <name>
Sequence Diagram: <name>
ERROR: Syntax error in activation condition
<ActivationCondition>
- ◆ Another message arrow detected between start point and end point of operation.
TEST: <name>
Sequence Diagram: <name>
Another message arrow detected between start point and end point of
Operation <name>.
This is not supported by TestConductor.
To execute the test, please move start/end points of other messages above or below the message arrow of

<name>.

- ◆ If there is an unspecified message in the specification sequence diagram
<Message_name>: Unrealized Messages to an internal instance will be ignored.
- ◆ If there is an unrealized message in the specification sequence diagram
<Message_name>: Messages with Stereotype <unrealized> will be ignored.
- ◆ If the specification sequence diagram has an unspecified class
TEST: <test_name>
Sequence Diagram: <name>
Class of Instance <class_name> is unspecified. Test will not be executed.

Restrictions

TestConductor supports Rhapsody in C/C++/Java/Ada with its existing and with its new features. The most important limitations are:

- ◆ Assertion based testing mode is only supported for RhapsodyC and RhapsodyC++.
- ◆ Code coverage computation with TestConductor is only supported for RhapsodyC.
- ◆ Code, flow chart (only C/C++), and statechart test cases only for Rhapsody in C/C++/Java/Ada
- ◆ Automatic sequence diagram based model population for test components only for Rhapsody in C++, C, Java and Ada
- ◆ Black box production code test case execution only for Rhapsody in C++ and C
- ◆ OfflineTesting only for Rhapsody in C/C++
- ◆ Code Coverage Computation with Test RealTime integration only for C/C++

Limitations of design elements (sequence diagrams)

Currently, TestConductor does not support the following sequence diagram features:

- ◆ Create arrow
- ◆ Destroy arrow
- ◆ Reply message
- ◆ Timeout
- ◆ Cancelled timeouts
- ◆ Constraints
- ◆ Language for condition marks

Condition marks must obey the same syntax as activation conditions. Currently, simple expressions with equality or inequality are not yet allowed in activation conditions and condition marks.

Note: TestConductor will ignore condition marks during test execution when the syntax of the condition mark is not valid.

If you use these unsupported features in a sequence diagram, TestConductor ignores them during test execution.

Functional Limitations

All TestConductor features are available for Rhapsody in C++, C, Java and Ada. Rhapsody Automatic Test Generation (ATG) is only available for Rhapsody in C++. For TestConductor, the most important limitations are

- ◆ Code, flow chart (only C/C++), and statechart test cases only for Rhapsody in C/C++/Java/Ada.
- ◆ Automatic sequence diagram based model population (automatic generation of driver and stub operations) for test components only for Rhapsody C/C++/Java/Ada.
- ◆ Black box production code test case execution only for Rhapsody in C/C++.
- ◆ OfflineTesting only for Rhapsody in C/C++.
- ◆ Full automatic test architecture support only for Rhapsody in C/C++/Java/Ada.

Beside the listed important limitation there are some other know limitations:

- ◆ Obsolete profiles (ATGProfile, TestingProfile_CPP, TestingProfile_C, TestingProfile_Java, TestingProfile_Ada) must be deleted from models manually.
- ◆ The “Update” functionality available in the context menu of a test package, test context and test case as well as “**Create Flowchart TestCase**“, “**Create Code TestCase**”, “**Create Statechart TestCase**” for a test context is only applicable to Rhapsody in C/C++/Java/Ada. The context menu entries are enabled for other languages, but TestConductor will raise a warning dialog or a warning message in this case.
- ◆ Only virtual operations can be stubbed.
- ◆ TestConductor cannot generate stubs for triggered operations.
- ◆ TestConductor cannot generate stubs, if the signature of overwritten operations in an inheritance hierarchy do not syntactically match to the related operation in the base class (for instance, due to different typedef-types to the same base type)
- ◆ The auto-generated code for driver- or stub-operations could be semantically incorrect, if non-default values for the properties `CPP_CG:: {Class, Type}:: {In, Out, InOut}` are used. Note that incorrectly generated code could be overwritten by setting the tag `RTC_DriverCallCode`, `RTCDriverInitCode` respectively `RTC_StubBodyCode`.
- ◆ If a TestComponent instance is linked to a SUT using a qualified association relation, Rhapsody does not generate code to implement the link. TestConductor can not generate driver operations for messages, which use such a link.
- ◆ Building SUT for black-box testing requires an animation property change in the design model.

- ◆ Auto created operations are not animated and cannot be used in test cases: due to a limitation in the Rhapsody animation, auto generated operations like getter/setter for class attributes are not animated during execution, they do not appear in animated sequence diagrams and observers don't get notifications about these messages (even if the property `CG:CGGeneral:GeneratedCodeInBrowser` is set to `true`).